Platform Documentation

ProVision

Application Version 7.4.0 / 7.4.1

Covering:

- Installation Guide
- Getting Started
- User Guide
- Admin Guide
- Developer Tools
- Help & Support

For additional information, please visit https://docs.6connect.com or contact 6connect at support@6connect.com

1. Home . . . 5
1.1 ProVision Installation Guide . . . 8
1.1.1 Hosted Instances Guide . . . 9
1.1.2 Local / VM Installation Guide . . . 10
1.1.2.1 System Requirements . . . 11
1.1.2.2 Backup and Redundancy: Local / VM . . . 13
1.1.2.3 ProVision Local Installation For CentOS 6 . . . 14
1.1.2.4 ProVision Local Installation For CentOS 7 . . . 20
1.1.2.5 ProVision Local Installation For Debian 7/8 . . . 26
1.1.2.6 ProVision Local Installation For Ubuntu . . . 30
1.1.2.7 6connect Local Software Upgrades . . . 35
1.1.2.8 Local Installations - Peering Setup . . . 36
1.1.2.9 Local Installations - Master-Master Replication . . . 38
1.1.3 ESXi VM Image Setup . . . 43
1.2 ProVision Getting Started . . . 45
1.2.1 First Steps . . . 46
1.2.2 Resource Concepts . . . 52
1.2.3 Workflow Concepts . . . 56
1.3 ProVision User Guide . . . 77
1.3.1 The Dashboard . . . 78
1.3.1.1 Customizing the Dashboard . . . 82
1.3.1.2 Working with Dashboard Widgets . . . 86
1.3.2 Working with Resources . . . 100
1.3.2.1 Working with Entries . . . 102
1.3.2.2 Customizing Sections . . . 114
1.3.2.3 Customizing Fields . . . 118
1.3.2.4 Customizing Resource Lists . . . 123
1.3.2.5 Gadgets . . . 137
1.3.2.5.1 XML Specifications . . . 165
1.3.2.6 Contact Manager . . . 167
1.3.3 DNS Tab . . . 176
1.3.3.1 Working with DNS Groups . . . 181
1.3.3.2 Editing DNS Zones . . . 198
1.3.3.3 Working with DNS Zones - Common Tasks . . . 207
1.3.3.4 Working with DNS Records . . . 219
1.3.4 DHCP Tab . . . 227
1.3.4.1 Working with DHCP Groups . . . 229
1.3.4.2 Working with DHCP Pools . . . 241
1.3.4.3 Working with DHCP Gadgets . . . 254
1.3.5 IPAM Tab . . . 267
1.3.5.1 Working with IP Aggregates . . . 280
1.3.5.2 Working with IP Blocks . . . 291
1.3.5.3 Working with IP Rules . . . 316
1.3.5.4 VLAN . . . 322
1.3.5.4.1 Working with Domains . . . 338
1.3.5.4.2 Working with the VLAN Manager . . . 346
1.3.6 Peering v2 . . . 359
1.3.6.1 Peering Exchanges . . . 368
1.3.6.2 Peering Routers . . . 374
1.3.6.3 Peering Sessions . . . 378
1.3.6.4 Managing Peers . . . 382
1.3.6.5 Peering Emails . . . 389
1.3.6.6 Peering Templates . . . 396
1.3.7 Reporting . . . 403
1.3.7.1 Working with Reports . . . 411
1.3.8 User Preferences . . . 421
1.4 ProVision Admin Guide . . . 422
1.4.1 Admin Preferences . . . 423
1.4.2 Authentication Options . . . 440
1.4.2.1 LDAP Authentication . . . 441
1.4.2.2 LDAP Authentication on Windows Server . . . 444
1.4.2.3 RADIUS Authentication . . . 448
1.4.3 IPAM Administration . . . 450
1.4.3.1 IPAM Parameters . . . 452
1.4.3.2 IPAM Rules . . . 463
1.4.3.3 Holding Tank Management . . . 468
1.4.3.4 RIR Integration: SWIP/RPSL . . . 473
1.4.3.5 LIR Management and Use . . . 477
1.4.3.5.1 ARIN LIR Setup and Use . . . 482
1.4.3.5.2 RIPE LIR Setup and Use . . . 487
1.4.3.5.3 LIR Walkthrough . . . 491
1.4.4 DNS Administration . . . 496
1.4.4.1 Working with DNS Servers . . . 505
1.4.4.2 Configuring ISC BIND Support . . . 515
1.4.4.3 Configuring PowerDNS Support . . . 519

1.4.4.4 Configuring Secure64 Support . . . 523
1.4.4.5 Configuring Route53 Support . . . 530
1.4.4.6 Configuring Split Horizon/Views . . . 534
1.4.4.7 Configuring DNSSEC . . . 539
1.4.5 DHCP Administration . . . 543
1.4.5.1 Working with DHCP Servers . . . 546
1.4.6 Importing Your Data . . . 556
1.4.6.1 Resource Import from CSV . . . 562
1.4.6.2 Resource Import Tool . . . 568
1.4.6.2.1 Resource Importer Walkthrough - Step 1 . . . 571
1.4.6.2.2 Resource Importer Walkthrough - Step 2 . . . 573
1.4.6.2.3 Resource Importer Walkthrough - Step 3 . . . 575
1.4.6.2.4 Resource Importer Walkthrough - Step 4 . . . 576
1.4.6.2.5 Resource Importer Walkthrough - Step 5 . . . 580
1.4.6.2.6 Resource Importer Walkthrough - Step 6 . . . 581
1.4.6.3 Import Sessions . . . 584
1.4.6.4 IP Import from CSV . . . 588
1.4.6.5 Import Aggregate Blocks . . . 595
1.4.6.6 Import DNS Zones . . . 598
1.4.6.6.1 BIND DNS Zone Upload / Import . . . 602
1.4.6.6.2 PowerDNS Zone Import . . . 607
1.4.6.6.3 InfoBlox Zone Import . . . 609
1.4.6.6.4 NS One Zone Import . . . 612
1.4.6.6.5 Dyn DNS Zone Import . . . 615
1.4.6.6.6 DNSMadeEasy Zone Import . . . 618
1.4.6.6.7 IPPLAN Zone Import . . . 621
1.4.7 Users & Permissions . . . 623
1.4.7.1 Global Permissions . . . 626
1.4.7.2 Resource Permissions . . . 628
1.4.7.3 Users and Groups . . . 630
1.4.7.4 Verifying Permissions . . . 636
1.4.8 API Tab . . . 638
1.4.8.1 Reverse API 1 . . . 640
1.4.9 Scheduler . . . 644
1.4.10 Log . . . 651
1.4.11 Approvals . . . 656
1.4.11.1 Pending Approvals . . . 669
1.4.11.2 Approval Permission Groups . . . 678
1.4.12 Constraints . . . 690
1.5 ProVision Developer Tools . . . 703
1.5.1 APIv2 . . . 706
1.5.2 API v1 . . . 713
1.5.2.1 API Module - Admin and Audit . . . 717
1.5.2.1.1 Authentication Testing . . . 718
1.5.2.1.2 Backup . . . 720
1.5.2.1.3 Log Management . . . 721
1.5.2.1.4 Scheduler 1 . . . 723
1.5.2.1.5 Zone Templates . . . 727
1.5.2.2 API Module - DHCP . . . 729
1.5.2.2.1 API Module - DHCPv2 . . . 734
1.5.2.3 API Module - DNS . . . 744
1.5.2.4 API Module - IPAM . . . 767
1.5.2.5 API Module - LIR . . . 787
1.5.2.6 API Module - Peering . . . 794
1.5.2.7 API Module - Resource . . . 803
1.5.2.8 API Module - VLAN . . . 812
1.5.2.9 3 - SDK . . . 820
1.5.2.10 How Do I... . . . 823
1.5.3 Portable Gadgets . . . 833
1.5.3.1 Getting Started With Portable Gadgets . . . 841
1.5.3.2 Portable Gadget Customization . . . 844
1.5.4 Reverse API . . . 846
1.5.4.1 Reverse API - Detail . . . 848
1.5.5 Toolkit . . . 852
1.5.5.1 IPPlan Importer . . . 856
1.5.6 CLI (Alpha) . . . 859
1.5.7 Resource Concepts 1 . . . 860
1.5.7.1 Resource Classes Doc . . . 861
1.5.7.2 Database Layout 1 . . . 863
1.5.7.3 Asset System . . . 865
1.6 Help & Support . . . 867
1.6.1 Tutorials . . . 868
1.6.1.1 Common Tasks . . . 869
1.6.1.2 UI Tours . . . 870
1.6.2 FAQ . . . 872

1.6.3 Additional Resources . . . 875
1.6.3.1 Import Templates . . . 876
1.6.3.2 List of Abbreviations . . . 877
1.6.4 Feedback and Feature Requests . . . 878
1.7 6connect Scanlet (Beta) . . . 879
1.8 Release Notes . . . 883
1.8.1 ProVision 7.4.0 . . . 885
1.8.2 ProVision 7.3.0 . . . 903
1.8.2.1 ProVision 7.3.1 . . . 939
1.8.3 ProVision 7.2.0 . . . 940
1.8.3.1 ProVision 7.2.1 . . . 966
1.8.4 ProVision 7.1.0 . . . 969
1.8.4.1 ProVision 7.1.1 . . . 990
1.8.5 ProVision 7.0.0 . . . 992
1.8.5.1 ProVision 7.0.2 . . . 1019
1.8.5.2 ProVision 7.0.1 . . . 1020
1.8.6 ProVision 6.1.0 . . . 1022
1.8.6.1 ProVision 6.1.2 . . . 1026
1.8.7 ProVision 6.0.0 . . . 1027
1.8.7.1 ProVision 6.0.2 . . . 1039
1.8.7.2 ProVision 6.0.1 . . . 1040
1.8.8 ProVision 5.3.0 . . . 1042
1.8.8.1 ProVision 5.3.2 . . . 1048
1.8.8.2 ProVision 5.3.1 . . . 1050
1.8.9 ProVision 5.2.0 . . . 1054
1.8.9.1 ProVision 5.2.2 . . . 1061
1.8.9.2 ProVision 5.2.1 . . . 1062
1.8.10 ProVision 5.1.0 . . . 1063
1.8.10.1 ProVision 5.1.4 . . . 1074
1.8.10.2 ProVision 5.1.3 . . . 1075
1.8.10.3 ProVision 5.1.2 . . . 1087
1.8.10.4 ProVision 5.1.1 . . . 1092
1.8.11 ProVision 5.0.0 . . . 1093
1.8.11.1 ProVision 5.0.4 . . . 1100
1.8.11.2 ProVision 5.0.3 . . . 1105
1.8.11.3 ProVision 5.0.2 . . . 1106
1.8.11.4 ProVision 5.0.1 . . . 1108
1.8.12 ProVision 4.2.0 . . . 1109
1.8.12.1 ProVision 4.2.1 . . . 1110
1.8.13 ProVision 4.1.0 . . . 1113
1.8.13.1 ProVision 4.1.23 . . . 1118
1.8.13.2 ProVision 4.1.22 . . . 1119
1.8.13.3 ProVision 4.1.21 . . . 1120
1.8.13.4 ProVision 4.1.20 . . . 1122
1.8.13.5 ProVision 4.1.19 . . . 1123
1.8.13.6 ProVision 4.1.18 . . . 1126
1.8.13.7 ProVision 4.1.17 . . . 1127
1.8.13.8 ProVision 4.1.16 . . . 1128
1.8.13.9 ProVision 4.1.15 . . . 1129
1.8.13.10 ProVision 4.1.14 . . . 1130
1.8.13.11 ProVision 4.1.13 . . . 1131
1.8.13.12 ProVision 4.1.12 . . . 1132
1.8.13.13 ProVision 4.1.11 . . . 1133
1.8.13.14 ProVision 4.1.10 . . . 1134
1.8.13.15 ProVision 4.1.9 . . . 1135
1.8.13.16 ProVision 4.1.8 . . . 1137
1.8.13.17 ProVision 4.1.7 . . . 1138
1.8.13.18 ProVision 4.1.6 . . . 1139
1.8.13.19 ProVision 4.1.5 . . . 1140
1.8.13.20 ProVision 4.1.4 . . . 1141
1.8.13.21 ProVision 4.1.3 . . . 1142
1.8.13.22 ProVision 4.1.2 . . . 1143
1.8.13.23 ProVision 4.1.1 . . . 1144
1.8.14 ProVision 4.0.0 . . . 1145
1.8.15 ProVision 3.9.0 . . . 1148
1.8.15.1 ProVision 3.9.3 . . . 1149
1.8.15.2 ProVision 3.9.2 . . . 1150
1.8.15.3 ProVision 3.9.1 . . . 1151
1.8.16 ProVision 3.8.0 . . . 1153
1.8.17 ProVision 3.7.0 . . . 1154
1.8.18 ProVision 3.6.0 . . . 1155
1.8.19 ProVision 3.5.0 . . . 1156
1.8.20 ProVision 3.4.0 . . . 1157
1.8.21 ProVision 3.3.0 . . . 1158
1.8.22 ProVision 3.2.0 . . . 1159

1.8.23 ProVision 3.0.0 1160
1.8.24 ProVision 2.5 1161
1.9 Coming Soon 1162
1.10 ProVision Plugins 1164
1.10.1 ProVision-vRA-Plugin 1165

Home

ProVision Support Documentation

Documentation provided is for the most current release. For previous versions, see "Documentation for Previous Versions" below.

Expand all Collapse all

Documentation for Previous Versions

Confluence Spaces

The links below provide archive online snapshots of final documentation for previous major versions, as well as the most recent prior version.

Documentation v7.3.0 / 7.3.1

Documentation v7.2.0 / 7.2.1

Documentation v7.1.0 / 7.1.1

Documentation v7.0.0 / 7.0.1

Documentation v6.0.0 / 6.1.1

Documentation v5.3.0

Documentation v5.2.0

Documentation v5.1.0

Additional Confluence documentation for minor releases may be available upon request for limited time periods.

For assistance, contact our support team at support@6connect.com with your request.

PDF Documentation

The links below provide compressed .pdf's of archive documentation snapshots for available ProVision versions. Combined Major-Minor version pdf booklets may be used for patch releases that immediately follow a major release.

Expand the link below and click on the desired version number to being downloading the file. Once downloaded, be sure to extract / unzip the file to your desired save location.

File	Modified

ZIP Archive 6connect-ProVision-v7.3.0-7.3.1_Manual.pdf.zip 7.3.0 / 7.3.1 Release: 2020-02-17	Feb 24, 2020 by The Force
ZIP Archive 6connect-ProVision-v7.2.0-7.2.1_Manual.pdf.zip 7.2.0 / 7.2.1 Release 2019-09-13-. Archived: 2020-02-24	Feb 24, 2020 by The Force
ZIP Archive 6connect-ProVision-v7.1.0-7.1.1_Manual.pdf.zip 7.1.0 / 7.1.1 Release	Apr 19, 2019 by The Force
ZIP Archive 6connect-ProVision-v7.0.0-7.0.1_Manual.pdf.zip 7.0.0/7.0.1 Release - 2018-07-20	Jul 23, 2018 by The Force
ZIP Archive 6connect-ProVision-v6.1.1_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v6.0.2_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v6.0.1_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v6.0.0_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.3.2_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.3.1_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.3.0_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.2.2_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.2.1_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.2.0_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.1.4_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.1.3_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.1.2_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.1.1_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.1.0_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.0.4_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.0.3_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v5.0.1_Manual.pdf.zip	Jun 14, 2018 by The Force
ZIP Archive 6connect-ProVision-v4.2.1_Manual.pdf.zip	Jun 14, 2018 by The Force

	ZIP Archive 6connect_ProVision-v4.1.6_Manual.pdf.zip	Jun 14, 2018 by The Force
	ZIP Archive 6connect_ProVision-v4.1.15_Manual.pdf.zip	Jun 14, 2018 by The Force
	ZIP Archive 6connect_ProVision-v4.1.0_Manual.pdf.zip	Jun 14, 2018 by The Force
	ZIP Archive 6connect_ProVision-v4.0.7_Manual.pdf.zip	Jun 14, 2018 by The Force
	ZIP Archive 6connect_ProVision-v4.0.0_Manual.pdf.zip	Jun 14, 2018 by The Force
	ZIP Archive 6connect_ProVision-v3.9.3_Manual.pdf.zip	Jun 14, 2018 by The Force

Download All

Please keep in mind that as the provided pdfs are snapshots, documentation changes are not retroactively applied. Edits and corrections to documentation may exist in subsequent versions.

Recent space activity



The Force
Constraints created Aug 13, 2020
ProVision 7.4.0 created Aug 12, 2020
Approvals created Aug 10, 2020
Approval Permission Groups created Aug 10, 2020
Scheduler created Aug 10, 2020

Space contributors

- The Force (4 days ago)
- 6c Ops (77 days ago)
- Pete Sclafani (105 days ago)

ProVision Installation Guide

Installing ProVision



You have 6connect ProVision and now it's time to set it up! 6connect offers both cloud hosted instances and local installations of ProVision. Follow the links below for specific instructions on each instance type.

For setup assistance or additional information, you can contact our support team at support@6connect.com.

Table of Contents

- Hosted Instances Guide
- Local / VM Installation Guide
- ESXi VM Image Setup

Hosted Instances Guide

Hosted Instances Guide

With a cloud hosted instance of ProVision, all you need is one of the following web browsers with an internet connection and login credentials!

Once you have confirmed that you have a supported browser and valid login, you can proceed to ProVision Getting Started, the ProVision User Guide, or the ProVision Admin Guide to learn more about ProVision.

- Hosted Instances Guide
  - 6connect Cloud Hosted Instance: Browser Requirements
  - Backup and Redundancy

6connect Cloud Hosted Instance: Browser Requirements

6connect makes every effort to maintain broad compatibility across browser vendors and versions.
Web Browsers Supported:

- Firefox, Safari, Chrome, Microsoft Edge (current versions).

Backup and Redundancy

Backup Schedule

Both local and hosted instances are provided with a default Scheduler task to perform a backup every 24 hours, with a 1 month retention policy.

Restoration
Is a phone call or email away. We can spin up a new instance with your preferred data set.

Local / VM Installation Guide

Installing ProVision

Local and VM installs of ProVision have specific requirements and configuration settings. Please follow the links below for detailed instructions on how to set up your local installation of ProVision.

For setup assistance or additional information, you can contact our support team at support@6connect.com.

Table of Contents

- System Requirements
- Backup and Redundancy: Local / VM
- ProVision Local Installation For CentOS 6
- ProVision Local Installation For CentOS 7
- ProVision Local Installation For Debian 8
- ProVision Local Installation For Ubuntu
- 6connect Local Software Upgrades
- Local Installations: Peering Setup
- Local Installations: Master-Master Replication

System Requirements

ProVision System Requirements

- ProVision System Requirements
  - 6connect Locally Hosted Instance
    - Hardware Requirements:
    - Software Requirements:
    - Port Requirements:

6connect Locally Hosted Instance

Initial application installation is included with the purchase of a license from 6connect. If modifications need to be made, we recommend contacting 6connect prior to any changes to ensure there is no negative impact to production systems or product functionality.

Hardware Requirements:

The optimum resource mix will be based on page views/refreshes. A larger concurrent user base with constant editing may benefit from additional RAM.
The minimum recommended hardware is:

	Minimum	Recommended
Processor	Dual-core Xeon class processor or equivalent	Quad-core Xeon
RAM	2GB RAM	4GB RAM
Storage	20 GB	100GB

*Virtual instances are also acceptable. We have confirmed functionality with Citrix Xen Essentials, VMware, KVM, etc.

6connect, Inc. will support customers who run 6connect ProVision products on supported Operating Systems, irrespective of whether they are running in VMware environments or not. 6connect, Inc. supports Operating Systems, not specific hardware configurations. Accordingly, VMware operates as a hardware abstraction layer.

VMware supports a set of certified Operating Systems and Hardware, and the customer and VMware will be responsible for any interactions or issues that arise at the Hardware or Operating System layer as a result of their use of VMware.

6connect, Inc. will not require clients to recreate and troubleshoot every issue in a non-VMware environment; however, 6connect, Inc. does reserve the right to request our customers to diagnose certain issues in a native certified Operating System environment, operating without the virtual environment. 6connect, Inc. will only make this request when there is reason to believe that the virtual environment is a contributing factor to the issue.

Any time spent on investigation of problems that may, in the sole opinion of 6connect, Inc. be related to VMware, will be handled in the following fashion:

1) 6connect, Inc. will provide standard support to all 6connect ProVision products.

2) If a problem is encountered while 6connect ProVision is/are running in a VMware environment, the client may be required to recreate the problem on a non-VMware server unit, at which time 6connect, Inc. will provide regular support.

3) The client can authorize 6connect, Inc. to investigate the VMware related items at normal time and materials rates. If such investigation shows that the problem is VMware related, the client may contract 6connect, Inc. to provide a software change to resolve the issue if such a resolution is possible.

4) Regardless of the problem type or source, if the problem is determined to be a non VMware related issue - time spent on investigation and resolution will be covered as part of regular maintenance, and support will be provided as usual.

Software Requirements:

Base Software Needed:

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	PHP 7.1.x	http://php.net/downloads.php
MySQL	MySQL 5.7	http://www.mysql.com/downloads/

MySQL Triggers

6connect does not support custom MySQL triggers at this time - please email support@6connect.com if you have any questions.

MySQL Packet Size Configuration

We recommend increasing the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Port Requirements:

Open outbound ports 443 and port 80

- cloud.6connect.com is used for license check
- checkip.dyndns.org validates the IP address of the machine to communicate with the licensing server

The ProVision DNS Module also supports zone checks on attached DNS Server(s) as an external user. Port 53 will need to be open and usable for ProVision to query the servers. If not, zone error checking and verification will not work as intended.

Depending on the Connectors in use, there may be other port requirements needed. Port 22 (SSH) is used extensively for control of downstream devices.

Backup and Redundancy: Local / VM

Backup and Redundancy

Local/VM Instance

Backup Schedule
Both local and hosted instances are provided with a default Scheduler task to perform a backup every 24 hours, with a 1 month retention policy.

Restoration
Is a phone or email away. We can spin up a new instance with your preferred data set, or send you a link to download your database. Optionally, we can even help you set it up and import your data to your new instance or assist with redundant configuration options depending on your RPO /RTO guidelines.

Backup your Data



For local customers, you should be backing up the following items:

mysqldump

And system folders off the 6connect root:

/scans

/zones

/keys

/archive

/data

ProVision Local Installation For CentOS 6

CentOS 6

- CentOS 6
- Before You Begin
- Install Requirements
    - 1) Upgrade your current packages
    - 2) Install Required Packages
        - PHP
        - MySQL
        - DNS and Additional Utilities
    - 3) Configuring the requirements:
        - SSL
        - Apache
        - MySQL
    - 4) Optional configurations:
        - Configure SELinux
        - Configure IPTables
        - Radius (Optional)
        - SSH
    - 4) Install 6connect ProVision Software:

Before You Begin

Ensure that System Requirements have been met prior to proceeding with the CentOS Configuration Guide.

Install Requirements

1) Upgrade your current packages

Upgrade your current packages.

```
yum update
```

2) Install Required Packages

PHP

Installations of ProVision 7.x and newer require PHP 7.1 (and related extensions). CentOS 6 comes with PHP 5.3 by default. You can either add a repository which provides PHP 7.1 or install PHP manually.

Repository & Syntax



The Webtatic and Remi repos both have versions of PHP which are newer than those in the official repos. For this example, we'll be using Webtatic.

If using a different repo or installing manually, your installation syntax may be different from what is listed here.

Add the repository:

```
rpm -Uvh https://mirror.webtatic.com/yum/el6/latest.rpm
```

Update:

```
yum update
```

Install:

PHP 7.x / Apache2 / extensions

- httpd
- php71w
- php71w-opcache
- php71w-mysqlnd
- php71w-pdo
- php71w-ldap
- php71w-pecl-memcache
- php71w-bcmath
- php71w-devel
- php71w-pear
- php71w-cli
- php7.1-imap

Development tools for pecl / additional system packages:

- curl
- openssl
- memcached
- mod_ssl

```
yum install httpd php71w php71w-opcache php71w-mysqlnd php71w-pdo php71w-ldap php71w-pecl-memcache php71w-
bcmath php71w-devel php71w-pear php71w-cli php7.1-imap curl openssl memcached mod_ssl
```

MySQL

Install MySQL 5.7 to use a local database.

MySQL is included with most CentOS installs, check for it with:

```
yum list installed | grep mysql
```

The default MySqL version included with most CentOS installs will need to be upgraded to the latest version:

```
rpm -Uvh https://mirror.webtatic.com/yum/el6/latest.rpm
```

If you have an existing installation, you can replace it with:

```
yum install mysql.`uname -i` yum-plugin-replace
yum replace mysql --replace-with mysql57w
```

For a fresh install:

```
    yum install mysql57w mysql57w-server
```

Then, re-start and configure.

```
    service mysqld start      chkconfig mysqld on
```

If a new install, set the MySQL root password:

```
     /usr/bin/mysqladmin -u root password 'new-password'
```

For an existing install / upgrade, you will need to upgrade the existing tables after the restart.

```
mysql_upgrade -u root -p
```

This will issue a password prompt for the user. If you don't have a root user password, remove the "-p".

DNS and Additional Utilities

5. Install the DNS and other remaining utilities:

- curl
- openssl
- nmap
- bind-utils
- bind
- expect

```
    yum install curl openssl nmap bind-utils bind expect
```

3) Configuring the requirements:

SSL

Self signed certificates in CentOS 6 by default have been already installed.

If you want to change it, follow the steps below:

Note: For production install, it is **HIGHLY RECOMMENDED** to use organization signed certs

Generate private key, CSR, and temporary key if one hasn't been provided.

```
openssl genrsa -out ca.key 1024    openssl req -new -key ca.key -out ca.csr
openssl x509 -req -days 365 -in ca.csr -signkey ca.key -out ca.crt
```

Copy the files to the correct locations

```
   cp ca.crt /etc/pki/tls/certs    cp ca.key /etc/pki/tls/private/ca.key    cp ca.csr /etc/pki/tls/private
/ca.csr
```

Make sure that you copy the files and do not move them if SELinux is enabled (which it is by default)

Edit the apache ssl config and put in the appropriate options:
(shown using the vi editor, though you may use the editor of your choice)

```
vi /etc/httpd/conf.d/ssl.conf
```

Find the lines that start with SSHCertificateFile and change them to be like:

```
SSLCertificateFile /etc/pki/tls/certs/ca.crt
SSLCertificateKeyFile /etc/pki/tls/private/ca.key
```

Then restart:

```
/etc/init.d/httpd restart
```

Add 443 virtual hosts as needed in httpd.conf.

Apache

Allow overwrites in the apache vhosts:

```
sed -i 's/AllowOverride None/AllowOverride All/g' /etc/httpd/conf/httpd.conf
```

Start Apache and make it start on boot:

```
chkconfig httpd on     service httpd start
```

mod rewrite REQUIRED

Please note that mod_rewrite is required! If it is not enabled in Apache, key elements will not work as expected.

MySQL

Set the MySQL Configuration:

```
mysql -p -e "SET GLOBAL sql_mode='NO_ENGINE_SUBSTITUTION';SET SESSION sql_mode='NO_ENGINE_SUBSTITUTION';"
```

then enter the MySQL root password when prompted.

MySQL Packet Size Configuration

We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

4) Optional configurations:

Configure SELinux

READ THIS BEFORE YOU USE SELINUX

SELinux is a very powerful method of securing the CentOS environment, but it is not "turn key" and requires expertise to configure it correctly. If you do not know how to configure SELinux, please do not use it. A badly configured SELinux install will not work well and result in frustration. If you have any questions or concerns about this - please contact 6connect Support at support@6connect.com.

RE-IP WARNING

Please remember - if you change the IP address of the your server, then you will need to update SELinux functions accordingly

Most CentOS install have SELinux enabled by default. One of its protections is to not allow httpd daemon to make network connections, we need to disable this for license checks.

To view the SELinux configuration for http:

```
/usr/sbin/getsebool -a | grep httpd
```

To turn protection off for the httpd daemon for creating network connections:

```
   /usr/sbin/setsebool -P httpd_can_network_connect 1
```

Configure IPTables

IPTables is enabled by default on CentOS. Add a new rule to allow 443 from anywhere. Make sure that this rule is in the chain BEFORE any blanket reject rule:

To list all current IPTable rules:

```
/etc/rc.d/init.d/iptables status
```

To add a rule for 443:

```
/sbin/iptables  RH-Firewall-1-INPUT -I 5 -m state --state NEW -m tcp -p tcp --dport 443 -j ACCEPT
```

Note

The -I 5 is what adds the rule to the 5th chain position. You might need to change this depending on existing rules. Look at what rules are there before running.

To save the new config:

```
/etc/rc.d/init.d/iptables save
```

OR (some versions of centOS have different iptables names, so the above won't work)

```
vi /etc/sysconfig/iptables
```

With the file open for editing, add:

```
-A RH-Firewall-1-INPUT -m state --state NEW -m tcp -p tcp --dport 443 -j ACCEPT
```

Once complete - restart the iptables service:

```
/etc/init.d/iptables restart
```

Customers can alter this post install to allow only their IP space, plus the 6connect management space.

Radius (Optional)

This section only needs to be followed if the customer will be using Radius for authentication.

Install radius module:

```
    pecl install radius     echo extension=radius.so > /etc/php.d/radius.ini
```

SSH

Install ssh module:

```
    yum install libssh2-devel     pecl install -f ssh2     echo extension=ssh2.so > /etc/php.d/ssh2.ini
```

4) Install 6connect ProVision Software:

1. Remove the current contents in the ProVision web folder (currently the www root) and after extract the archive contents (where 7.x.x is the version number for the ProVision, and php7.x is the required php version build) :

```
 tar -xf productionBuild-7.x.x-php7.x.tar -C /var/www/html
```

2. Change the permissions to be the web user permissions

chown -R apache.apache /var/www/html

3. Go to http://<web root>/install/configTest.php. Follow the provided instructions, correcting any configuration errors if they occur. Once all steps are completed, you are ready to use your ProVision instance!

ProVision Local Installation For CentOS 7

CentOS 7

- CentOS 7
- Before You Begin
- Install Requirements
    - 1) Upgrade your current packages
    - 2) Install Required Packages
        - PHP
        - MySQL
        - DNS and Additional Utilities
    - 3) Configuring the requirements:
        - SSL
        - Apache
        - MySQL
    - 4) Optional configurations:
        - Configure SELinux
        - Configure IPTables
        - Radius (Optional)
        - SSH
    - 5) Install 6connect ProVision Software:

Before You Begin

Ensure that System Requirements have been met prior to proceeding with the CentOS Configuration Guide.

Install Requirements

1) Upgrade your current packages

Upgrade your current packages:

```
yum update
```

2) Install Required Packages

PHP

Installations of ProVision 7.x and newer require PHP 7.1 (and related extensions). CentOS 6 comes with PHP 5.3 by default. You can either add a repository which provides PHP 7.1 or install PHP manually.

Repository & Syntax

The Webtatic and Remi repos both have versions of PHP which are newer than those in the official repos. For this example, we'll be using Webtatic.

If using a different repo or installing manually, your installation syntax may be different from what is listed here.

Add the repository:

```
rpm -Uvh https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
rpm -Uvh https://mirror.webtatic.com/yum/el7/webtatic-release.rpm
```

Install PHP and extensions:

PHP 7.x / Apache2 / extensions

- httpd
- php71w
- php71w-opcache
- php71w-mysqlnd
- php71w-pdo
- php71w-ldap
- php71w-pecl-memcache
- php71w-bcmath
- php71w-devel
- php71w-pear
- php71w-cli
- php7.1-imap

Development tools for pecl / additional system packages:

- curl
- openssl
- memcached
- mod_ssl

```
yum install httpd php71w php71w-opcache php71w-mysqlnd php71w-pdo php71w-ldap php71w-pecl-memcache php71w-
bcmath php71w-devel php71w-pear php71w-cli php7.1-imap curl openssl memcached mod_ssl
```

MySQL

Install MySQL 5.7 / MariaDB to use a local database.

MySQL is included with most CentOS installs, check for it with:

```
yum list installed | grep mysql
```

If it is not installed:

```
    rpm -Uvh http://repo.mysql.com/mysql-community-release-el7-5.noarch.rpm
    yum install mysql-server
    service mysqld start
    chkconfig mysqld on
```

Set the MySQL root password:

```
     /usr/bin/mysqladmin -u root password 'new-password'
```

If you prefer to install MariaDB:

```
    yum install mariadb-server mariadb
    systemctl start mariadb
```

Set the root password, as currently it is not set, just hit ENTER on the current password:

```
mysql_secure_installation
```

Set so that it starts on boot:

```
systemctl enable mariadb.service
```

DNS and Additional Utilities

5. Install the DNS and other remaining utilities:

- curl
- openssl
- nmap
- bind-utils
- bind
- expect
- wget
- bzip2

```
yum install curl openssl nmap bind-utils bind expect wget bzip2
```

3) Configuring the requirements:

SSL

1. Self signed certificates in CentOS 7 by default have been already installed.

If you want to change it, follow the steps below:

Note: For production install, it is **HIGHLY RECOMMENDED** to use organization signed certs

Generate private key, CSR, and temporary key if one hasn't been provided.

```
openssl genrsa -out ca.key 1024
openssl req -new -key ca.key -out ca.csr
openssl x509 -req -days 365 -in ca.csr -signkey ca.key -out ca.crt
```

Copy the files to the correct locations

```
cp ca.crt /etc/pki/tls/certs
cp ca.key /etc/pki/tls/private/ca.key
cp ca.csr /etc/pki/tls/private/ca.csr
```

Make sure that you copy the files and do not move them if SELinux is enabled (which it is by default)

Edit the apache ssl config and put in the appropriate options:
(shown using the vi editor, though you may use the editor of your choice)

```
vi /etc/httpd/conf.d/ssl.conf
```

Find the lines that start with SSHCertificateFile and change them to be like:

```
SSLCertificateFile /etc/pki/tls/certs/ca.crt
SSLCertificateKeyFile /etc/pki/tls/private/ca.key
```

Then restart.

```
/etc/init.d/httpd restart
```

Add 443 virtual hosts as needed in httpd.conf.

Apache

Allow overwrites in the apache vhosts:

```
sed -i 's/AllowOverride None/AllowOverride All/g' /etc/httpd/conf/httpd.conf
```

Start Apache and make it start on boot:

```
systemctl start httpd.service
systemctl enable httpd.service
```

mod rewrite REQUIRED

Please note that mod_rewrite is required! If it is not enabled in Apache, key elements will not work as expected.

MySQL

Set the MySQL Configuration:

```
mysql -p -e "SET GLOBAL sql_mode='NO_ENGINE_SUBSTITUTION';SET SESSION sql_mode='NO_ENGINE_SUBSTITUTION';"
```

Then enter the MySQL root password when prompted.

MySQL Packet Size Configuration

We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

4) Optional configurations:

Configure SELinux

READ THIS BEFORE YOU USE SELINUX

SELinux is a very powerful method of securing the CentOS environment, but it is not "turn key" and requires expertise to configure it correctly. If you do not know how to configure SELinux, please do not use it. A badly configured SELinux install will not work well and result in frustration. If you have any questions or concerns about this - please contact 6connect Support at support@6connect.com.

RE-IP WARNING

Please remember - if you change the IP address of the your server, then you will need to update SELinux functions accordingly

Most CentOS install have SELinux enabled by default. One of its protections is to not allow httpd daemon to make network connections, we need to disable this for license checks.

To view the SELinux configuration for http:

```
/usr/sbin/getsebool -a | grep httpd
```

To turn protection off for the httpd daemon for creating network connections:

```
/usr/sbin/setsebool -P httpd_can_network_connect 1
```

Configure IPTables

IPTables is enabled by default on CentOS. Add a new rule to allow 443 from anywhere. Make sure that this rule is in the chain BEFORE any blanket reject rule:

To list all current IPTable rules:

```
iptables -L
```

To add a rule for 443:

```
/sbin/iptables  RH-Firewall-1-INPUT -I 5 -m state --state NEW -m tcp -p tcp --dport 443 -j ACCEPT
```

Note

The -I 5 is what adds the rule to the 5th chain position. You might need to change this depending on existing rules. Look at what rules are there before running.

To save the new config:

```
/etc/rc.d/init.d/iptables save
```

OR (some versions of centOS have different iptables names, so the above won't work)

```
vi /etc/sysconfig/iptables
```

With the file open for editing, add:

```
-A RH-Firewall-1-INPUT -m state --state NEW -m tcp -p tcp --dport 443 -j ACCEPT
```

Once complete - restart the iptables service:

```
/etc/init.d/iptables restart
```

Customers can alter this post install to allow only their IP space, plus the 6connect management space.

Radius (Optional)

This section only needs to be followed if the customer will be using Radius for authentication.

Install radius module:

```
    pecl install radius
    echo extension=radius.so > /etc/php.d/radius.ini
```

SSH

Install ssh module:

```
yum install libssh2-devel
pecl install -f ssh2
echo extension=ssh2.so > /etc/php.d/ssh2.ini
```

5) Install 6connect ProVision Software:

1. Remove the current contents in the ProVision web folder (currently the www root) and after extract the archive contents (where 7.x.x is the version number for the build) :

```
tar -xf productionBuild-7.x.x-php7.x.tar -C /var/www/html
```

2. Change the permissions to be the web user permissions

```
chown -R apache.apache /var/www/html
```

3. If enabled SELinux you must execute the following command:

```
chcon -R -t httpd_sys_rw_content_t /var/www/html

chcon -R -t httpd_sys_rw_content_t /tmp
```

You must also execute the same command for the 6c secure path created from **configSecureKeys.sh**

4. Go to http://<web root>/install/configTest.php. Follow the provided instructions, correcting any configuration errors if they occur. Once all steps are completed, you are ready to use your ProVision instance!

ProVision Local Installation For Debian 7/8

Debian 8

- Debian 8
- Before You Begin
- Install Requirements
    - 1) Upgrade your current packages
    - 2) Install Required Packages
        - PHP
        - MySQL
        - DNS and Additional Utilities
    - 3) Configuring the requirements:
        - SSL
        - Apache
        - MySQL
    - 4) Optional configurations:
    - 5) Install 6connect ProVision Software:

Before You Begin

Ensure that System Requirements have been met prior to proceeding with the Installation Guide.

Install Requirements

1) Upgrade your current packages

Upgrade your current packages.

```
apt-get update
apt-get upgrade
```

2) Install Required Packages

PHP

Installations of ProVision 7.x and newer require PHP 7.1 (and related extensions). ProVision 7.x installations using Debian versions prior to Stretch 9 require updating to PHP 7.1. Debian Wheezy comes with PHP 5.4 by default. You can either add a repository which provides PHP 7.1 or install PHP manually.

For this example, we are using Debian/Ubuntu installation instructions from:

https://ayesh.me/Ubuntu-PHP-7.1 , using Ondej Surý's PPA.

Another reference containing instructions for Debian 7, 8, CentOS / RHEL, MacOS X, and Windows is available here:

https://www.colinodell.com/blog/201612/installing-php-71

Depending on what repository you choose, installation instructions and syntax may differ.

Debian 8 Install Package

```
sudo apt install apt-transport-https lsb-release ca-certificates
sudo wget -O /etc/apt/trusted.gpg.d/php.gpg https://packages.sury.org/php/apt.gpg
sudo sh -c 'echo "deb https://packages.sury.org/php/ $(lsb_release -sc) main" > /etc/apt/sources.list.d/php.
list'
sudo apt update
```

And update the packages list:

```
    apt-get update
```

Install Apache2/PHP7/MySQL and development tools for pecl:

PHP 7.x / Apache2 / extensions

- httpd
- php7.1w
- php7.1w-opcache
- php7.1w-mysqlnd
- php7.1w-pdo
- php7.1w-ldap
- php7.1w-pecl-memcache
- php7.1w-bcmath
- php7.1w-devel
- php7.1w-pear
- php7.1w-cli
- php7.1-imap

Development tools for pecl / additional system packages:

- curl
- openssl
- memcached
- mod_ssl

```
    apt-get install apache2 libapache2-mod-php7.1 php7.1 php7.1-cgi php7.1-cli php7.1-gd php7.1-curl php7.1-
ldap php7.1-mysqlnd php7.1-ssh2 php-pear php7.1-dev php7.1-imap curl openssl memcached php7.1-memcache
```

While installing you will be asked to set the MySQL root password.

MySQL

Install MySQL 5.7 to use a local database.

```
apt-get install mysql-server
```

You will be asked to enter a root password for the mysql server.

DNS and Additional Utilities

Install the DNS and other utilities:

- curl
- openssl
- memcached
- php7.1-memcache
- nmap
- dnsutils
- bind9utils
- expect

```
apt-get install curl openssl memcached php7.1-memcache nmap dnsutils bind9utils expect
```

3) Configuring the requirements:

SSL

Enable the necessary apache modules with the following command:

```
a2enmod php7 ssl rewrite
```

In order to create self-signed certificates and to work properly, the hostname must be resolved properly.

Open the hosts file for editing:

```
vi /etc/hosts
```

Add a record for your hostname

```
yourhostname X.X.X.X
```

Create self-signed certificate:

```
make-ssl-cert generate-default-snakeoil --force-overwrite
```

Apache

mod rewrite REQUIRED

⚠ Please note that mod_rewrite is required! If it is not enabled in Apache, key elements will not work as expected.

Enable the default vhost for apache:

```
a2ensite default-ssl
```

Allow overwrites in the apache vhosts:

```
sed -i 's/AllowOverride None/AllowOverride All/g' /etc/apache2/sites-available/default*
```

6. Reload apache:

```
service apache2 reload
```

MySQL

MySQL Configuration:

```
mysql -p -e "SET GLOBAL sql_mode='NO_ENGINE_SUBSTITUTION';SET SESSION sql_mode='NO_ENGINE_SUBSTITUTION';"
```

Then, enter the MySQL root password when prompted.

MySQL Packet Size Configuration

⚠ We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

4) Optional configurations:

Radius (Optional)

This section only needs to be followed if the customer will be using Radius for authentication.

1. Install radius module:
Debian 7:

Debian 7:

```
pecl install radius
```

Debian 8:

Debian 8:

```
apt-get install php7-radius
```

Create module loading configuration:
(shown using the vi editor, though you may use the editor of your choice)

```
vi /etc/php5/mods-available/radius.ini
```

Add the following lines to radius.ini:

```
; configuration for php radius module
; priority=20
extension=radius.so
```

To enable the radius module, type the following command:

```
php7enmod radius
```

5) Install 6connect ProVision Software:

1. Remove the current contents in the ProVision web folder (currently the www root) and after extract the archive contents (where 7.x.x is the version number for the build):

```
tar -xf productionBuild-7.x.x-php7.x.tar -C /var/www/
```

2. Change the permissions to be the web user permissions:

```
chown -R www-data.www-data /var/www
```

3. Go to http://<web root>/install/configTest.php. Follow the provided instructions, correcting any configuration errors if they occur. Once all steps are completed, you are ready to use your ProVision instance!

ProVision Local Installation For Ubuntu

Ubuntu 18.04

- Ubuntu 18.04
- Before You Begin
- Install Requirements
    - 1) Upgrade your current packages
    - 2) Install Required Packages
        - PHP
        - MySQL
        - DNS and Additional Utilities
    - 3) Configuring the requirements:
        - SSL
        - Apache
        - MySQL
    - 4) Optional configurations:
        - Radius (Optional)
        - SSH
    - 5) Install 6connect ProVision Software:

Before You Begin

Ensure that System Requirements have been met prior to proceeding with the Installation Guide.

Permissions

Before installing, verify that you have appropriate install permissions. Depending on your permissions and system setup, commands may need to be run as superuser by prepending "sudo" to the listed commands.

Install Requirements

1) Upgrade your current packages

Upgrade your current packages.

```
apt-get update
apt-get upgrade
```

2) Install Required Packages

PHP

Installations of ProVision 7.x and newer require PHP 7.1 (and related extensions). You can either add a repository which provides PHP 7.1 or install PHP manually. In this example, we use the default package sources for Ubuntu 18.04 to install Apache 2.4 and PHP 7.1. We also provide an option to install PHP 5.7 through a third-party repository.

If you are installing ProVision 7.x, or after, make sure that your build archive has "php7.x" as part of its name. For example "productionBuild-7.0.0-php7.1.tar".

1. Add PHP 7.1 package sources to your system:

```
add-apt-repository ppa:ondrej/php
```

and confirm with ENTER to continue.

If you get an error here, you may need to install python-software-properties first and then repeat the repository add as follows:

```
apt-get update
apt-get install python-software-properties

add-apt-repository ppa:ondrej/php
```

2. Update packages:

```
apt-get update
```

3. Install PHP:

```
apt-get install php7.1
```

and confirm with “y” and ENTER.

You’ll now see “PHP 7.1.x” in the scrolling installation logs.

To verify the installed version of PHP, run:

```
php7 -v
```

Install Apache2/PHP 7.x/MySQL 5.7 and development tools for pecl:

PHP 7.x / Apache2 / extensions

- httpd
- php7.1w
- php7.1w-opcache
- php7.1w-mysqlnd
- php7.1w-pdo
- php7.1w-ldap
- php7.1w-pecl-memcache
- php7.1w-bcmath
- php7.1w-devel
- php7.1w-pear
- php7.1w-cli
- php7.1-imap

Development tools for pecl / additional system packages:

- curl
- openssl
- memcached
- mod_ssl

```
apt-get install apache2 libapache2-mod-php7.1 php7.1 php7.1-cgi php7.1-cli php7.1-gd php7.1-curl php7.1-ldap
php7.1-mysqlnd php7.1-ssh2 php-pear php7.1-dev php7.1-imap curl openssl memcached php7.1-memcache
```

MySQL

ProVision 7.x and above requires MySQL 5.7 and above.

Add new repository for MySQL 5.7 distribution.

```
apt-key adv --keyserver pgp.mit.edu --recv-keys 5072E1F5
echo "deb http://repo.mysql.com/apt/ubuntu/ trusty mysql-5.7" >> /etc/apt/sources.list.d/mysql.list
```

Update current packages.

```
apt-get update
```

Install MySQL 5.7 to use a local database.

```
apt-get install mysql-server-5.7
```

You will be asked to enter a root password for the mysql server.

MySQL is now installed. You can proceed to next section DNS And Additional Utilities

Install MySQL to use a local database:

```
apt-get install mysql-server
```

You will be asked to enter a root password for the mysql server.

DNS and Additional Utilities

Install the DNS and other utilities:

- curl
- openssl
- nmap
- dnsutils
- bind9utils
- expect

```
apt-get install curl openssl nmap dnsutils bind9utils expect
```

3) Configuring the requirements:

SSL

Enable the necessary apache modules with the following command:

```
a2enmod php7 ssl rewrite headers
```

In order to create self-signed certificates and to work properly, the hostname must be resolved properly.

Open the hosts file for editing:

```
    vi /etc/hosts
```

Add a record for your hostname:

```
X.X.X.X yourhostname
```

Create self-signed certificate:

```
make-ssl-cert generate-default-snakeoil --force-overwrite
```

Apache

mod rewrite REQUIRED

⚠ Please note that mod_rewrite is required! If it is not enabled in Apache, key elements will not work as expected.
Enable the default vhost for apache:

```
a2ensite default-ssl
```

Allow overwrites in the apache vhosts:

```
sed -i 's/AllowOverride None/AllowOverride All/g' /etc/apache2/apache2.conf
```

Update site configurations to use /var/www for docroot:

```
sed -i 's/\/var\/www\/html/\/var\/www/' /etc/apache2/sites-available/000-default.conf
sed -i 's/\/var\/www\/html/\/var\/www/' /etc/apache2/sites-available/default-ssl.conf
```

Restart apache:

```
service apache2 restart
```

MySQL

MySQL Configuration:

```
mysql -p -e "SET GLOBAL sql_mode='NO_ENGINE_SUBSTITUTION';SET SESSION sql_mode='NO_ENGINE_SUBSTITUTION';"
```

Then, enter the MySQL root password when prompted.

MySQL Packet Size Configuration

⚠ We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

4) Optional configurations:

Radius (Optional)

This section only needs to be followed if the customer will be using Radius for authentication.

Install radius module:

Debian 8:
`apt-get install php7-radius`

Create module loading configuration:
(shown using the vi editor, though you may use the editor of your choice)

```
vi /etc/php5/mods-available/radius.ini
```

Add the following lines to radius.ini:

```
; configuration for php radius module
; priority=20
extension=radius.so
```

To enable the radius module, type the following command:

```
php7enmod radius
```

SSH

Install ssh module:

```
apt-get install libssh2-1-dev
```

then run:

```
pecl install ssh2-1.1.2
```

Create module loading configuration:
(shown using the vi editor, though you may use the editor of your choice)

```
vi /etc/php7/mods-available/ssh2.ini
```

Add the following lines to ssh2.ini (adding extension=ssh2.so to your ssh2.ini):

```
; configuration for php ssh2 module
; priority=20
extension=ssh2.so
```

To enable, type the following command:

```
phpenmod ssh2
```

Reload apache:

```
service apache2 reload
```

5) Install 6connect ProVision Software:

The latest version of ProVision can be found at https://cloud.6connect.com/Download/Latest/ and downloaded using the credentials provided to you!

If you need credentials provided to you, or any other assistance, please contact our support team atsupport@6connect.com.

1. Remove the current contents in the ProVision web folder location (currently the www root) and after extract the archive contents (where 7.x.x is the version number for the build):

```
tar -xf productionBuild-7.x.x-php7.x.tar -C /var/www/
```

2. Change the permissions to be the web user permissions

```
chown -R www-data.www-data /var/www
```

3. Go to http://<web root>/install/configTest.php. Follow the provided instructions, correcting any configuration errors if they occur. Once all steps are completed, you are ready to use your ProVision instance!

6connect Local Software Upgrades

Local Software Upgrades

- Local Software Upgrades
  - Upgrade Methods for Local Installs of 6connect Provision
    - Manual Upgrade (Recommended)

Upgrade Methods for Local Installs of 6connect Provision

The recommended upgrade method for local installations of ProVision is a manual download of the latest version and running the associated upgrade script.

For upgrades consisting of multiple versions, ensure that each version upgrade is performed in order. If you have a particularly complicated upgrade or special concerns, contact our support team, and 6connect engineers can recommend an upgrade strategy tailored to your situation and assist as needed.

If you have questions, need assistance, or wish to schedule an upgrade to the latest version, contact support@6connect.com.

Manual Upgrade (Recommended)

A manual upgrade is the recommended route for local installations, providing the highest level of control and oversight, and may be performed in installation scenarios where company policies restrict automatic downloads / script executions :

1. Download the latest 6connect tar file from https://cloud.6connect.com/Download/Latest/
2. Extract into web root.
3. Run configDir.sh <web user> from the command line as root in the web root. This will setup the directories apache user needs read /write access to.

```
cd /var/www/html /var/www/html/configDir.sh <web user>
```

4. Run the upgrade scripts located in the upgrade/scripts directory in order of version number via:

```
php <upgrade-script.php> -v
```

The following local upgrade options are available, but are not generally recommended - differences in installation setup and access levels may result in these options being less reliable than the manual upgrade option.

GUI

In the 6connect tool, navigate to Admin Admin Preferences page. If there is a new version available, an Upgrade button will be available. Click on the Upgrade Now button to go to the upgrade page. It will automatically download the latest version available, run all upgrade scripts, and create a log of the upgrade process.

Command Line

In upgrade/scripts run 'php upgrade.php -h' to get the help and full usage of upgrade.php. This script will automatically get the latest tar file, create a backup, and run all the necessary upgrades between the current and latest version. The most common usage of upgrade will look like this 'php upgrade.php -v -b </path/to/store/backup>'

Local Installations - Peering Setup

Peering Setup - Local Installations:

ProVision versions 5.3.0 to 6.1.2

ProVision uses a locally-hosted mirror of the PeeringDB database in order to perform non-edit Peering functions. There are a few steps to take in order to set up your locally hosted instance to coordinate with PeeringDB information.

As of PeeringDB 2.0, SQL dump files are no longer provided. If you are using ProVision 5.3.0 or higher, you must follow this new install process. If you are using a lower version of ProVision, then please follow the instructions in the previous version of this page.

1) Create a new database to store the PeeringDB data. This **must** be on the same server as the database which is used by ProVision.

2) Download, install, and use the PeeringDB Python Client to populate the database.

The PeeringDB documentation is available here: http://peeringdb.github.io/peeringdb-py/

3) Once this has been done, edit the ProVision global configuration file located here:

```
[ProVision Root]/data/globals.php
```

It must be updated with the following variables to inform ProVision of the location of this new install. The username and password fields correspond to the username and password of the MySQL account which has access to the database (Not the username and password to your PeeringDB account).

This can, but does not have to be, the same MySQL user which is used for the ProVision database. However, the ProVision MySQL user **must** have at least READ access to the PeeringDB database.

```
$peeringdb_host = 'localhost';          // Database host must be the same for provision and peering
$peeringdb_username = 'username';       // username for the MySQL user
$peeringdb_password = 'password';       // password for the MySQL user
$peeringdb_db_name = 'peeringdb';       // name of the database in MySQL
```

4) Periodically sync with the PeeringDB server to get the latest updates. This can be done manually, or there are instructions in the PeeringDB documentation on how to automatically schedule syncs using cron (http://peeringdb.github.io/peeringdb-py/cli/#sync).

ProVision versions 7.x and newer

For ProVision versions 7.x and later, ProVision directly interfaces with PeeringDB's API to update exchange and peering data, caching the data for a default time of 12 hours.

This requires a PeeringDB account, and for the account credentials to be set in ProVision. The credentials may either be hard coded into globals.php, or set into the database via the Admin/Peering GUI. See Admin Preferences and Peering for detailed information.

Additional Peering constants may be added into globals.php to change the PeeringDB URL between the main and beta site (some users may find the beta site to have faster response times), and to adjust the PeeringDB cache TTL.

For real-time updates, TTL may be set to 0. However, some users may experience severe lag with a TTL = 0; we recommend using a 10 to 15 minute or greater TTL if this occurs.

Peering Constants

In globals.php, the following constants can be defined to tweak the Peering internals:

PEERINGDB_USERNAME

```
define('PEERINGDB_USERNAME', 'username');
```

Default value: none

The username for the account used to connect to the PeeringDB API

Instead of saving the username and password in the database, the values can be hard coded into globals.php

PEERINGDB_PASSWORD

```
define('PEERINGDB_PASSWORD', 'mypass');
```

Default value: none

The password for the account used to connect to the PeeringDB API

PEERINGDB_URL

```
define('PEERINGDB_URL', 'https://peeringdb.com/api/');
```

Default value: https://peeringdb.com/api/

The URL of the PeeringDB API. Alternate value: https://beta.peeringdb.com/api/

PEERINGDB_CACHE_TTL

```
define('PEERINGDB_CACHE_TTL', 43200);
```

Default value: 43200 (12 hours)

How often (in seconds) to purge the cached PeeringDB API calls. If a customer wants real time access, this can be set to 0.

If experiencing major lag issues with real time access, it is recommended to increase to increase the cache TTL from 0 to 5, 10, or 15 minutes.

Additional Information:

For additional information on working with Peering, see the following documentation sections:

Peering

Import Peering Sessions

Local Installations - Master-Master Replication

Configuring ProVision for Master-Master Replication

1. Create two ProVision installs on two different servers. These servers can be bare metal or they can be VMs. These servers will be referred to as **Rep1** and **Rep2**.

2. Open an SSH session to **Rep1**.

3. Confirm that **Rep1** can communicate with **Rep2** by issuing a ping command:

```
ping ip-of-Rep2
```

If the **Rep1** cannot communicate with **Rep2**, consult your system or network administrator to clear this error.

4. Stop the apache2 service using the following command:

```
service apache2 stop
```

5. Run the following command to open the MySQL configuration file for editing:

```
vi /etc/mysql/mysql.conf.d/mysqld.cnf
```

6. Find the line that reads:

```
bind-address = 127.0.0.1
```

And change it to:

```
bind-address = 0.0.0.0
```

Note: you may wish to consult with your security department to determine the least-permissible values.

7. Add the following lines to the end of the file, then save and exit:

```
server-id=1

   log-bin="mysql-bin"

    binlog-do-db=name_of_database

    replicate-do-db=name_of_database

    relay-log="mysql-relay-log"

    auto-increment-offset = 1

auto-increment-increment = 10
```

Note: “name_of_database” is a placeholder for the name of the 6connect ProVision database. This is typically “provision” but may be different based on the choices made during installation.

8. Enter the following command:

```
service mysql restart
```

If you get errors, please re-check that you have correctly entered the changes in step (6) to the configuration file, and that you have replaced the name of the database correctly.

9. Create a dump of the current database state:

```
mysqldump -uroot -p name_of_database > initial.sql
```

You will need the MySQL root password for this, which can normally be found at:

/var/www/html/data/globals.php

Note you will also need to change the database name as in the previous step.

10. Transfer the database dump to **Rep2**, to serve as the basis for the synchronization:

```
scp initial.sql username@location-of-rep2:~
```

You will have to customize this command with a user on **Rep2** and its location. Ex:

```
scp initial.sql username@67.221.241.164:~
```

Note: You will need to customize this command with your credentials on **Rep2**.

11. Run the following command:

```
rm /var/lib/mysql/auto.cnf
```

12. While still on **Rep1**, log in to MySQL as root.

```
mysql -u root -p
```

13. Run the following commands in MySQL:

```
CREATE USER 'replicator'@'%' IDENTIFIED BY 'replication_password';

GRANT REPLICATION SLAVE ON *.* TO 'replicator'@'%';
```

Note: The specific requirements for password strength are governed by your local policies.

14. Run the following command in MySQL:

```
SHOW MASTER STATUS;
```

Note the ‘File’ and ‘Position’ columns. These will be referred to later as “rep1_file” and “rep1_position.”

15. Leave the SSH session to **Rep1** open. Open a second SSH session to **Rep2**.

16. Confirm that **Rep2** can communicate with **Rep1** by issuing a ping command:

```
ping ip-of-Rep1
```

If the **Rep2** cannot communicate with **Rep1**, consult your system or network administrator to clear this error.

17. Stop the apache2 service using the following command:

```
service apache2 stop
```

18. Run the following command to open the MySQL configuration file for editing:

```
vi /etc/mysql/mysql.conf.d/mysqld.cnf
```

19. Find the line that reads

```
bind-address = 127.0.0.1
```

And change it to:

```
bind-address = 0.0.0.0
```

Note: you may wish to consult with your security department to determine the least-permissible values.

20. Add the following lines to the end of the file, then save and exit:

```
server-id=2

   log-bin="mysql-bin"

    binlog-do-db=name_of_database

    replicate-do-db=name_of_database

    relay-log="mysql-relay-log"

    auto-increment-offset = 2

auto-increment-increment = 10
```

Note: “name_of_database” is a placeholder for the name of the 6connect ProVision database. This is typically “provision” but may be different based on the choices made during installation.

21. Enter the following command:

```
service mysql restart
```

If you get errors, please re-check that you have correctly entered the changes in step (20) to the configuration file, and that you have replaced the name of the database correctly.

22. Run the following command:

```
rm /var/lib/mysql/auto.cnf
```

23. Log into MySQL as root:

```
mysql -u root -p
```

24. Run the following commands to delete the current ProVision database and to adopt the MySQL dump that was created in step (9). If this is not part of the initial ProVision configuration, ensure that proper backups have been made and are accessible before deleting.

```
DROP DATABASE name_of_database;

CREATE DATABASE name_of_database;

USE name_of_database;

source /home/root/initial.sql;
```

Note: you may have to customize the final line with the location of the “initial.sql” file that was transferred to **Rep2** in step (10).
Note: you will have to replace name_of_database with the 6connect ProVision database chosen at install.

25. While still in MySQL on **Rep2**, run the following commands:

```
CREATE USER 'replicator'@'%' IDENTIFIED BY 'replication_password';

GRANT REPLICATION SLAVE ON *.* TO 'replicator'@'%';
```

Note: The specific requirements for password strength are governed by your local policies.

26. Run the following command in MySQL:

```
SHOW MASTER STATUS;
```

Note the ‘file’ and ‘position’ columns. These will be referred to later as “rep2_file” and “rep2_position.”

27. On **Rep1**, in MySQL, run the following commands:

```
STOP SLAVE;

CHANGE MASTER TO MASTER_HOST = 'location_of_rep2',MASTER_USER = 'replicator', MASTER_PASSWORD =
'replication_password', MASTER_LOG_FILE = 'rep2_file', MASTER_LOG_POS = rep2_position;

START SLAVE;
```

Note that you must replace “location_of_rep2”, “replication_password”, “rep2_file” and “rep2_position” with values from earlier in this tutorial.

28. On **Rep2**, in MySQL, run the following commands:

```
STOP SLAVE;

CHANGE MASTER TO MASTER_HOST = 'location_of_rep1',MASTER_USER = 'replicator', MASTER_PASSWORD =
'replication_password', MASTER_LOG_FILE = 'rep1_file', MASTER_LOG_POS = rep1_position;

START SLAVE;
```

Note that you must replace “location_of_rep1”, “replication_password”, “rep1_file” and “rep1_position” with values from earlier in this tutorial.

29. On **Rep1**, exit MySQL and enter the following command:

```
service apache2 start
```

30. On **Rep2**, exit MySQL and enter the following command:

```
service apache2 start
```

31. Replication should now be running between the two servers. To test this, log in to MySQL on both **Rep1** and **Rep2**, switch to the ProVision database on both and run the following command:

```
SELECT COUNT(*) FROM log;
```

This will show how many logs are recorded by each database. Now, use a web browser to navigate to the ProVision GUI on **Rep1** and log in. This will produce additional log events within the ProVision database.

Return to MySQL on both databases and run the above command again. You should see two things: that the log count has increased, and that the count is identical on both servers. If this matches what you see then replication is working.

To complete the test now use a web browser to navigate to the ProVision GUI on **Rep2** and log in. This should again produce an equal increase in log counts on both servers.

A Note On Passwords!



For local password storage, you will need to sure that the encryption key is "in sync" across your replicated instances.

The way ProVision/ACP works is that when we have to store a password to an external system we encrypt it in our database, then store the encryption key outside the database on the file system. This way if there is a database compromise, access credentials are unusable.

The encryption key is stored in a file described in the "secure_dir" parameter in the ProVision/ACP config.php file. It is typically:

'secure_dir' => '/var/www/secure/'

The file will be named "[your-database].keyFile".

If you have installations in master-master configuration, and one or more of the keyFiles is out of sync with the rest of the cluster, that out-of-sync node will be encrypting passwords that the other nodes cannot decrypt.

The solution for this is to just pick a keyFile and replicate it across all the nodes.

If a keyFile is lost it means that no stored passwords will be able to be decrypted. This can be fixed by just re-entering the passwords.

After copying the KeyFile, please ensure that you check permissions on the file.

ESXi VM Image Setup

Before you Begin:

Ensure that you have the root user information for the VM and a license key - please contact 6connect Support (support@6connect.com) or your Reseller/VAR for more information.

Step 1

Download OVF and VMDK files from 6connect (or approved) download area. If you do not have this information, please contact 6connect Support (support@6connect.com) or your Reseller/VAR for more information.

Step 2

Option 1: Import OVF and VMDK to your ESXi VM environment (VMware ESXi 6.5 or later).

Option 2: If you do not have ESXi 6.5 or later, then you can create a new VM (CentOS, 64-bit, 4GB RAM) and use the VMDK disk image that you downloaded in Step 1.

Step 3

Power on the VM and login, using the root user account information per "Before you Begin".

Step 4

Customize the VM environment for the following items:

1. Change the root user password from its default
2. edit /etc/sysconfig/network-scripts/ifcfg-ens192 with your IP information
3. edit /etc/hostname
4. edit /etc/resolv.conf
5. Optional - add SSL certs (non self signed) per normal CentOS7 installation
6. Reboot the VM

Step 5a

Finish setup of ProVision for your organization:

1. Go to https://<hostname or IP address>/install/configTest.php in a web browser
2. Scroll to the bottom to complete Step 13 (see image below). The Registration Email is your License Email that would have been sent to you by 6connect or ProVision VAR. If your VM is in an "offline" or SCIF environment please go to Step 5b.



3. You should now be able to go to your Instance URL and login with the credentials generated for your user/registration email address.

Step 5b

For an "offline" license, you will be emailed a license file and path to place it. Without this file, you will not be able to login to ProVision. One the license file is applied, you should now be able to go to your Instance URL and login with the credentials generated for your user/registration email address.

Please note that the offline license file is version specific, so before you upgrade to a new version of ProVision, you will also need to make sure you update the license file after the upgrade.

ProVision Getting Started

Welcome to ProVision!

Our Getting Started documents provide a high-level overview to orient you to working in ProVision.

If you need setup assistance or additional information, you can contact our support team at support@6connect.com.

- Welcome to ProVision!
  - ProVision Getting Started
  - ProVision User Guide
  - ProVision Admin Guide
  - ProVision Developer Tools
  - Additional Resources

ProVision Getting Started

First Steps - Not sure where to begin? Here are some key items to consider when setting up your first ProVision instance, high level overviews of Resources, Permissions, and Importing data into ProVision.

Resource Concepts - The Resource Management System is a key component of ProVision. This system supports a variety of hierarchies and metadata - understanding how these pieces can be used is important prior to importing data or setting up the application.

Workflow Concepts - ProVision has two distinct interfaces depending on the user level and task. It is important to understand how these interfaces work together from the centralized data. This is important for user on-boarding and training of internal operations staff, developers or engineering teams.

ProVision User Guide

The user guide gives you an overview on the standard UI functions of ProVision and installed Modules.

ProVision Admin Guide

The Admin Guide provides an overview of administrative functions of the different functional areas of ProVision.

ProVision Developer Tools

The Developer Tools section has details on our API and related information - including code samples.

Additional Resources

You can also browse the Tutorials and FAQ, if you have any questions, please contact our support team at support@6connect.com.

First Steps

ProVision First Steps

- ProVision First Steps
  - Overview Video: First Steps - Part 1
  - Before you Begin
    - 1) What type of physical and non-physical components do you wish to track?
    - 2) What is your current data structure? What is your ideal data structure?
    - 3) Who needs access to what data?
  - Overview Video: First Steps - Part 2
  - Getting your Data into ProVision
    - 1) Gather and Prep your data
    - 2) Import or Manually Add Data
      - A) Resources
      - B) IP Aggregates and Blocks
      - C) Add DNS servers and zones
    - 3) Add Users and Groups
  - Working In Provision

Overview Video: First Steps - Part 1

This video gives a high level overview of the "Before you Begin" content on this page, as well as an introduction to ProVision's Resource System.

Note: Recorded in ProVision v5.1.x, newer versions may have interface updates.

This video may also be viewed at https://www.youtube.com/watch?v=apJRcQv3ZQ0.

Before you Begin

We recommend that new users work through the following questions with their internal team to plan their ProVision instance:

Need Help?

Remember that 6connect's engineers are here to help. If you have questions, or want to test out some ideas, our team has worked with a variety of data sets and can help get you started on the right path. You can reach us any time at support@6connect.com.

1) What type of physical and non-physical components do you wish to track?

Impacts: What Sections and Resources are created

An important first step is determining what items you currently are, or will be, tracking, and what relationship they have with each other. ProVision's flexible Resource system allows you create and customize detailed entries for any type of item you may want to track: Customers, Contacts, Data Centers, Routers, VMs, and more. These types of resources are labeled as "Sections" in ProVision. Once a section is made, individual items (resources) may be created as a part of that Section. Each Section may have different Gadgets selected, which then provide additional functionality on a resource entry page.

See: Resources, Customizing Sections, Gadgets

2) What is your current data structure? What is your ideal data structure?

Impacts: Resource Hierarchy, Assignment Behavior

The resource hierarchy structure in ProVision allows for "child" resources to be created under a parent resource (for example: servers as children under a datacenter resource entry, or subsidiaries under a parent company, who then share IP aggregates). The structure decided upon will influence how resources are set up in ProVision, as well as the behaviors of functions while working with items such as IP blocks or DNS zones.

See: Resources, The Resource System

3) Who needs access to what data?

Impacts: User and Group Permissions

In ProVision, standard user permissions are set by resource and functional area (IPAM, Resource, Peering, etc). Global Admin permissions give access to additional functions such as configuration settings, importing, and Scheduler tasks. Determine which users will require administrative access, and which will have access to only specific resources or functional areas. You will need to get more specific later, but having some high level groups to work with is a great start.

See: Users & Permissions

Overview Video: First Steps - Part 2

This video gives a high level overview of the "Getting your Data into ProVision" content on this page.

Note: Recorded in ProVision v5.1.x, newer versions may have interface updates.

This video may also be viewed at https://www.youtube.com/watch?v=2e0H1H4rTTs.

Getting your Data into ProVision

After determining your internal goals and processes, it's time to get your data into ProVision!

Start Small

When importing data into ProVision, data validation is a key step to ensure that everything is accurate. Upon importing your data, you may see some errors that result in a stop in the import process! It is recommended that you break up your imports to both keep them manageable and give you a chance to normalize your data prior to importing.

1) Gather and Prep your data

Determine where your data will be from:

Excel / Spreadsheets:

May be used to import: Resources, IP Aggregates/ Blocks, DNS BIND Zones

If you currently use Excel or other spreadsheet program for tracking, you will need to verify that your spreadsheets are "cleaned up" according to the information on the Importing Your Data page under "Preparing for Data Import":

- Make sure that you use UTF-8 encoding, remove extraneous blank rows, and compare your data to the data fields available in ProVision, shown under "Which Import Tool Should I Use?".
- Review sample files if desired to see example formats.
- If you plan to track custom types of Resources by creating Sections, you will need to create a Section with custom fields, and verify that your spreadsheet contains the same fields.

Once your verification / cleanup is complete, export your spreadsheet as a .csv file.

See: Importing Your Data, Resources, Import DNS Zones

RIR

May be used to import: IP Aggregates

No advance preparation is needed for aggregates imported from RIR. ProVision's built-in importer will ask for your ORGID or an IP, and then populate an aggregate list from that information. Simply choose which aggregates you wish to import.

See: Import Aggregate Blocks

DNS Servers

May be used to import: DNS Zones

ProVision provides automated tools for importing DNS zones from the following server types: BIND, PowerDNS, InfoBlox, NS One, Dyn DNS, and DNSMadeEasy servers, as well as IPPlan MySQL Databases.

Before importing DNS zones, it is recommended that a DNS Group be created to hold the zones being imported, and that the DNS server be added into ProVision so that zone updates may be pushed.

For general DNS taks, see: DNS Administration, DNS Tab, Working with DNS Groups, Working with DNS Servers

For specific DNS zone import instructions for each DNS server type, see: Import DNS Zones

Manually Adding Data

ProVision allows manual adding of data at any time. We recommend verifying that the item has not already been added beforehand (to prevent duplicates), and keeping your desired data structure in mind.

2) Import or Manually Add Data

The order in which items are added will depend on what ProVision functional area (Resources, IPAM, DNS) you will be using, and what the current / desired data structure is. In general, the following order is recommended:

A) Resources

Importing or creating your resources first allows subsequent items to be associated with those resources.

Note: If you already have "Resource" data associated with your IP block data (ie, as fields in a spreadsheet with Resource Name and Resource ID), you may choose not to create those resources ahead of time. The IP Import from CSV tool will give you an option to create those Resources during the IP import process.

Import customers, physical devices, locations, and so forth through the Resource Import from CSV tool. If you wish for additional customization, you may create a custom Section, add the desired fields, and import resources under that Section through the Resource Import Tool.

Adding resources manually may be done at any time under the **Resources** Tab, by clicking the "Add Entry" button.

See: Resources, Importing Your Data

B) IP Aggregates and Blocks

Import your IP Aggregates through the Import from RIR tool, or from a .csv file via IP Import from CSV.

The Import from CSV tool will create Top-Level Aggregates and place blocks under those aggregates based on the following method:

> First, the importer will parse through the provided data, order all blocks from largest to smallest, then attempt to split the largest block out of an existing block matching the IP space and RIR. If that fails (no larger block exists), then that block is added in the system as its own Top-Level-Aggregate. Subsequent blocks will undergo the same process.

This method ensures that your list of IP blocks does not need to be organized in any particular order.

If your import includes a large number of small blocks (/30s, /32s), be sure you've included at least one large block which encompasses them (/24, /22). This will ensure that the smaller blocks are neatly organized under the larger block, rather than imported as their own Top-Level Aggregates.

See: Importing Your Data

C) Add DNS servers and zones

If using the DNS Module in ProVision, you will need to add your servers prior to importing zones.

Add DNS Severs

Adding DNS Servers requires administrative access.

Servers are added under the DNS Tab of ProVision, under "DNS Servers". Click on "Add Server" and fill out the server information.

See: Working with DNS Servers

Information for specific server types and options is available under the following sections:

Configuring ISC BIND Support

Configuring PowerDNS Support

Configuring Secure64 Support

Configuring Split Horizon/Views

Configuring DNSSEC

Import DNS Zones

After creating the applicable servers in ProVision, you may import or manually add DNS zones.

ProVision offers multiple DNS zone import options, available under the Data Import tab in the Admin section. For more information on importing DNS zones, see Importing your Data and Import DNS Zones.

BIND Zone Import

- Imports using the named.conf configuration file tied to the zones you are uploading, a .zip or .tar file of the zones themselves, and an optional .csv file mapping zones to customers.

PowerDNS Zone Import

- Option is available after configuring a PowerDNS server with a MySQL backend. Connects to the selected server and imports all zones.

InfoBlox Zone Import

- Imports DNS zones using a provided Host, Username, and Password. The InfoBlox import pulls all zones on the InfoBlox LOCAL grid and adds them to a designated Group. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

NS One Zone Import

- Imports DNS zones using a NS One API Key. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

Dyn DNS Zone Import

- Imports DNS zones using a Dyn DNS Customer Name, Username, and Password. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

DNSMadeEasy Zone Import

- Imports DNS zones using a DNSMadeEasy API Key and API Secret. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

IPPlan Zone Import

- Imports DNS zones using IPPlan MySQL database options. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

Manually adding zones may be done at any time from the **DNS** Tab. See Working with DNS Zones and DNS Zones Overview.

3) Add Users and Groups

In ProVision, the permissions structure is handled by assigning users to groups, then setting specific resource-level C/R/U/D permissions for that group. It is designed to give you as much flexibility as you need to accommodate most use cases. When mapping out the permissions structure for your organization, keep in mind who you want to access to application:

- Internal Users and Roles (Admins, Read Only, etc.)
- Partners related to multiple specific Resources/Accounts
- Customers/Departments with limited view to only their respective Resources/Accounts

See: Users & Permissions, Working With Users and Groups

Users and Groups may be added at any time. However, assigning permissions to users and groups is best done after the applicable resource hierarchy has been added into ProVision.

Working In Provision

With the basic data now imported, and users set up, you (and your team) are ready to work in ProVision!

Refer to our User Guide and Admin Guide for details on standard user and admin level areas of ProVision. Or, follow the links below for additional details grouped by specific task areas:

Concepts:

Resource Concepts

Workflow Concepts

Resources:

Resources

Customizing Sections

Customizing Fields

Gadgets

IPAM:

IPAM Tab

Working with IP Blocks

Working with IP Rules

IPAM Administration

DNS:

DNS Tab

Working with DNS Groups

Working with DNS Zones

DNS Zones Overview

DNS Administration

Working with DNS Servers

DHCP:

DHCP Tab

Working with DHCP Groups

Working with DNS Zones

Working with DHCP Gadgets

DHCP Administration

Peering:

Peering

Peering Exchanges

Peering Routers

Peering Sessions

Import Peering Sessions

Resource Concepts

The Resource System


- The Resource System
  - Resource System Components
    - Resources
    - Section
    - Entry
    - Category
  - Resource Hierarchy
    - Additional Information:

Resource System Components

Resources

In ProVision, a “Resource” is simply an umbrella term for the components that you are tracking. Resources may be:

- Physical assets such as servers and routers
- Virtual assets such as DNS Zones or VMs
- Individual people or companies (customers)
- Places holding your assets, such as datacenters




Section

The generic type of a resource is called a Section. General terms such as Rack, Routers, Customer, Servers, and Datacenters would be considered "Sections" in ProVision.

Example: You might have an individual server named "Test Server", but its generic type of resource is that of a “Server” – so we would associate “Test Server” with the Section “Server”.


Think of Sections as templates for your resources. When a Section is created, you can associate specific fields and gadgets with that Section. In the case of our "Server" section, we would want to associate fields that are common server properties, such as Make, Model, Operating System, and Domain. Then, anytime we looked up a specific server in ProVision, we can see and update the Make, Model, OS, and Domain information.



Entry

Think of an Entry as the individual item you are tracking – it has a specific name, it might have an IP Address, a physical address, or additional descriptive data that is associated with it.


Our "Test Server" resource is an Entry under the "Server" Section.



Here, we can see that under the “Datacenter” section, we have two entries – one is the Ashburn Datacenter, the other is the Boston Datacenter. Under “Servers”, we have entries for “Test Server” and “Backup Server”.

Category

Another part of ProVision's resource system is "Categories". Categories allow you to group resources together under a name of your choosing to further organize your resources. A category that is often used is "Customer", grouping customer resources together




In this example, we are grouping Racks, Servers, and Routers under the "My Custom Grouping" Category.

Creating categories is entirely optional, so you can decide internally if the additional organization is needed in your instance.

Resource Hierarchy

In ProVision, "Child" Resources can be created underneath a "Parent" resource. This functionality allows for hierarchies to be created to match the desired organizational structure. An example of this would be to create racks and servers as children under a datacenter entry. Chart View, available from the **Resources** Tab, lets you see this structure graphically.



The structure decided upon will influence how resources are set up in ProVision, as well as behaviors of functions while working with items such as IP Blocks or DNS zones.

Additional Information:

Resources

Working with Entries

Customizing Sections

Customizing Fields

Gadgets

Workflow Concepts


Workflow Concepts

- Workflow Concepts
- IP Assignment Lifecycle
    - IP Management
- Peering
- VLAN Manager
    - VLAN Workflow:
        - Create Domain(s)
        - Add / Edit VLANs
        - Add IP Blocks to VLANs
        - Manage Domains and VLANs
    - VLAN Workflow (Legacy):
        - Standard flow (without VLAN tags):
        - Optional flow (with VLAN tags):
- DHCP
- DNSv3 Workflow
- Approvals Workflows
    - Initial Setup
        - Step 1 - Review Existing User Groups and Process Needs
        - Step 2 - Add or Edit ProVision User Groups
        - Step 3 - Assign Approval Action Settings to Groups
        - Step 4 - Enable Notifications (Optional)
        - Step 6 - Add Scheduler Task: "Approvals - Delete events older than 1 month"
    - Daily Use

IP Assignment Lifecycle

In ProVision, the IP assignment lifecycle starts with an available block which is free to be assigned to any IPAM-enabled resource holder. There are multiple methods that may be used to assign a block to a resource holder: Smart Assign, Direct Assign, or Manual Assign (Smart Browse).

Once an IP block is assigned, blocks can be further subassigned via the same methods if desired. When an assigned block is un-assigned it proceeds into the Holding Tank: a special resource where blocks are held until either a set time has elapsed or until they are manually reclaimed to 'available' status.



For more information on performing tasks in this IP Assignment Lifecycle, see the following documentation sections:


Working with IP Blocks

IPAM Administration

IP Management

IP Management is comprised of four basic functions: adding aggregates into ProVision, managing those aggregate blocks, assigning them to a resource, and deleting the aggregates.

ProVision provides multiple ways for you to achieve each step, depending on your needs. For example, if your organization currently uses spreadsheet data to track aggregates, ProVision provides tools that can import your existing spreadsheets for bulk updates, saving you time. Need to just quickly assign a single IP? Direct Assign will allow you to do so with just a few clicks.



For more information on performing tasks in this IP Management Flow, see the following documentation sections:

Working with IP Blocks

IPAM Administration

Importing Your Data

Import Aggregate Blocks

Peering

ProVision versions 7.0.0 and later:


Initially, ASNs and Peering DB information will need to be entered into ProVision to enable Peering functionality. After the, Peering starts with designating Routers. Routers may be added from the "Add Router" button under the Peering Tab Routers sub-tab. Once a router has been created, Peer Groups may be added from the Router Details page or the Peer Group Gadget.


After the router(s) and Peer Groups have been created in ProVision, Sessions need to be added. Sessions may be added manually through the "Add Session" dialog in the Peering tab, or Imported from a router (requires ProVision Admin permissions).

Once a session has been created, it can be configured and managed through the Sessions list and Session details page (using 1-click Config or Config Management), or multiple sessions may be configured for a specific Peer via the "Configure Multiple Sessions" option, which will provide options to either "Config Now" or "Schedule Config" for a later time.


Managing Peer Communications is done primarily from the Exchange Communications menu, sending requests and marking peers as existing / not qualified / approved, etc. If desired, a corporate Peering email account may be associated with ProVision under the Peering Emails subtab, allowing for peering requests to be viewed from ProVision and associated with Peers.

PEERING WORKFLOW





ProVision versions 6.2.1 and earlier:



For more information on performing tasks under Peering, see the following documentation sections:

Peering:

Peering

Peering Exchanges

Peering Routers

Peering Sessions

Import Peering Sessions

VLAN Manager

ProVision versions 7.3.0 and later:

The VLAN Manager allows users to add domains and VLANs to their ProVision instance, and associate them with IP Blocks. Customizable VLAN columns - including up to ten user-defined metadata columns - allow you to rename column headers, set the display order, select which columns are visible, and display your own information fields.

Permissions and VLAN

The Permissions structure in VLAN includes the following items of note:

The following VLAN tasks requires Admin-level permissions:

- Adding new Numbering Authority ranges for VLAN use
- Editing IPAM / VLAN Columns
- Adding, editing, and removing Domains
- Adding, editing, and removing VLANs

Non-Admin users may:

- View the VLAN Home Page and utilization data, however, only resources that the user has view permissions for will display under the "Resources" and "Recent Assignments

VLAN Workflow:

Create Domain(s)

The workflow starts with creating a domain in the IPAM Tab VLAN section of ProVision, by clicking the "Add Domain" button and entering domain information.

VLAN domains may be created as pre-set Numbering Authority ranges, or defined manually. Two default Numbering Authority VLAN ranges are provided, one for a Cisco Standard domain, and another for a Cisco Extended Domain. Admins may create new Numbering Authority ranges at any time to support other router types, range extents, or exclusions. Those ranges will then be available as options when adding a new domain from the VLAN area. If you select to create a new domain by defining a manual range, you may enter the range extents, any exclusions, and associate a specific router if desired.

Add / Edit VLANs

VLANs may be added to the domain at the time the domain is created (via the "Add VLANs" input area) or added to an existing domain later via the "Add VLANs" button. You can add one VLAN, multiple VLANs, a large range of VLANs, or a mixed selection at the same time.

Once a VLAN has been added to a domain in ProVision, the VLAN may be edited to add a VLAN name or metadata information, and have IP blocks associated with it.

Add IP Blocks to VLANs

Once a VLAN has been added to a domain in ProVision, IP blocks may be associated with ('assigned to') that VLAN. There are multiple methods to set the VLAN for a block:

- **Individual block edit** - Edit one or more blocks and set the Domain and VLAN fields to the desired values. Direct edit may be performed from IPAM Manage, VLAN Manage, and the IPAM Gadget, by selecting "Edit Block".
- **Direct Assign a block** - Open the "Assign Blocks" panel, expand "Direct Assign", and type in the CIDR to assign to the VLAN. Advanced options are available to distinguish between duplicate blocks. The "Assign Block" panel is available from the VLAN's Utilization Box, and/or the VLAN Manage header bar.
- **Smart Browse for blocks** - Open the "Assign Blocks" panel, expand "Browse Assign", and enter filter criteria to create a list of blocks meeting that criteria. Then, select one or blocks from the list to assign to the VLAN. The "Assign Block" panel is available from the VLAN's Utilization Box, and/or the VLAN Manage header bar.

After assigning a block to the VLAN by any method, that block will immediately display in VLAN Manage for that VLAN, in the VLAN's Quickview Panel, and the VLAN Utilization display panel will be updated to include the new block.

Manage Domains and VLANs

Managing VLANs and blocks under the VLANs may include standard IPAM tasks, such as editing blocks, splitting / merging blocks, or allocating/ assigning / unassigning the blocks to a resource. All of these functions, and more, may be performed from either VLAN Manage or IPAM Manage.

Other tasks, such as editing VLAN names, metadata, or adding/removing VLANs from a domain are performed from the VLAN Action Panels on the VLAN Home page, or from VLAN Manage.

Editing Domains - including renaming, adding metadata, and deleting - may be performed from VLAN Advanced.

VLAN Workflow (Legacy):

ProVision versions 7.3.0 and earlier:

The VLAN Manager allows Admin users to add domains and VLANs to their ProVision instance, and associate them with IP Blocks. Optionally, VLAN tags may be associate with ranges or individual VLANs under a domain, to help limit VLAN search results when enabling VLANs.

Standard flow (without VLAN tags):

The workflow starts with creating a domain in the VLAN Admin section of ProVision. During creation, domains may be selected as "standard" or "extended" domains, declaring the size of the VLAN pool from which VLANs are available to be enabled. Next, VLANs must be enabled and added to the domain. This is done under the IPAM Tab -> VLAN section of ProVision. Add VLANs to the domains by clicking "Add", searching for the desired range of VLANs to enable from the standard / extended pool, and selecting the desired VLANs to enable. Once enabled, VLANs may be edited or have IP blocks associated with that VLAN. Editing VLANs and Direct / Smart Browse / Search IPs functions for adding blocks to VLANs are available from the Domain/ VLAN list under under the IPAM Tab -> VLAN section of ProVision by expanding the desired domain and clicking on the VLAN link. IP blocks may also be edited individually through the IPAM gadget, IPAM Manage, and VLAN Manage areas to add domain and VLAN information to the block.

Optional flow (with VLAN tags):


The workflow starts with creating a domain in the VLAN Admin section of ProVision. During creation, domains may be selected as "standard" or "extended" domains, declaring the size of the VLAN pool from which VLANs are available to be enabled. VLAN tags may be added (from the VLAN Admin Tab -> Edit Tags submenu) before or after domain creation. Tags created in this area are available to all domains and VLANs.

If the tags created need to be added to a large range of VLANs, the next step would be to add tags to the desired range(s) of VLANs from the VLAN Admin -> Domain "Manage" button. Domain Manage allows you to select an existing tag, type in the numeric VLAN start and end point, and assign that tag to that entire range of VLANs under the current domain.

Once a bulk range of tags is associated with VLANs, you can use the tag as a search criteria when adding VLANs to a domain. This is done under the IPAM Tab -> VLAN section of ProVision. Add VLANs to the domains by clicking "Add", using the tag name as a search field for the desired range of VLANs, and then selecting the desired VLANs to enable.

If tags are only desired for individual VLANs, they may be added when editing a VLAN after the VLAN has already been added/enabled for the domain. Editing VLANs may be accessed from the IPAM Tab -> VLAN section, then expanding the desired domain and clicking on the VLAN link, selecting "Edit".

Next, VLANs must be enabled and added to the domain. This is done under the IPAM Tab -> VLAN section of ProVision. Add VLANs to the domains by clicking "Add", searching for the desired range of VLANs to enable from the standard / extended pool, and selecting the desired VLANs to enable. Once enabled, VLANs may be edited or have IP blocks associated with that VLAN. Editing VLANs and Direct / Smart Browse / Search IPs functions for adding blocks to VLANs are available from the Domain/ VLAN list under under the IPAM Tab -> VLAN section of ProVision. IP blocks may also be edited individually through the IPAM gadget, IPAM Manage, and VLAN Manage areas to add domain and VLAN information to the block.



DHCP

ProVision versions 7.0.0 and later:

ProVision 7.0.0+ includes many updates to the DHCP module, including the introduction of DHCP Groups, updated interface, improved permissions control, and simplified pool management. The DHCP Tab contains areas for managing both admin and non-admin tasks together for DHCP Groups, DHCP Servers, and DHCP Pools.

DHCP Groups allow you to create, view, and manage groups of DHCP Servers and Pools. Using groups, you can configure and push selected combinations of zones at one time. DHCP pools may be gathered under DHCP Groups, and servers attached to those Groups. Pools, attached servers, and failovers are managed at a per-Group level. Users can then view and manage Groups, individual pools, failover values, attach servers, and perform pushes all on the same page.

Additionally, starting in ProVision 7.0.0, any IPAM aggregate or block may be used for DHCP pools - provided it meets the specified criteria when creating a DHCP Pool. If assigning a pool out from a specific resource, ensure ahead of time that the resource contains suitable blocks with subassignments enabled.

The DHCP Workflow begins with adding DHCP Servers into ProVision and creating an additional DHCP Groups as needed.


New DHCP servers may be added from the DHCP Tab - DHCP Servers subtab by clicking "Add Server" (requires Admin access). Type in the server information, select the service, and choose the resource to which the DHCP server belongs if applicable. This creates a hierarchical relationship, with the server as a child resource under the selected parent, and affects how permissions are handled for the server and pools. Then, enter any service-specific or advanced settings for the server. You may also choose which DHCP group to associate with the server if the group already exists, but you may also add that setting later.

If desired, you may create additional DHCP Groups to organize certain pools and associated DHCP servers together to push concurrently, with the option of a common failover value. A common scenario is using separate DHCP Groups per server, or separate Groups for IPv4 vs. IPv6 pools. A new DHCP Group may be created from the DHCP Groups subtab "Add Group" button. Enter the Group Name and parent resource. Once created, you may attach a DHCP server to the Group, associate a failover, and add pools to it.

Next, you may add/assign DHCP pools. Before assigning pools, ensure that you have suitable IP aggregates created in ProVision meeting your desired parameters to assign to the pool (such as desired RIR, region, VLAN, or allocated to a specific Resource). If assigning a pool out from a specific resource, ensure ahead of time that the resource contains suitable blocks that have subassignments enabled.

To add a pool to a DHCP Group, click the "Add Pool" button for that group. You may also add a pool from the DHCP Pools subtab without associating the pool with a DHCP Group. From the "Create New Pool" dialog, select the pool type ("Subnet" or "Host), enter in the relevant information, and select to either Direct Assign a specific block, or have ProVision Smart Assign a block based on provided filter criteria - such as assigned resource, region, rule, or VLAN. Click "Save" to complete the Pool assignment.

Once servers, groups, and pools have been created, you may complete management tasks such as pushing configs on either a server, group, or individual pool level, schedule pushes, update reservations or assignment ranges, and change group/server associations as needed.



For ProVision versions 6.2.1 and earlier:


The DHCP Workflow in ProVision begins with denoting the DHCP IP Aggregate(s) from the IPAM Tab -> "Add Aggregate". When creating DHCP aggregates, ensure that the block is designated as 1918 space, and has the check boxes next to "DHCP Aggregate" and "Allow Sub-assignment" selected. This will ensure the block is automatically added to the DHCP Available Resource, and is usable when defining DHCP Pools.

Separately, ensure that the DHCP server is added into ProVision. New DHCP servers may be added from the DHCP Tab "Add DHCP Server" button. Type the server name, then choose the resource to which the DHCP server belongs. This creates a hierarchical relationship, with the server as a child resource under the selected parent.

Once the server has been created in ProVision, click on the server name in the DHCP server list to go to the server's Entry Page. If the server was created through the DHCP Tab, the DHCP Management Gadget will already be enabled for the DHCP server. If created elsewhere, the DHCP Gadget may need to be enabled by simply selecting the "On" radio toggle next to "DHCP Services", and clicking the "Update" button. Next, add in the connection configuration and server details for the DHCP server in the DHCP Gadget.

Now that the DHCP server is set up and DHCP aggregates created, DHCP Pools may be created and managed. Pools may be created by subnet or host. Creating by subnet allows for a block to either be directly assigned manually, or for ProVision to SmartAssign a block based on the provided criteria. Creating by host requires providing a host and MAC address, and then likewise may have an IP directly assigned or Smart Assigned. DHCP Pools, once created, are managed by linking or unlinking to the DHCP server. IP assignments and pool details may be changed at any time by clicking on the pool name, editing the details as desired, then clicking "Save".

DHCP WORKFLOW



For more information on working with DHCP in ProVision, see the DHCP Tab documentation.

For more information on DHCP tasks, see the following sections:

DHCP Tab

Working with DHCP Groups

Working with DHCP Pools

Working with DHCP Gadgets

DHCP Administration

Working with DHCP Servers

DNSv3 Workflow

DNSv3 revolves around Groups. Zones are gathered under Groups, servers attached to Groups, and pushes may be done on a per Group level. Thus, the first workflow step in DNSv3 is to set up one or more DNS Groups. A "Default Group" is automatically provided in ProVision, but other Groups may be desired to organize zones and default values.

To create a new DNS Group, click the "Add Group" button from the **DNS Groups** tab. Enter the desired default values for the Group, and save. If only using the Default Group, ensure the default parameter values are set as needed. For more information, see Working with DNS Groups.


After Groups have been set up, DNS servers should be added or settings verified. Admin users may add DNS servers from the **DNS Servers** tab "Add Server" button. Input the server information and save. Existing servers may be reviewed and edited by clicking on the server name in the DNS Server List. Once a server is created in ProVision, it may be attached to any DNS Group under the Group's "Attached Servers" module. Attaching a server to a Group will allow for zones in that group to be pushed to the attached server(s). See Working with DNS Servers.

Next, add zones to your groups. Zones may be manually added under each group by clicking the "Add Zone" button, or it may be imported via DNS Importers into a selected Group. Add the zone and record information, and save. See Working with DNS Zones for additional information.

Zones may be only exist once per Group, but may be duplicated under multiple Groups. Zones may also be moved from Group to Group as needed.

At this point, all major components of the ProVision DNS system have been added - from here management tasks take over. Zones may be updated and moved to or from Groups; Groups may be edited with different default values or servers, and pushes maybe be performed for an individual zone, a full Group, or for an entire server. Pushes may be manual or scheduled for a future time through the Scheduler.

DNS WORKFLOW



For more information on DNSv3 tasks, see the following sections:

DNS Tab

Working with DNS Groups

Working with DNS Zones

DNS Administration

Working with DNS Servers

Import DNS Zones

Approvals Workflows

Initial Setup

The high level process to use when first setting up approvals is as follows:

1. Review User Groups and Approval Process Needs

Step 1 - Review Existing User Groups and Process Needs

When setting up Approvals for the first time, review the information in the previous section under "Approvals Fundamentals" to ensure a basic understanding of how Policies, Actions, and User Groups relate together in Approvals.

Then, take a few minutes to think about the following questions to get a better sense of how to use Approvals with your specific organization:

Who are the users that perform DNS tasks, and at what level?

Affects which users should be included in what User Groups

What ProVision User Group(s) are they in?

Approvals settings are applied to the User Group, not individuals - ensure users with similar oversight needs are grouped together

What actions made by a certain user group should be automatically denied, if any?

Assign the "Deny" policy to that Action/User Group combination

What actions made by a certain user group should require oversight (admin approval / rejection)?

Assign "Action to be approved" to that Action/User Group combination

Who is the admin / User Group that will make the final approval on a change?

Ensure the approver(s) is in a User Group with the "Must Approve" policy assigned for the actions requiring approval

Should any changes require multiple admins / User Groups to approve it in order to execute?

A single user from every group assigned with "Must Approve" for the action must approve the action for it to succeed

If two admins are required to both separately agree on a change, they should be under two separate User Groups assigned "Must Approve"

What User Groups would need to receive email Approval Status notifications, and on what type of actions?

Affects whether to enable notifications and set up the scheduler task to send the notifications, and to what User Groups. When enabled, all users of the relevant group(s) will receive the email(s)

Once your User Groups are optimized for use with Approvals, you may want to write down a quick note on which Action Types and policies are planned for each group.

2. Edit User Groups / Create Approvals-Specific User Groups, if needed

Step 2 - Add or Edit ProVision User Groups

From here, depending on the answers to the questions in step 1, you may need to do one or more of the following from the **Users** tab:


a. Edit existing User Groups to add or remove users, in order to combine users who will need similar action types approved.
b. Verify the User Groups have appropriate CRUD permissions set to perform the action(s) to be approved (e.g, you may have previously removed "Create" permissions for a group, but if the intent is now for those users to have "Add" actions approved by an Admin, the submitter will need User Group resource "Create" permissions back!)
c. Create new User Groups specifically for use with Approvals (recommended)
d. Associate users with different, or additional User Groups (remember - users can be associated with multiple groups!)

For more information on adding and editing ProVision User Groups, see Users & Permissions, Global Permissions, and Working With Users and Groups.


3. Assign Action and Policy Settings to User Groups

Step 3 - Assign Approval Action Settings to Groups


From the **Approvals** Tab, navigate to the **Permission Groups** sub-tab.



Then, under the **Groups** page tab, find the ProVision User Group you wish to want to assign a policy to and click "Assign".



Clicking the "Assign" button for a group brings up a checklist to select what policy to apply to the group for what Family and Actions (i.e. DNS Zone 'Add' or DNS Group 'Update'). You can "quick-select" all actions for a DNS Family (Severs, Groups, Zones, Records) by clicking the checkbox next to the family name, or only select individual action types for each Family.




Once you've selected the applicable Family/Action combinations to apply a policy for, select either "Deny", "Action to be Approved", or "Must Approve Action" under Policy.

When done, Click "Assign", and repeat as needed for other Policy types or User Groups.


4. If using Approvals notifications, enable notifications for the appropriate Permissions Group(s)

Step 4 - Enable Notifications (Optional)

From the **Approvals** Tab, navigate to the **Permission Groups** sub-tab **Groups** page tab.



Click on the group name for which you want to set notifications - the Group Permissions Detail page will provide additional information on the group's settings.



For any Family/Action that you want to enable notifications, click the checkbox under "Enable Notifications". All users of that group will get email notifications when a change of the selected type(s) are made.

5. If using Approvals notifications, set up a Scheduler task for "Approvals - Process Subscription"

Step 5 - Add Scheduler Task: "Approvals - Process Subscription"

The "Approvals - Process Subscription" task processes approval request events and handles the sending of notification emails to subscribed Approvals Groups - this task must be created and running on a regular interval in order for Approval Notification emails to be sent.

In order to receive the most up to date information in the Approval Notifications, is recommended to create this task with a run time of "every 5 minutes" and no end date.

For information on setting up Scheduler Tasks, see Scheduler Tab.

6. Set up a Scheduler Task for "Approvals - Delete events older than 1 month", to occasionally clear out old and obsolete Approval request events

Step 6 - Add Scheduler Task: "Approvals - Delete events older than 1 month"

The "Approvals - Delete events older than 1 month" task deletes any Approvals history events older than 30 days.

It is recommended to set this task to run monthly with no end date, to clear out obsolete approvals items, reduce data storage space needs, and reduce approvals page load time.

For information on setting up Scheduler Tasks, see Scheduler Tab.

Daily Use


On a day-to-day basis after initial setup, an Approvals Workflow will be similar to the following (with "Submitter" as the user whose actions require approval, and "Approver" as the admin with the ability to approve/reject the change):

1. Submitter makes an action (either by action type or DNS Family) that requires approval
2. Submitter is notified that their action is pending approval




3. The requested change is sent to the **Approvals** Tab **Pending Approvals** list, and also to the **DNS** **Resources Awaiting Approval** module (the submitter may see their own submitted action under "Resources awaiting approval", but only Approvers can take approve /reject actions)


The **Pending Approvals** list is under the **Approvals** Tab. It shows Approvals events (change requests) for which the user has the ability to Approve or Deny - it does not show approval requests for all of ProVision or those for other users.



A "Resources Awaiting Approval" module will display in selected DNSv3 pages to Users with Admin / Approval permissions, if a change has been submitted on that page that is pending approval by the User's Approval Group.




4. The Approver reviews the change in either their **Approvals** Tab **Pending Approvals** list, or the **DNS****Resources Awaiting Approval** module, and chooses to Approve or Reject the change:



   a. If Approved, and no other groups need to approve it, then the change executes and is saved. A status change notification email is sent, if enabled.
   b. If Approved, and is waiting approval from an additional User Group, the change continues to be held as Pending, until the other group responds (Both groups must "Approve" for the change to execute). A status change notification email is sent, if enabled, stating that the change is awaiting another Group.
   c. If Rejected, the change is not executed. A status change notification email is sent, if enabled.

Example Notification Email:



See the following areas for more information on Approvals and using Approvals with DNS:

- DNS Tab
- Approvals
- Pending Approvals
- Permission Groups
- Scheduler Tab

ProVision User Guide

User Guide


The ProVision User Guide provides information on features accessible in the standard user tabs within ProVision - Dashboard, Resources, DNS, DHCP, IPAM, Peering, and Reporting. For more detailed information on features accessible with Admin permissions, see the ProVision Admin Guide.

Table of Contents

- The Dashboard
- Resources
- DNS Tab
- DHCP Tab
- IPAM Tab
- Peering
- Reporting
- User Preferences

The Dashboard

The Dashboard



The Dashboard is your first stop when logging into 6connect Provision, giving you a quick graphical status overview as well as convenient links for reference and support. The Dashboard is comprised of modular "Widgets" that show different types of information. These Widgets may be added, moved, edited, and customized to create personalized Dashboards.

There are two levels of Dashboards:

Default Dashboard: The Default Dashboard is a shared dashboard for all users of the ProVision instance. It may only be edited by admin level users, but it is viewable by all users.

Individual Users' Dashboards: Additional Dashboards may be created by individual users. These dashboards are tied to the user logged in, and are only viewable / editable by that user.


Dashboards and Permissions

Note: An individual's permission levels may limit what that user can view in both default and personal Dashboards. Although all users can view the Default Dashboard, they may be not be able to view all elements or data inside the dashboard.

- The Dashboard
  - ProVision Default Dashboard Overview:
    - Activity Chart (Viewable by Admins Only):
    - IP Charts:
    - Clock:
    - Status:
    - Resource Tree:
    - Contact Us:
    - ProVision Learning Links: (Markdown Widget)
    - 6connect Professional Services: (iFrame Widget)
    - 6connect Links (Links Widget):
    - 6connect RSS (RSS Feed Widget):
- Additional Information

ProVision Default Dashboard Overview:

Although each user may have access to or create wildly differing dashboards, below are descriptions of the Widgets available shown on the ProVision Default Dashboard (from left to right):



Activity Chart (Viewable by Admins Only):

Illustrates activity level for API, IPAM, DNS, Peering, and Resource areas of ProVision.

Select the desired ProVision area by clicking on the radio buttons. Then, hover over the chart, and use the mouse scroll wheel to zoom in or out of specific date / times. Clicking on a bubble will show activity detail, and resource / IP block links if applicable.

Only one Activity Chart Widget may exist on a dashboard.

IP Charts:

Illustrates the percentage of assigned, unassigned, allocated, or holding tank hosts for 1918 / IPv4 / IPv6 space out of the total available hosts in ProVision viewable by the user. Hovering over any section of the ring will display additional data.

Only one IP Charts Widget may exist on a dashboard.

Clock:

Shows the current time and date for the selected time zone, based on format set by the user.

Multiple Clock Widgets may exist on a dashboard.

Status:

General status information on number of user / admin accounts, ProVision version number, and a 'Coming Soon' link to the future releases roadmap in the the documentation.

Only one Status Widget may exist on a dashboard.

Resource Tree:

An interactive horizontal or vertical treeview of a selected Resource and its children. Select a top-level resource from the Widget's Edit menu. Users may click and drag to move within the Widget, as well as zoom in and out using a scroll wheel. Clicking on filled dots will expand the tree to show the children of that resource. Double-clicking on a resource in the tree will give you the option to navigate to the resource's entry page.

Multiple Resource Tree Widgets may exist on a dashboard.

Contact Us:

Provides support email, phone, and feedback form information. Support phone number and email address are set from the ProVision Admin settings. The feedback form email address is editable within the Widget.

Only one Contact Us Widget may exist on a dashboard.

ProVision Learning Links: (Markdown Widget)

Pre-created Markdown Widget containing links to commonly referenced ProVision documentation sections, video guides, and walkthroughs.

The Markdown Widget is a blank slate where users may add links, text, or other content through use of the Markdown language.

Multiple Markdown Widgets may exist on a dashboard.

6connect Professional Services: (iFrame Widget)

Pre-created iFrame Widget accessing the 6connect Professional Services website.

The iFrame Widget sets a https URL to be viewed in an iFrame, to view stats or commonly referenced websites.

Multiple iFrame Widgets may exist on a dashboard.

6connect Links (Links Widget):

Pre-created Links Widget listing 6connect ProVision company and documentation links.

Link URL and display may be set from within the Widget.

Multiple Links Widgets may exist on a dashboard.

6connect RSS (RSS Feed Widget):

Pre-created RSS Feed Widget accessing the 6connect Blog RSS.

Shows the most recent five entries of a selected https RSS Feed. Feed links open in a new window when clicked.

Multiple RSS Feed Widgets may exist on a dashboard.

Additional Information

Continue on for details on dashboard customization, as well as how to add, move, update, and delete individual Widgets.

- Customizing the Dashboard
- Working with Dashboard Widgets

Customizing the Dashboard

Dashboard Customization

The Dashboard is your first stop when logging into 6connect Provision, giving you a quick graphical status overview as well as convenient links for reference and support. The Dashboard is comprised of modular "Widgets" that show different types of information. These Widgets may be added, moved, edited, and customized to create personalized Dashboards.

There are two levels of Dashboards:

Default Dashboard: The Default Dashboard is a shared dashboard for all users of the ProVision instance. It may only be edited by admin level users, but it is viewable by all users.

Individual Users' Dashboards: Additional personal dashboards may be created by individual users. These dashboards are tied to the user logged in, and are only viewable / editable by that user.

Dashboards and Permissions

Note: An individual's permission levels may limit what that user can view in both default and personal Dashboards. Although all users can view the Default Dashboard, they may be not be able to view all elements or data inside the dashboard.

Browser Compatibility


It is recommended to use the most recent versions of the Chrome or Firefox browsers when working with the dashboard. Due to incompatibilities with Internet Explorer / Edge, the dashboard is set to read-only mode and is not editable when accessed from IE at this time.

- Dashboard Customization
- Working with Dashboards
  - Viewing an Existing Dashboard
  - Adding a Dashboard
  - Editing a Dashboard
    - To Edit the Page Layout:
    - To Edit the Location of Individual Widgets:
  - Saving a Dashboard
  - Deleting a Dashboard
  - Reset the Default Dashboard
- Next Step: Widgets

Working with Dashboards

Viewing an Existing Dashboard


The Default Dashboard will be the primary dashboard that appears when clicking on the **Dashboard** Tab. To view another, already created dashboard, click on the dashboard name at the top left of the Dashboard page. This will open the list of existing dashboards. From there, click on the name of the dashboard you wish to view.




Adding a Dashboard

To add a new personal dashboard, click on the dashboard name at the top left of the Dashboard page. This will open the list of existing dashboards.

Click on "Add New Dashboard"



Fill out the desired dashboard name, and choose whether the dashboard will be empty or cloned from the default dashboard. Selecting "Empty" will provide a (mostly) blank canvas for selecting and placing Widgets from scratch; selecting "Clone" will duplicate the current state of the Default Dashboard, which the user can then edit as desired.



Note

Note: If "Empty" is selected, a default Widget will still show in the head of each page column, this is to assist in both visualizing the current page layout and to aid in placing new Widgets. These widgets may be edited or deleted as desired during the process of selecting layout and adding other Widgets.

For best performance of the dashboard, ensure that at least one Widget is placed in each column, or columns may be difficult to "detect" when moving Widgets to different page areas.

MyDashboard has now been created as an "Empty" dashboard, is accessible from the dropdown list of dashboards, and is ready to set up!




Editing a Dashboard


You can change the layout of your dashboard by selecting overall page layout options (for column size and location on the page), as well as move individual widgets around the page.

To Edit the Page Layout:

At the top of the page, click "Edit Layout".



This will bring up an option box where you can choose to rename your dashboard, and / or select a column organization structure.



Title: Type in how you want your dashboard title to display.

Layout: Click on a layout option to immediately apply that layout to your dashboard. Hovering over the option will show the column width percentages.

100% / (50% / 50%): Creates a page with a full width section at the top, and two equal sized columns below that.

33% / 66%: Creates a page with two columns, with the left column being one-third of the page width, and the right column as two-thirds of the page width.

50% / 50%: Creates a page with two equal sized columns, split down the middle.

66% / 33%: Creates a page with two columns, with the left column as two-thirds of the page width, and the right column as one-third of the page width.

To Edit the Location of Individual Widgets:

Individual Widgets may be moved around the page by clicking and dragging on the "Move" icon on the right side of the Widget header.


While mousing over the move icon, when the cursor changes to a hand icon, click and hold your left mouse button, then drag the widget up or down to the desired location. To move the Widget to another column, drag the widget sideways to the column, then up to briefly hover over a Widget already in the desired column (this "selects" the column for the Widget). Then, drop the Widget in the desired location in that column.

Saving a Dashboard

Personal dashboards are automatically saved after making layout or Widget edits (the exception is that Widget resizing must be manually saved - see Working with Dashboard Widgets).


Default Dashboards must be manually saved after edits for those changes to apply to all dashboard users.

Admin users can save Default Dashboard changes by clicking "Save as Default Layout" at the top right section of the dashboard page, and the changes will be applied for all users.



Deleting a Dashboard


Personal dashboards may be deleted by clicking the "Delete Dashboard" button at the top right of the page. Default Dashboards may not be deleted.



Reset the Default Dashboard

The Default Dashboard may be reset to the ProVision default dashboard by clicking "Reset Dashboard".

This will remove any admin changes, and set the Default dashboard to its original state. This action may only be made by admin users.



Next Step: Widgets

Continue on to Working with Dashboard Widgets for information on each Widget, as well as how to add, move, update, and delete individual Widgets.

- Working with Dashboard Widgets

Working with Dashboard Widgets

Dashboard Widgets

The previous section, Customizing the Dashboard, gave a high level overview of the dashboard types, how to create new personal dashboards, edit the dashboard layout, and remove personal dashboards. This section will give an overview of how to work with individual Widgets, and options available in each Widget type.


Before you begin working with individual Widgets, make sure that you have reviewed the information contained in Customizing the Dashboard and are familiar with the tasks outlined there.

- Dashboard Widgets
  - Working with Widgets
    - Adding Dashboard Widgets
    - Move a Widget:
    - Maximize / Pop-Out a Widget:
    - Edit a Widget (Widget Action Menu):
  - Available Widgets
    - Activity Chart (Admin only)
    - Resource Tree
    - IP Charts
    - IPAM Stats
    - RSS Feed
    - Status
    - Clock
    - Contact Us
    - Logs
    - Markdown
    - Links
    - iFrame


Working with Widgets

Adding Dashboard Widgets

To add a widget to personalize your dashboard, click on the "Add Widget" button at the top of the page.



Then, click on the name of the Widget you want to appear on your page. It will automatically be added into the leftmost column of your page.




Some Widgets may only have one instance per dashboard, whereas other Widgets may be able to have multiple instances per dashboard. The Add New Widget dialog will only show you the widgets you have available to add.

For detailed information on each individual Widget, view the Available Widgets section on this page.

Move a Widget:

Individual Widgets may be moved around the page by clicking and dragging on the "Move" icon on the right side of the Widget header.




While mousing over the move icon (when the cursor changes to a hand icon) click and hold your left mouse button, then drag the widget up or down to the desired location.

To move the Widget to another column, drag the widget sideways to the column, then up to briefly hover over a Widget already in the desired column (this "selects" the column for the Widget). Then, drop the Widget in the desired location in that column.

Your browser does not support the HTML5 video element

Maximize / Pop-Out a Widget:


Widgets can temporarily be viewed at a larger size by hitting the "Maximize" icon on the Widget header. This will "pop out" the widget information to a larger page size for easier viewing.



While maximized, you may interact with the widget as normal. When done, hit the "Close" button.

Edit a Widget (Widget Action Menu):

To open the edit menu for a widget, click on the Action Menu (wrench icon) on the right side of the Widget header. A drop down menu will appear with some of the following options:



Edit: Opens an edit widget pop up, where widget-specific options may be changed. Options may include changing the title, links, applicable resources, and so forth depending on the particular Widget.


Resize: For Widgets able to be resized vertically, brings up a draggable black bar at the bottom of the widget. Drag the bar up or down to the desired widget height, then select the Action Menu again and click on "Save Resize" to save and complete the size edit.

Save Resize: Available only after the "Resize" action has been used. After resizing a Widget, selecting the Action Menu again and clicking on "Save Resize" will save the Widget size.

Delete: Deletes the widget.

Available Widgets

Activity Chart (Admin only)



Illustrates activity level for API, IPAM, DNS, Peering, and Resource areas of ProVision. The Activity Chart is only visible to Admin users. Only one Activity Chart Widget may exist on a dashboard.

Activity Chart Actions:

Radio Buttons: Select the desired ProVision activity area to view by clicking on the radio buttons (API, IPAM, DNS, Peering, or Resources).

Chart: While hovering over the chart, you can:

Use the Scroll Wheel to zoom in or out of the date/time detail level

Double click to zoom into the next date/time detail level

Click & Drag left or right to move to an earlier or later date/time at the current zoom level


Single Click on a bubble will show the activity detail, and resource / IP block links if applicable.

Activity Chart Edit Options:



Title: Edits the title of the Widget shown on the header.

Resource Tree



Interactive graphical display of the resource structure for a parent resource.

Resource Tree Actions:

Users may:


Click & Drag to move the chart within the Widget,

Use the Scroll Wheel to zoom in or out

Click on Filled dots to expand the tree to show the children of that resource.

Double click on a resource in the tree to give you the option to navigate to the resource's entry page.

Resource Tree Edit Options:




Title: Edits the title of the Widget shown on the header.

Orientation: Select "Horizontal" to view the tree in horizontal form, with the top level resource on the leftmost side of the widget, and children expanding to the right. "Vertical" will show the tree with the top level parent at the top of the widget, with children expanding downward.

Resource: A text search box to select the resource that will be the top level resource for the tree.

When done editing, hit "Apply" to save your changes, or "Cancel" to exit without saving.

IP Charts



Illustrates the percentage of assigned, unassigned, allocated, and holding tank hosts for 1918 / IPv4 / IPv6 space out of the total available hosts in ProVision viewable by the user.


Hovering over a particular status will display detailed data in the center of the chart for that status type.

IP Charts Edit Options:

Title: Edits the title of the Widget shown on the header.


IPAM Stats

The IPAM Stats widget contains read-only IPAM data on host count by status, assigned date range, assignment rate, and projected runout under three tabs.




Users may select to view IPv4, IPv6, or 1918 stats by clicking on the tab for the block type you wish to view.

RSS Feed



Shows the most recent five entries of a selected RSS Feed. Feed links open in a new window when clicked.

RSS Feed Edit Options:



Title: Edits the title of the Widget shown on the header.

Feed URL: Edits the URL of the RSS Feed to show.

Status




Shows 6connect ProVision status information, including number of user accounts (admin only), number of admin accounts (admin only), current version number, and a link to the "Coming Soon" section of the ProVision documentation.

Status Edit Options:


Title: Edits the title of the Widget shown on the header.

Clock



Shows the current time for the selected time zone.

Clock Edit Options:



Title: Edits the title of the Widget shown on the header.

Time Pattern: Sets the desired format for the current time. Example: "HH:mm:ss z" shows hours, then minutes, then seconds, then time zone.

Date Pattern: Sets the desired format for the current date. Example: "YYYY-MM-DD" shows 4 digit year, then month, then day.

Time Zone: The desired time zone to show the current time for.

Time / Date Patterns

For applicable time / date patterns, see http://momentjs.com/docs/#/displaying/format/


Some common date patterns might be:

Display	Pattern
Wednesday, October 10th, 2015	dddd, MMMM Do, YYYY
10/21/2015	l
October 21, 2015	MMMM DD, YYYY
10-21-15	MM-DD-YY
2015-10-21	YYYY-MM-DD

Some common time patterns might be:

Display	Pattern
15:36:14 EDT	HH:mm:ss z
3:36:12 PM EDT	h:mm:ss A z
03:36:12 pm EDT	hh:mm:ss a z
15:36 -04:00	HH:mm Z

Contact Us



Provides support email, phone, and feedback form information. Only one Contact Us Widget may exist on a dashboard.

Contact Us Edit Options:




Title: Edits the title of the Widget shown on the header.

Feedback Email: Sets the desired email address for the feedback form.

Note: Support phone number and email address are set from the ProVision Admin settings.


Logs

The Logs Dashboard Widget displays the most recent 'x' number of logs for a specified search term, such as resource name, task, id number, username, and so forth.



Once the Logs Widget has been added to a Dashboard, edit it by clicking the wrench icon in the upper right side of the Widget.


In the Edit menu, you may edit the Logs Widget name, enter a search term, select number of results to display, and select a log level to filter results by.



When complete, click "Apply" to save your changes.

You can preview or test specific Logs Widget search terms by entering the same term into the Admin "Logs" tab, to verify the desired term and filter set.


Markdown



The Markdown Widget is a blank slate where users may add links, text, or other content through use of the Markdown language. Multiple Markdown Widgets may exist on a dashboard.

If you are unfamiliar with Markdown, check out Markdown Basics


Markdown Edit Options:



Title: Edits the title of the Widget shown on the header.


Markdown Content: Area to enter the markdown content.

Links



Provides a list of website links. Multiple Links Widgets may exist on a dashboard.


Link Edit Options:



Title: Edits the title of the Widget shown on the header.


Links: Enter the desired link text, then the URL of the website to link. Click "Add" to add a new link, or "Remove" to remove an individual link. Hit "Apply" to save your changes.

iFrame



Set a https URL to be viewed in an iFrame. Useful to view stats or commonly referenced websites.

iFrame Edit Options:



Title: Edits the title of the Widget shown on the header.

URL: Sets the desired https address of the website to display in the frame

Advanced:

Sandboxing: Allow Scripts: Check to allow scripts.

Not all webpages allow themselves to be embedded into iframes. If the target server has set X-Frame-Options or CSP directives to prevent embedding, the widget will appear blank.

Working with Resources

Working with Resources

- Working with Resources
  - What is a Resource?
  - How to Work with Resources?
  - Additional Information

What is a Resource?


The "Resource" system is tied to the Permissions structure. What this means is that you get granular control on a resource level and can create groups around a single resource or even groups of resources. Since Resources can inherit permissions from others - it can be an easy way to categorize generic objects.

WARNING!
⚠
There are key Resources that are used by the System that should not be deleted. We have put in some safeguards in the UI, but the API can delete these resources if prompted. The resources that you should not remove are "Holding" and "Reverse". The "Available" Resource can be renamed - simply not deleted.


How to Work with Resources?

The Resource is an entity that users can assign Network Resources to (IP blocks, hosts, DNS zones, etc.). You can also create hierarchies between resources which allows you to leverage permissions to control who can view and interact with any given resource and its assigned elements. Please note that you can also have Resources that do NOT have anything assigned to them regarding Network Resources. The result of this flexible architecture is that you can work with Resources in three ways:


- **Resource Entries:**
  These are the actual Resource names. When you click the "Add Entry" button you can customize various elements of the entry and assign the Parent Resource, Section and Category from their respective dropdown menus. You may also add a Custom ID if desired. When done, hitting "Create" will pull up the field set for the chosen Section and allow you to enter the data for the given Entry.



- **Resource Sections:**
  These can be anything from "customers" to "firewalls" to "cross-connects". Since you can customize the fields for these elements, and assign them to a Parent Section, you have flexibility in organizing the data. Check out Customizing Sections and Customizing Fields for more details on how to fit these elements to your business.



- **Resource Categories:**
  Categories can be used to create some filtered views for given Resources and Sections. For example, you can create a Section called "Resource Holder" and then assign a Category "Customer". Then you can view a list of Resources that have been assigned to Category "Customer". In the same way, you could also assign a Section called "Router" under the Parent Resource "Corporate Datacenter" and then assign a Category "Infrastructure".



Want to customize Sections? Check out Customizing Sections and Customizing Fields for more details!

Some examples:

1) Service Provider

2) Managed Service Provider

3) Datacenter/Colocation Provider

4) Enterprise

Additional Information

- Working with Entries
- Customizing Sections
- Customizing Fields
- Customizing Resource Views
- Gadgets
  - XML Specifications
- Contact Manager


Working with Entries

Working with Entries

The list of Resource Entries is under the **Resources** Tab. To access it, you may either click on the Resources Tab, or select "Entries" from the Resource Tab dropdown menu.

- Working with Entries
  - Resource Tab / Entry List User Interface
    - Resource Action Menu
      - Action Menu - Single Resource
      - Action Menu - Multiple Resources
  - Chart View
  - The Resource Entry Page (View Resource)
  - Create an Entry
  - Edit or Delete an Entry
  - Export Resource Fields
    - Resource List Export:
    - Multiple Resources Export:
    - Single Resource Export:
  - Add Child Entries
  - Resource Clone
    - To Clone an Entry
  - Additional Information

Resource Tab / Entry List User Interface



Page Header Button Bar:




1) List View Buttons: Click each Resource View button to display the desired list. *Entries*, *Section*, *Categories*, *Contacts*, and *Customers* are provided by default, although custom list views may be created and pinned to the button bar.

2) Add Entry Button: Click to add a new entry.

3) Clone Resource Button: Click to clone an existing resource

4) Settings: Click to open up the settings page, where default and custom list filters, settings, column fields, and column order may be customized.

Resource List:



1) List Resource Count: Displays the number of resources in the current list view

2) List View Name: The name of the current view

3) Export Options: Click to export the list to .csv

4) Chart View: Opens a link to Chart View, which graphically shows the entries in filterable, hierarchy form.

5) List Filters: Click to expand list filter options, including Section, Category, Parent Resource, Resource Type, or Attribute Name / Value.

6) Items per Page / Pagination: Set the desired number of resources per page. Pages display at the bottom of the resource list.

7) Search: This text box allows the user to enter in criteria to filter the list of Entries. Click "match name" for an exact name match.

8) Resource Selection Box: Click to select multiple resources to apply bulk changes to. When multiple resources are selected, the actions menu will change to display options to apply to the selected resources.


9) Resource Field Columns: Each column displays a resource field. Columns with arrows next to the names may be sorted by ascending /descending values by clicking on the column name. The fields that display, as well as their order, may be customized in "Settings".

10) Resource Links: Clicking on a resource name will take the user to that resource's individual entry page.

11) Action Menu: Right click anywhere on a resource's row to open the Action Menu. The Action Menu (gear icon) gives a list of actions to perform on the resource. If more than one resource is selected, bulk edit actions will display instead.

Resource Action Menu

Action Menu - Single Resource



Opening the Action Menu in the Entry List View for a single resource will bring up the following options:

View: Opens the resource's Entry page

Edit: Opens to the resource's Edit options


Clone: Opens the clone resource page for the selected resource

Edit Attributes: Opens the edit attributes options to view or update field values for that resource

Unassign IP Addresses: Unassigns all IP addresses assigned to the resource

Delete: Deletes the resource, if appropriate permissions exist.

Action Menu - Multiple Resources



Opening the Action Menu in the Entry List View when multiple resources are selected will bring up the following options:

Export to CSV: Exports the selected resources to .csv

Edit: Opens the resource Edit options, to bulk change all resources

Edit Attributes: Opens the edit attributes options to view or update field values for the selected resources.Note: Attributes will only be able to be changed if the available fields are the same for all selected resources (in general, the resources are of the same section).

Unassign IP Addresses: Unassigns all IP addresses assigned to the resources

Unselect All: Deselects the resources


Delete All: Deletes the resources, if appropriate permissions exist.

Chart View

Chart View illustrates the resources created in a node-based tree.

Select the Top Resource, Section Type, and limit of number of resources to display from the dropdown menus, if desired, and then click "Reload".

Users will only be able to view sections of the resource tree on which they have view permissions.



While viewing the main chart, you may:

- View in horizontal or vertical tree mode by clicking the "Switch Chart Orientation" button.




- View fullscreen by clicking the "View Fullscreen" button.



- Left click and drag within the tree view, or scroll wheel in/out to change the area viewed.
- Single or double-clicking on a node with children will collapse or expand the tree at that resource.
- Clicking and dragging a resource node to another resource will relocate the resource to be a child of the resource it is dropped on.

Hovering over a specific Resource or node, then right clicking will open a context menu with the following options:



Quick View: Shows summarized details about the resource and its children, and links to the Resource Entry page(s).

Use As Top Node: Set the current resource as the Top Node of the displayed hierarchy.

Edit: Opens to the resource's Edit page


Clone: Opens the clone resource page for the selected resource

Delete: Deletes the resource, if appropriate permissions exist and no child resources/assignments exist under the resource.


The Resource Entry Page (View Resource)

The Resource Entry Page displays details for an existing Resource and any associated Gadgets. Here, users may edit the Resource's fields, clone the resource, add child resources, and perform Gadget-level actions such as assigning and managing IPAM Blocks, Contacts, generate DNS Zones, add Field information, and manage Peering Sessions.

Open the page by clicking on a Resource name from the Resource List, or select "View" from the Action Menu for the resource in the Entry List.



The Resource Entry page displays basic details about the Resource, including name, id, section, and category.



Additional information and actions are available to perform for the Resource, depending on which Gadgets are enabled for the associated Section:

Note

A few things to keep in mind on Gadgets:

- Not all Gadgets are appropriate for all Resource types - some are suited for Routers, Servers, etc.
- Some Gadgets (marked "Legacy") may not be available to new ProVision users or newer versions of ProVision.
- Some Gadgets may be specialized for very specific use cases or connect with other products.

Currently Available Gadgets:

- **ACP ("Workflows") Gadget:** Connector to ProVision's API Composer Platform. Executes selected ACP Workflows.
- **Contact Info**: Displays phone, address, and billing details for the Resource.
- **Contacts:** Assigns Contacts to the Resource from the Contact Manager.
- **DHCP Server Management (Legacy):** Manage a DHCP Server details and pools.
- **DHCP Customer Configuration (Specialized):** Assign and Configure DHCP Pools from APNIC Blocks.
- **DNS**: Lists DNS Zones associated with the Resource and links to the zone's DNSv3 page.
- **DNS Autogenerator:** Autogenerates DNS forward and reverse zones for the resource, based on assigned IP Blocks.
- **Document Storage:** Load, View, and Download assorted image or text documents.
- **Field Gadget**: View and Edit data and information fields associated with the current resource.
- **IPAM (Legacy):** Manage IP Blocks.
- **IPAMv2:** Manage IP Blocks - supports additional functionality over the old IPAM Gadget.
- **Notes:** Type and view short text notes.
- **Peer Groups**: View and assign Router Peer Groups.
- **Peering Sessions:** View and manage peering sessions.
- **Peering VRFs:** Manage Peering VRFs.
- **Resource Linkage Gadget:** Create a reciprocal link to another resource.
- **Resource Linkage - IPAM Linked IPs Gadget:** View the IPs assigned to Linked Resources.
- **Resource View:** Displays the basic Resource entry information - name, section, etc.


- **Reverse API Console:** Display custom reverse API content.
- **Tech Info:** Display NS and Technical RIR info.

From here, you can work with your selected Gadgets, performing tasks such as assigning DNS zones, IP Blocks, assign Contacts, and more.

See the Gadgets Page for detail on working with individual Gadgets.

Create an Entry


To create a new Entry, click on the "Add Entry" button from the Resource Tab / Entry List Page.




This will take you to the Add Resource screen.

Fill in the Name of your new Resource Entry, select a Section (the chosen Section determines what gadgets will show on your new resource's Entry page), the Parent Resource, Category, and enter a Custom ID number if desired.

When complete, click the "Create" button. If you wish to exit without saving your changes, click "Close".



Once the Entry is created, the **Resource Entry** page loads for that Resource, displaying whatever gadgets are enabled for the associated Section .




From here, you can work with your selected Gadgets, performing tasks assigning IP Blocks, Contacts, and more.

See the Gadgets Page for detail on working with individual Gadgets.


Edit or Delete an Entry

To edit or delete an Entry, go to the bottom of that resource's Entry Page, and select "Edit".




This will bring up the Edit Entry Page, where you can edit basic information such as Name, Section, Parent, Category, or Custom ID.

When done, hit the "Save" button.



If you wish to delete the Entry, select the "Delete" button.

You may also edit or delete an Entry from the Resource Entry List, by right clicking on the resource, and selecting "Edit" or "Delete" from the Action Menu.




Note

If an entry has children, the delete option will not be available. Child Entries must be deleted before a Parent Entry can be deleted.

Export Resource Fields


Resource List Export:

To export all resources/ resource fields displayed in a Resource List, select "Export to CSV" from the top header for the desired resource list.



Multiple Resources Export:

To export multiple resources, select the desired resources from the resource list, then open the action menu and click "Export to CSV".



Single Resource Export:

Resource Entry pages have an "Export As CSV" button that generates a .csv file containing the Resource's basic field information.

To export the Resource, click the "Export as CSV" button in the header on the Resource Entry Page.




The downloaded .csv file will contain the fields containing values from the Resource Info, Contact Info, Tech Info, and Resource Field Gadget(s), with the field name in the first column, and the field values in the second column.

	A	B	C
1	Name	A QA Entry	
2	Section	Resource Holder	
3	Category	QA	
4	Created	2019-06-27T13:32:02-0700	
5	Modified	2020-01-13T12:34:51-0800	
6	Street 1	123 Main St.	
7	City	Sometown, CA	
8	Zip	12234	
9	Street 1	123 Main St.	
10	City	Sometown, CA	
11	Zip	12234	
12	Phone Main	123456789	
13	Last Billing Date	awd	
14	Country	DZ	
15	Country	DZ	
16	Residential Customer Privacy Enable	TRUE	
17	ns1	ns1	
18	Contract Number	12345	
19	Notes	Test	
20			
21			
22			
23			

Add Child Entries


Adding a Child Entry creates a resource underneath the current resource in the hierarchy.

To add a Child Entry, at the bottom of the Resource Entry page, click "Add Child".




This brings up the Add Entry dialog. Looking at the top navigation breadcrumbs, you can see that we are adding an Entry underneath the resource "MyNewEntry".

Fill out the Name, Section, Category, and Custom ID (if desired), and hit the "Create" button. The Parent field is pre-selected for you.



Once created, the Child Entry will show in a list at the bottom of the Parent Entry page.



Resource Clone

Cloning an Entry duplicates the Entry and, if desired, any Child Entries existing under it.

This feature can be used to quickly and efficiently create multiple resources with same format, field information, or similar hierarchy structure. One example may be a datacenter with x number racks with y number of servers on each. One rack, with its servers as child entries could be created, and then cloned until the necessary quantity is reached. As text field information is copied during the clone, changes in individual server information would still need reviewed and updated. Think of cloning as creating a template from an existing Resource Entry.


Information Cloned: Format of the original Resource (which gadgets are enabled, location, fields), contact / tech information, field information, and (if selected) Child Entries, and Child Entry sections, fields, and field information - in general, items that are chosen or input at the entry creation, or input into text fields.

Information not Cloned: IP Blocks, DNS Zones, uploaded documents - in general, items that are *assigned* to the entry rather than input into fields.

To Clone an Entry

The Resource Clone feature may be accessed from either the **Resources** Tab, or from a Resource Entry page.


From the **Resources** Tab, select "Clone". This open the Resource Clone options.



You may also select "Clone" from the bottom of a Resource Entry page, in which case the Entry page you clicked "Clone" from will be automatically selected as the resource to clone.



Once on the Resource Clone Page, enter the Resource to clone, Parent Resource, and the New Name for the clone. If you wish for all children of that resource (and their children, if applicable) to be cloned, check the "Clone Resource Children" checkbox. When complete, click the "Clone Resource" button.



To repeatedly clone the resource, simply change the "New Name" field (if you want the subsequent clones to have a different name), and click "Clone Resource" again. You may repeatedly click "Clone Resource" and each click will produce a new clone.

When done, you may click on the link provided for the most recently created clone, or hit the back button from your browser to return to the parent resource.

Tip

Review the cloned resources using the chart view to see the hierarchy structure!

Additional Information

Continue on to the following pages for additional information on working with Resources in Provision:

- Working with Entries
- Customizing Sections
- Customizing Fields
- Gadgets
    - XML Specifications
- Contact Manager

Customizing Sections

Customizing Sections


You can create as many Sections as you wish (Firewall, Server, VM, Virtual Interface, etc.) and customize the Gadgets and fields that apply to each Section.

For example, you may not need to track the console port for your virtual firewall, so you would simply not use that field for the "Virtual Firewall" Section. This way you can still track the console port for your physical firewalls like normal.


- Customizing Sections
  - Step 1: Create a New Section
  - Step 2: Add a Custom Field to a Section
  - Step 3: Edit Custom Field Data
  - Step 4: Add Gadgets to your Section
  - Additional Information

Step 1: Create a New Section

Click "Add Section" from the **Sections** view button under the **Resources** Tab




Create a new Section by specifying a Name, Parent, and Category. Then hit the "Create" button.




Step 2: Add a Custom Field to a Section

Manage existing fields and add custom fields for the selected Section by opening the Action Menu for the section, then clicking "Edit".




Add existing or Custom Fields for your Section. You can add new Custom Fields of different types (text input, text area, choice box, radios, checkbox) by dragging and dropping the fields as well as using any existing fields that are available. See the Customizing Fields page for more details.



Step 3: Edit Custom Field Data

Select the field name and you will get an editing window to modify the parameters of the field. Custom fields may be renamed and have other attributes updated, whereas protected system fields may have noted restrictions.




Any fields enabled here will be available to add to the Field Gadget, if desired.

Step 4: Add Gadgets to your Section

You will notice on this customization screen that you also have an area for Gadgets. Gadgets are modules of additional functionality that can be added to the UI of a given Resource. Simply select the Gadget you want to show for that section, hit "Add".



Once added, you may organize them by dragging into the order you wish them to appear on the page. You may also remove added Gadgets by clicking the "delete" icon.



When done, click "Save".

Once added to the Section, Gadgets will be visible for all Resources of that Section.

For a detailed list of gadgets and descriptions, see the Gadgets page.

Additional Information

Continue on to the following pages for additional information on Resources in Provision:

- Customizing Fields
- Gadgets
- Contact Manager

Customizing Fields

Working with Fields


Fields are individual pieces of data that you can associate with a particular Section. For example, you may want to have "Operating System", "Make", and "Model" fields for a server or device. Provision includes many default fields to choose from, but you may also create custom fields and edit fields to suit your needs.

Once a field is added to a particular Section, it will be available add to the Field Gadget for later to edit, manage, or remove.

- Working with Fields
  - Add Existing Field to a Section
  - Add Custom Field to a Section
  - Editing/Removing Fields
  - Using the Field Gadget
    - Manage Resource Fields
    - Exporting Fields
  - Additional Information


Add Existing Field to a Section

To add an existing field to a Section, select the field name from the dropdown menu and click on the "Add Field" button.




Add Custom Field to a Section

To add a new custom field to a Section, simply click on the custom field type name (Text Input, Text Area, Choice Box, etc), then drag the field over to the field list and release in the desired location. Edit the field name and options as described in Editing / Removing Fields.




Editing/Removing Fields

Once fields are added to a Section, you can click on the field name to make additional changes to the fields. Custom fields may be renamed and have other attributes updated, whereas protected System Fields may have noted restrictions.




To rearrange the field list order, click and hold on the field name, then drag and drop into the preferred order.

To remove a field, click and hold on the field name, then simply drag and drop the field to the right side of the screen to where the "Remove Field" prompt is visible.



Using the Field Gadget

The Field Gadget displays the information fields that been added to the Section, and have been added for the specific Resource that is being viewed.




Users may add enabled fields to the resource, edit field values, and remove fields from the Resource through this Gadget. Field values in this Gadget (such as Hostname, Username, and Password, among others) may also be used by other Resource Gadgets and Provision modules.

Manage Resource Fields

The Field Gadget and the individual fields must both be enabled and added to the Resource's Section before they can be used in the Field Gadget on the Resource Entry page.


Once the fields are added to the Section, they will be available to add to the Field Gadget for any Resource of that Section, from the Field Gadget's "Add New Field" dropdown.

To Add, Edit, or Remove fields, click the "Edit" Button at the bottom right corner of the Field Gadget.




To add an available field to the Gadget, select one of the available fields from the "Add New Field:" dropdown, then click "Add".

Once added, the field will be available to edit or remove.



Edit the field value(s) by typing into the input box, and/or selecting the desired option, then click "Save". You may also remove a field from the gadget by clicking "Remove" - it will be available to re-add later, if needed.



When done with your edits, click "Save" to return to view mode.

Exporting Fields

Resource Entry pages have an "Export As CSV" button, which generates a .csv file containing the Resource's basic field information.

To export the Resource, click the "Export as CSV" button in the header on the Resource Entry Page.



The downloaded .csv file will contain the fields containing values from the Resource Info, Contact Info, Tech Info, and Resource Field Gadget(s), with the field name in the first column, and the field values in the second column.

	A	B	C
1	Name	A QA Entry	
2	Section	Resource Holder	
3	Category	QA	
4	Created	2019-06-27T13:32:02-0700	
5	Modified	2020-01-13T12:34:51-0800	
6	Street 1	123 Main St.	
7	City	Sometown, CA	
8	Zip	12234	
9	Street 1	123 Main St.	
10	City	Sometown, CA	
11	Zip	12234	
12	Phone Main	123456789	
13	Last Billing Date	awd	
14	Country	DZ	
15	Country	DZ	
16	Residential Customer Privacy Enable	TRUE	
17	ns1	ns1	
18	Contract Number	12345	
19	Notes	Test	
20			
21			
22			
23			


Additional Information

Continue on to the following pages for additional information on Resources in Provision:

- Gadgets
- Contact Manager

Customizing Resource Lists

Customizing Resource Views




The list of Resource Entries is under the **Resources** Tab. To access it, you may either click on the Resources Tab, or select "Entries" from the Resource Tab dropdown menu.

Five resource view lists are provided by default, including "Entries", "Sections", "Categories", "Contacts", and "Customers", and users may either edit the provided views or create additional custom views from variety of filter and attribute column options.

- Customizing Resource Views
  - Resource List Views Settings
    - Default Views
    - Resource View List
      - Filter
      - Pin / Unpin
      - Create a New View
      - Clone an Existing View
      - Delete an Existing View
    - Set Default Filter Values
    - Set Default Columns
      - Select Field(s) to Add
      - Toggle Column Visibility
    - Reorder Columns
    - Remove Columns
    - Resize Columns / Additional Options
    - Rename Columns
  - Additional Information


Resource List Views Settings

To view, edit, or create resource views, click on "Settings" from the Resource List header bar.



The settings page consists of three main areas: A list of existing resource Resource Views on the left sidebar, the Default Filter Values for the selected Resource View at the top center, and the Default Field/Column settings at the bottom center.

These settings may be changed for any Resource View, including the default Views. You may also create a new view at any time by clicking "Add View" at the top page header.



Default Views

Five default Resource Views are provided, and are automatically pinned to the top header bar for quick access:

Entries: Displays resource entries. Applied filter: Resource Type = Entry

Sections: Displays ProVision sections. Applied filter: Resource Type = Section

Categories: Displays ProVision categories. Applied filter: Resource Type = Category

Contacts: Displays ProVision contacts. Applied filter: Resource Type = Contact

Customers: Displays the customer list. Applied filter: Category = Customer

For all of the default views, the default column fields include:

- Id (id)
- Slug (slug)
- Name (name)
- Parent Id (parent_id)
- Parent Name (parent_name)
- Category Id (category_id)
- Category Name (category_name)
- Created (date)
- Modified (modified)


Users may edit the filters or default column settings to customize any of the default views, as well as pin/unpin the view to the header bar. However, the name may not be changed or the view deleted.

Resource View List

All existing views are listed on the left sidebar of the page under "Resource Views".

Filter


To filter the view list, type all or part of the view name into the search bar, and the list will filter down to relevant results.




Pin / Unpin

To Pin / Unpin a Resource View to the top header bar (where it will display as a button), right-click on the view, then select:

"Pin to top bar" to add a bar button for the view, or "Unpin from top bar" to remove an existing header button.




If custom views are pinned, they will be visible in a second button row by clicking the expand (...) button in the page header:




Create a New View

To add a new Resource View to the list, click "Add View" at the right side of the header bar.



A new "untitled" view will be added to the view list, with no default filters applied and standard default columns enabled.


Click on the "untitled" view in the list to select it. To rename the view, click the view name above "Default Filter Values" and type the new name.



From here, you may either save the view and exit out, or continue on to apply specific filters to the view, display field attributes as columns, and adjust column order visibility.


Clone an Existing View

You may clone an existing Resource View by opening the view, scrolling to the bottom of the view settings, then clicking "Clone".



The view will be cloned, along with all of its existing filter and column settings.

The new view will be named "(Previous View Name)-cloned", and will immediately be added to the Resource View list.



If further edits are needed to the view, edit the filters and/or columns as desired, and click "Save Changes".



Delete an Existing View

User-created Views may be deleted by clicking the "Delete" button at the bottom right of the view settings.




Default views may not be deleted.

Set Default Filter Values

Default filter values allow you to fine-tune which resources display in your Resource View. If you'd like to have all resources visible in your view, you may leave all fields blank, or enter any combination of filters to narrow down the resulting list.

You may even restrict your view to only show those resources that have a particular value for an attribute, by entering the attribute (field) name obtained from the resource's section setup, and the specific value for that attribute that the resource should have.



Available filter values include:

Resource Type: Chose from Section, Entry, Category, or Contact.

Parent: Enter a parent resource to limit the list to only resources with that parent.

Section: Select a resource section, such as Resource Holder, Server, Rack, VM, or any custom section from your ProVision instance.

Category: Select an existing category, such as Customer, Internal, or any custom category that has been created.

Attribute Name: Type an attribute name to limit the results to only resources with that attribute. See: "Find the Attribute Name information box, below".

Attribute Value: Type an attribute value to limit the results to only resources with that value for the attribute. Select "Match Value" to limit results to exact attribute value matches.

Once you have selected the desired filter(s) for your view, be sure to click "Save Changes" at the bottom of the page!

Finding the Attribute Name

Note: The attribute name is the system slug designation for the attribute, *not* the display name shown in column headers or field labels.

Slugs are unique ids entirely in lower-case lettering, and use dashes or underscores instead of spaces.

To find the attribute slug, go to the Edit Section page, and look for either of the following areas for the desired field:

1) Click on the field name label (here: "Hostname") for a field that has already been added to the section, to open the field details information box:




The field attribute slug will be listed under "Slug" - here, the slug for "Hostname" would be "6c-network-fqdn"

2) If the field has not yet been added to the section, you may view the field name with field slug after it, in parentheses, in the "Add Existing Fields" selection box:




Here, the slug displayed for "2nd Email" is "6c-contact-email2".

Once the attribute name and value has been entered as filter conditions, it should look like this:




The resulting view list will then display only the resources with "QA1.6connect.com." entered for the Hostname (6c-network-fqdn) field:



Set Default Columns

Default Column settings allow you to choose which resource fields are displayed as columns, as well as the column order, name, and visibility settings.




For all of the default views, the default column fields include:

- Id (id)
- Slug (slug)
- Name (name)
- Parent Id (parent_id)
- Parent Name (parent_name)
- Category Id (category_id)
- Category Name (category_name)
- Created (date)
- Modified (modified)

These default columns may be reordered, renamed, or be hidden, but they may not be deleted. You may, however, hide any unwanted columns and add custom fields to display only the specific information you wish to see in your view.

Select Field(s) to Add

You may add any existing resource field as a column for a view. In the "Select Field" input box, click and search for the field name you wish to add:



Once selected, the field will automatically be added to the bottom of the column field list, and automatically set with visibility to "off".

Create New Fields


Note: If you would like to create a new custom field to display as a column, you must first create the field for the desired section. Then, the new field will be available to select as a column.

For additional information on creating fields, see Customizing Sections and Customizing Fields.

From here, you may add or edit additional fields, or click "Save Changes" to save your changes.

Toggle Column Visibility

To toggle column visibility on or off, click the "eye" icon on right side of the field row.




Fields that have visibility turned off will display as a red bar, whereas visible fields will be grey bars.

Reorder Columns


To reorder columns, click on the "list" icon (three horizontal lines) on the far left of the field bar, then drag the bar to the desired location in the list.

Release the mouse button when it is placed in the new location.



Remove Columns

Default columns are not able to be removed (you may hide visibility, instead), but user-added columns may be removed by clicking on the "delete" icon (trash can) for the desired field.




Resize Columns / Additional Options

Additional options exist to manage column sizing and behavior. Click the menu icon (three dots) on the right side of the field bar.




This opens the "More Options" box. From here, you can set a specific minimum pixel width for the column, or enable/disable drag resizing in the field view.



When done, click "Update", or click "Close" to exit without saving your changes.

Rename Columns

The display name for any column may be renamed by simply clicking inside the name box, and typing your changes.



When done, click "Save Changes".

Additional Information

See the following pages for additional information on working with Resources in Provision:

- Working with Entries
- Customizing Sections
- Customizing Fields
- Customizing Resource Views
- Gadgets
- Contact Manager

Gadgets

Gadgets

- Gadgets
  - What are Gadgets?
    - Adding Gadgets to a Section
  - Available Gadgets
    - ACP ("Workflows") Gadget
    - Contact Info
    - Contacts
    - DHCP Server Management (Legacy)
    - DHCP Customer Configuration
    - DNS
    - DNS Autogenerator
    - Document Storage
    - Field Gadget
    - IPAM (Legacy)
    - IPAMv2
    - Notes
    - Peer Groups
    - Peering Sessions
    - Peering VRFs
    - Resource Linkage Gadget
    - Resource Linkage - Linked IPs Gadget
    - Resource View
    - Reverse API Console
    - Tech Info
  - Creating your own Gadgets
  - Additional Information

What are Gadgets?

Gadgets display on the Resource Entry page, providing information or actions for various ProVision modules. They are best described as self contained webapps; widgets but with more power. Gadgets can have their own fields, HTML templates, and even accompanying scripts and stylesheets. They can interface with the API to display simple information such as the resource Section, or they can perform much more complex functions, such as IP assignment in the IPAM Gadget.

Gadgets are enabled per Section, so that the Gadgets that display in the UI may be different for various section types - A resource with the "Server" section would have different display and functionality needs than a resource using the "Resource Holder" resource.


Adding Gadgets to a Section

In order to display on a Resource Entry page, Gadgets must first be added to a Section - see Customizing Sections for detailed instructions.

When editing a Section, navigate to the "Manage Gadgets" area at the bottom of the page, select the Gadget you want to show for that section, and hit "Add".



Once added, you may customize the order you wish them to appear on the page by dragging and dropping into the desired order.



When done, click "Save". Once added to the Section, Gadgets will be visible for all Resources of that section.


To view the Gadgets, open the Resource Entry page for any resource under that section.

For additional details on editing sections and enabling Gadgets, see Customizing Sections.

Available Gadgets

ACP ("Workflows") Gadget

The ACP Workflow Form is a Gadget connecting 6connect's ACP (API Composer Platform) with the ProVision interface to run Workflows.




It allows users to specify and execute Workflows created in the ACP product on a ProVision Resource Entry page.



See below for additional details on setting up and working with the ACP Workflow Form:

Setting up ACP Access in ProVision

Before using the ACP Workflow Gadget, you must set the ACP URL and user credentials in Admin Admin Preferences.



Enter the ACP URL for a licensed ACP instance, then provide the ACP Username and Password for the user that should be used to execute Workflows. To verify the account, click "Test Configuration" - you will be notified whether the account is valid.


When done, click "Update".

After setup, the ACP Workflows Gadget will load with the available Workflows from your ACP instance, and can be configured to select which Workflow and inputs you wish to use.

Configuring the ACP Workflow Form


The ACP Workflow form is access from the Edit Section page, under "Manage Gadgets".

Once ACP settings have been added to Admin Preferences, the "ACP Workflow Form" Gadget can be added to a Section, and Workflows from the associated ACP instance will be available to select. containing fields to select the desired Workflow to Run, Title, and map input options.



Select a Workflow, then edit the title to display on the gadget and map input options. Input options will vary according to the selected Workflow.

You may also choose to refresh the page once the workflow execution is complete, and/or show JSON results.



Multiple Forms may be added to a Section, in order to run additional Workflows or option settings. When complete, click "Save".

Working with the ACP Workflow Form

Once enabled, the Gadget will show on the resource page for any resource of the section type.

Input the field data necessary for the Workflow - here, it's adding a hostname - then click "Execute Workflow" to process the chain of workflow calls.



If "Display JSON Results" has been enabled, a display modal will appear showing the JSON response of the executed workflow.



When done reviewing the response, click "Close".


If the page has not refreshed, you will see a message informing you whether the Workflow has successfully executed.



In this example, a "Customer Turn-Up" Workflow was selected (created in ProVision's ACP product) that performed six functions with one button click. The successful "Execute" for "Customer Turn-Up" created a new customer resource entry, assigned IPv4 and IPv6 blocks to them, created a DNS zone for the hostname, and lastly created 'A' and 'AAAA' records for the zone.

Contact Info


This Gadget is used on the Resource Holder Section type. In the Contact Info Gadget, you can track information such as mailing / billing addresses, phone number, and fax number for that Resource. You may also add a separate GEO IP address, if desired.



Contacts

The Contacts Gadget may be used on any Section type to assign a contact (from the Contact Manager) to a Resource.


To assign a contact, search for and select the desired contact in the search box, then click "Assign". The Contact will show in the list below.



Contacts Action Menu:

The Action Menu (wrench icon) in the contacts gadget has three options:

Set Role: Opens a dialog box to select a role to assign to the contact, add a new role, or delete an existing role.



Unassign: Unassigns the contact from the resource

View: Redirects to the contact's detail page in the Contact Manager

Refer to the Contact Manager page in the documentation for more detail on working with the Contacts gadget and the Contact Manager.

A Note on Permissions

The ability to view and assign a contact to a resource is restricted by the Parent assigned to the contact upon creation. If a user does not have permissions for a contact's Parent Resource, that contact will not be able to be viewed / assigned via the gadget.


DHCP Server Management (Legacy)

The DHCP Server Management Gadget has functionally been replaced by the **DHCP** Tab updates in version 7.0.0.

Although the DHCP Management Gadget may still be used, we recommended checking out the **DHCP Groups**, **DHCP Servers**, and **DHCP Pools** pages instead for an improved user experience.


The DHCP Server Management Gadget should be used with the "Server" Section.

When initally added to the section, it will show in the "Off" configuration:




To enable the DHCP Management Gadget, select the "On" radio button next to "DHCP Services", and click the "Update" Button.

The DHCP Management Gadget in the "On" configuration:



Each of the sections in the DHCP Management Gadget - Group Management, Connection Configuration, Server Details, Scan Server, DHCP Pools, and Create a New DHCP Pool - may be expanded to change settings in each area.


Additional sections may appear in the Gadget once unpushed or pushed configurations are saved:



For detailed information on working with the DHCP Management Gadget, see DHCP Tab - Managing DHCP Server Configurations.

DHCP Customer Configuration

The DHCP Customer Configuration Gadget allows users to assign IP aggregates to the DHCP server pools and generates DHCP Server Configuration changes depending on the tag(s) and DHCP options selected.



These configurations are then sent to the associated DHCP server Management Gadget as "Unpushed Configurations", where they may be held until a manual or schedule push occurs.

Before You Begin

Before using the DHCP Customer Configuration Gadget, the following should be set up in ProVision:

- The associated DHCP server should be created in ProVision and set up in the DHCP Management Gadget or **DHCP** Tab - **DHCP Servers** list (See: **DHCP** Tab).
- Add the DHCP Customer Configuration Gadget to the desired Section. You may want to create a specific "DHCP Customer" Section for DHCP customer entries (See: Customizing Sections).
- Have, or set up APNIC Aggregates for DHCP use from the **IPAM** Tab with the desired IP space type, Region(s), Tags, and any desired VLAN criteria. Regions are a required field when assigning IPs from the DHCP Customer Configuration Gadget. Any APNIC aggregate may be used for DHCP, so you may want to create a "DHCP" IPAM Tag to help denote the desired aggregate(s).
- If you are planning on Direct Assigning the DHCP blocks in the Customer Configuration Gadget, ensure that the desired blocks in the DHCP are split to individual /32 or /128 size. Smart Assign and Smart Browse will automatically split the block to assign the correct size.

Associate with DHCP Server


Once the Gadget is enabled, the first step is to associate it with an already-created DHCP server in ProVision. Select the DHCP Server to link to, and click "Continue".



Assign IP's

Next, Assign IP's for Pools from DHCP Aggregates. You may Direct Assign, Smart Assign, or assign from Smart Browse based on the selected criteria.


Once assigned, a Pool Name will be automatically generated under "Resource". Pools may be unassigned by clicking the "Unassign" button.




Set up Configuration

Once IP's have been assigned, the "Configuration" tab will appear. Click on the tab, and then select or deselect the DNS Server associated with the Customer, add Option 82 Elements, Add Circuit ID text, and add notes if desired. Use the "Preview" field to confirm the accuracy of the data, and select the status as "Activate" or "Terminate".

When done, click "Update Configuration". The configuration will be sent to the associated DHCP server's DHCP Management Gadget.




Reviewing and Pushing Configuration Updates
When a configuration has been saved from the DHCP Customer Configuration Gadget, it will appear as an "Unpushed Configuration" in the DHCP Management Gadget for the DHCP Server. If you expand that option, you will see the config elements highlighted – red are config elements that will be deleted, green are config elements that will be added.



At this point, an Admin user may manually push the updated configuration, or use a scheduled DHCP push task to automate the pushes.

DNS

This gadget is used on the Resource Holder Section type. The DNS Gadget shows zones that have the current Resource Holder set as their parent, and provides links to the zone's View Zone page.




To go to the View Zone page, you may either click on the zone name, or click on the Action Menu (wrench icon) and select "View Zone".

For more information on DNS functions and managing zones, refer to the documentation for the DNS Tab.

DNS Autogenerator


The DNS Autogenerator Gadget uses the Hostname field (6c-hostname-fqdn) of the Resource to generate a list of DNS forward and reverse zone entries based on the blocks assigned to the Resource in the IPAM Gadget It will generate a list of potential zone records - just select the ones you want to create, save the changes and you are ready to push the zones.



Enabling the DNS Autogenerator

To set up this Gadget, ensure that the Section of the Resource (typically, "Resource Holder"), has the "Hostname" field (6c-hostname-fqdn) and the DNS Autogenerator Gadget added to the Section. (See: Customizing Sections and Customizing Fields).

Then, check that the Resource itself has information entered into the "Hostname" field. If the field is already filled out, it will show in the "Fields" information area at the bottom of the Resource Entry page. To add or edit the hostname, click "Edit" at the bottom of the resource entry page, add the information to the Hostname field, and click "Save".




Once a hostname has been associated with a Resource, and the page refreshed, the DNS Autogenerator Gadget will be visible.

Before you Begin


Before starting, check that the blocks assigned to the Resource in the IPAM Gadget are correct and up-to-date - the Autogenerator uses these blocks to create the records. If using a DNS Group other than "Default" to hold zones, ensure that the desired DNS Group to hold the generated records has been set up. (See: Working with DNS Groups).

Working with the DNS Autogenerator

One enabled and visible, the DNS Autogenerator Gadget will initially show a short description, the hostname, and a button to "Autogenerate Records".




When ready, click the "Autogenerate Records" button. The Gadget will search through the blocks in the IPAM gadget and provide a list of found blocks.




Add Subdomain / DNS Group

Next, add in a subdomain if desired (optional), and select the DNS Group to hold the records (required). Click on the listed blocks to select (highlighted green) or deselect (grey) for DNS zone / record creation.



Save and Push


Finally, hit the "Save" button at the bottom of the gadget - the selected forward and reverse DNS records will be created and added into the DNS Group, viewable in the DNS Tab.



At this point, you may choose to immediately push the autogenerated zone(s), schedule a push, or re-run the workflow to edit the subdomain or group.

Document Storage


The Document Storage gadget allows you to upload documents to a resource, and have those documents accessible to download from the 6connect cloud to your local machine. It may be enabled on any Section type.




Upload Files

First, ensure the Document Storage gadget is enable for the Section type. Then, select the "Uploader" tab under the Document Manager gadget.


Click on the "Choose Files" button, and select the file(s) you would like to upload.



The selected files will show in a list under the Uploader tab. To upload the file(s), click on either the "Upload" button adjacent to the file to upload the individual file, or the "Upload All" button to upload all files listed. You may also choose to remove files from the upload list, or cancel.




Once the progress bar is filled in, your upload is complete! Your files will show under the "Files" tab.



Download Available Files

Successfully uploaded files are listed under the "Files" tab of the Document Manager gadget. From here, you can see the file Name, Size, Type, Date, and available Actions.

To download a file to your local machine, ensure you are on the "Files" tab, then click on the "Download from Cloud" icon.




If a file is no longer needed, you may delete the file from the Document Manager by clicking on the Delete (trash can) icon.

Note: The uploader has a file size limit of 14mb, files above this size will not successfully upload.

Field Gadget

The Field Gadget displays the information fields available for the Section and added to the specific Resource that is being viewed on the Resource Entry page.

Users may add enabled fields to the resource, edit field values, and remove fields from the Resource through this Gadget. Field values in this Gadget (such as Hostname, Username, and Password, among others) may also be used by other Resource Gadgets and Provision modules.




Before You Begin

First, ensure that the Feld Gadget has been added to the section - see "Adding Gadgets to a Section" at the top of this page, or go to Customizing Sections for detailed instructions.

Then, fields must be enabled and added to the Resource's Section in order to be used in the Field Gadget.


Fields enabled in a Section (pictured below) will be available to add to the Field Gadget for any Resource of that Section.




Working with the Field Gadget

Once the Field Gadget has been added, and fields have been enabled for a Section, the Field Gadget will display on the Resource Entry page for a resource of that section.


To add all or some of the enabled fields to the Gadget, navigate to the Resource Entry page, and click the "Edit" Button at the bottom right corner of the Field Gadget.




Then, next to "Add New Field:", select one of the available fields from the dropdown, and click "Add".



Continue to add the desired fields to display for this specific resource.



Once added, the field will be available to edit or remove. Edit field value(s) as desired, then click "Save".




IPAM (Legacy)

The IPAM Gadget has functionally been replaced by the IPAMv2 Gadget in version 7.0.0.

Although the original IPAM Gadget is still able to be used by existing customers, we recommend switching to the IPAMv2 Gadget for improved speed, filters, and UI customization options.


This gadget is used on the Resource Holder Section type. IPAM Gadget allows you to view, assign, and manage blocks for that resource.

For more information on assigning and managing blocks, see Working with IP Blocks - Assigning IP Space.



IPAMv2


The IPAMv2 Gadget is used on the Resource Holder Section type, and allows you to view, assign, and manage blocks for that resource. As of ProVision 7.0.0, it replaces the previous IPAM Gadget.



It contains improvements over the original IPAM gadget, such as improved speed, pagination, advanced filters, sortable columns, reverse zone generation, customized column order/names, and custom data fields.


Using this gadget, you can:

- **Direct Assign** with or without additional filtering options. In cases where duplicate blocks exist, using the filter options with Direct Assign allows you to specifically control which of the dupilicate blocks is assigned.
    - To open the Direct Assign section of the Gadget and the advanced options, click the expansion caret in the upper right section, and then click "Advanced Options".




- **Smart Assign** with or without additional filtering options. Required fields for Smart assign are: "Type", "RIR", and "Size", but additional fields such as "Region", "VLAN", "LIR", "Resource" (for blocks that allow subassignments), and various "Tag" mode options.
- **Smart Browse** using smart assign filter options to bring up a browsable list of blocks meeting that critera, from which you may assign or assign out of.


- To open the Smart Assign / Smart Browse section of the Gadget and the advanced options, click the expansion caret in the upper right Smart Assign section, and then click "Advanced Options".



- **View, Filter, and Sort Assigned Blocks** for the resource via the "IP Blocks" list.
  - To Filter: click the "filter" link in the top right area of the header to open filter options. Enter your desired criteria and hit "Apply".




  - To Sort: Click on the header name you wish to sort by, and the field will toggle between ascending and descending order.




- **Manage Assigned Blocks** for the resource by going into the "IP Blocks" list, and using the Action Menu (Gear Icon) to perform actions for the selected block.

All options available in IPAM Manage for a block are also available in the IPAM Gadget Action menu, although the "Templates" option will be applicable in the IPAM Gadget.



- **Edit Multiple Blocks:** by shift-clicking or cmd-clicking to select multiple blocks, and then right click to show the multi-block Action options, then select "Edit". The Edit Block Attributes screen will display.




For more information on assigning and managing blocks, see Working with IP Blocks - Assigning IP Space.

Notes


The Notes Gadget is a simple text area box, where you can save text notes relevant to the Resource.

To save a note, just click inside the note box, type the desired notes, and click the "Save Notes" button.




Peer Groups

The Peer Group Gadget allows you to add peer groups for IPv4 and IPv6 for a selected exchange from a router's Resource Entry page.



To do this, simply select the exchange, type in a Peer Group name in the text box, select IPv4 or IPv6, the click "Add Group".

Peer Groups added from this gadget will be then be available to select in the "Add Session" dialog box in the **Peering** tab.



Note

Peer groups listed in the Gadget are for ProVision only and should reflect groups that exist on the router.

Adding or deleting peer groups from the Gadget will not add or delete them on the router.

For additional information on Peering, see Peering v2.

Peering Sessions

This Gadget is used on the Router Section type. From here, new sessions may be added by clicking on the "Add Session" button, then entering session information into the "Create New Session" page.



Existing sessions may be managed by clicking on the "View" link for the session, bringing up the Peering v2 session details page.




For additional information on Peering, see Peering v2.

Peering VRFs

The Peering VRF Gadget allows you to add VRFs from a router's Resource Entry page.




Enabling "VRF Support" in the Admin home page under "Peering Settings" will automatically add the VRF gadget to the router Section.



The VRF gadget will then be accessible in a router's Resource Entry page.



To add a VRF, type the VRF name and ASN, then hit "Add VRF".




To delete a VRF, click on "delete" next to the VRF entry in the gadget.

Once VRFs are set up for a router, the source ASNs for the associated VRFs will appear in the Source ASN dropdown when adding or editing a session for that router from the **Peering** tab.
Peering VRF currently only supports Cisco routers.

Resource Linkage Gadget

The Resource Linkage Gadget allows you link a Resource to other Resources, and display the links in one place, without needing a hierarchy relationship.This gives you more flexibility to centralize data without requiring direct relationships. By default, all links created in the Resource Linkage Gadget are reciprocal.

The Resource Linkage Gadget also provides information to the Linked IPs Gadget - Resources linked here will have their IP Block information displayed in the Linked IPs Gadget.




Working with the Resource Linkage Gadget

To use the Resource Linkage Gadget, first, ensure that "Resource Linkage" is enabled under "Manage Gadgets" for the Section type of the Resource being used.


At this step, an empty Resource Linkage Gadget is displayed on the Resource's Entry page.

Add a new link by clicking the "Add New" button.



Search for the desired Resource to add, select, type in a note, and click "Add new linkage". A reciprocal link will be created, and the linked Resource will show in the Resource list for the gadget.


To follow the link, simply click on the resource name for the linked Resource.




Once a resource link has been created, you may also edit the comment or delete the link.

Edit a Resource Link

Editing a link allows for changes to be made to the associated comment - just click on the action menu (gear icon) for the link, then select "Edit".



Type in the desired comment change, and click "Save" when complete. Or, you may exit out by clicking "Cancel".




Export Linked Resource Fields to .csv

Resource field data for a linked Resource may be exported to a .csv file. This includes basic resource metadata, such as the resource's Name, Section, Category, Created Date, and Modified Date.

If the resource also contains data in custom resource fields (fields that have been added to the Resource Field Gadget, and filled in), those fields will also be contained in the export.


To export, click on the action menu and select "Export to .csv" - the file will download via your browser.



Copy Link Data

You may copy either a single row of data, or the entire table, to the clipboard to paste into another application.

To copy the entire table, click "Copy table content" at the top of the gadget. To copy only a single row, open the action menu (wrench icon) for the row, and select "Copy row".




Then paste the data into the desired application.

Delete a Resource Link

To delete a Resource Link, click the "Delete" button for the desired link in the list, and confirm the delete in the message that appears.

Deleting a resource link also deletes the reciprocal link from the other resource's page.




For additional information on working with Sections and Fields, see Customizing Sections and Customizing Fields. For adding field data to the Resource Field Gadget, see the "Resource Field Gadget" section on this page.

Resource Linkage - Linked IPs Gadget


The Linked IPs Gadget lists IP blocks assigned to Resources linked under the Resource Linkage Gadget, with a link to the resource holder.

Block information may be refreshed by clicking the "Reload" button to check for changes.



Resource View


This Gadget is used on the Resource Holder Section type. The Resource view displays and provides links for the Section and Category for the Resource.



Reverse API Console


The Reverse API Console Gadget allows you to add endpoints from a Resource Entry page, and view customizable javascript displays set for the selected endpoint. The Reverse API Console may be added to any type of Section / Resource, and must be enabled for a Resource for certain rAPI processes to successfully complete.

After adding the gadget to a section, the Reverse API console will appear as whitespace with the option to add an endpoint display. Endpoints must already be created via rAPI or through the Admin Reverse API interface in ProVision to be selectable via the gadget.



Selecting an Endpoint and clicking "Add" will allow the javascript display code (added via rAPI or the Admin Reverse API interface) associated with that endpoint to display on the Resource Entry page.


An example display might be integrating Observium to display server status modules and alerts for Resources with the "Server" Section:



As a completely customizable area, displays can be designed to meet individual Resource needs - create charts, alerts, command buttons, or any other type of data that you wish to view.

Tech Info

This visual element is used on the Resource Holder Section type. This Gadget allows you to list DNS servers, ARIN information, and enable /disable customer privacy.



Creating your own Gadgets

6connect provides XML specifications for users interested in creating their own gadgets for ProVision. See the XML Specifications section linked below for more information.

User created gadgets are not supported at this time and the specification below could change without notice. If you want to make your own gadget, please get in touch so we can help you

- XML Specifications

Additional Information

Continue on to the following pages for additional information on Resources in Provision:

- Contact Manager

XML Specifications

XML Specifications

THIS IS AN EXPERIMENTAL FEATURE

User created gadgets are not supported at this time and the specification below could change without notice. If you want to make your own gadget, please get in touch so we can help you.

- XML Specifications
  - XML Specification
    - Implemented Tags
    - Example
    - Fields

XML Specification

The XML gadget specification is based on the Atlassian Gadgets.

Implemented Tags

The implemented tags and corresponding attributes are:

- ModulePrefs

  Description
  - title
  - width - "full" or "half" are the only options for now
- ContentSources
  - type - "file" uses the file given in src, "html" uses the content in the tag (eg. <Content type="html">This is the content</Content>)
  - src - relative filename or url
- Source
  Fields
  - type - "css" or "javascript"
  - src - relative filename or url
- Field
  - slug

Example

```
<?xml version="1.0" encoding="UTF-8" ?>
<Module>
    <ModulePrefs title="Contact Info" width="half" />
    <Description>This gadget adds a field editor for fields related to contact info (phone, address, ect).<
/Description>
    <Content type="file" src="template.html" />
    <Sources>
       <Source type="javascript" src="script.js" />
    </Sources>
    <Fields>
       <Field slug="6c-resourceholder-phone-main" />
       <Field slug="6c-resourceholder-phone-fax" />
    </Fields>
</Module>
```

Fields

If a gadget uses fields, you can optionally add the slug of the field in this section to hide it from the main field list.


This can be very useful and make your Resource Sections easier to work with. If the fields are not hidden, this can lead to long lists of redundant data in multiple places and can cause confusion. However, all viewing and editing of the field will have to be done through the

gadget. If your gadget uses a field in a read-only manner, then you should **not** add it to the gadget's manifest because that would prevent users from editing the field data through the standard edit page.

Contact Manager

Contacts

View the Contacts list by clicking "Contacts" from the **Resource** Tab, or from the Resource tab dropdown menu, under "Contacts". The Contacts list displays existing contacts and provides options to import new contacts into ProVision. You can create new contacts manually, or import contacts from RIR. Contacts may then be assigned to ProVision resources through the Contacts Gadget.



- Contacts
  - Working with Contacts
    - View Contact Details
  - Create New Contact
  - Import Contact from RIR
    - 1) Select RIR / Type
    - 2) Enter Point of Contact Handle
    - 3) Verify and Add
  - Edit or Delete Contact
- Working with the Contacts Gadget
  - Assigning a Contact to a Resource
    - Assign the Contact
    - Create a Contact Role
    - Assign a Role to a Contact
    - Delete a Role from the Roles List
  - Unassign a Contact
  - View the Contact Details Page


Working with Contacts

View Contact Details

To view the contact details, click on the contact's name in the Resource Contact List. You will be taken to the contact details page.

A Local contact created in ProVision will have modules shown for Address, Email/Phone, and Comments, as well as a list of any resources that contact is assigned to via the Contacts gadget.

You may edit or delete a Local contact by clicking the "Edit" button at the bottom of the page.




A contact imported from a RIR will have its details shown as determined by the imported RIR module - this data is not editable in ProVision.

You may delete the contact by clicking the "Delete" button at the bottom of the page.




Create New Contact

You can manually create a new contact in ProVision by clicking on "Add Contact" from the Contacts List View.



Fill in the contact's information for Name, Parent Resource (if desired), Phone, Custom ID, Email, Address, and Comments if desired.




When done filling out the information fields, hit the "Create" button to save your contact.

Parent

The parent field relates the contact to a resource's permissions structure, only allowing users with permissions for that resource to view and assign the affiliated contact(s). To allow the contact to be viewed globally in ProVision, check the "Global Contact" box above the Parent Field.

Import Contact from RIR

To import a contact from ARIN or RIPE, click the "Import from RIR" button from the contacts page.




1) Select RIR / Type

Once on the the Import from RIR page, on the left hand side of the page select the RIR from which you wish to import - ARIN or RIPE.




If you select RIPE, you will also be prompted to choose whether you are importing a "Person" or "Role".



2) Enter Point of Contact Handle


After selecting the RIR / Type (if applicable), enter the ARIN or RIPE Point of Contact Handle for the contact you are importing, then click "Search".

Point of Contact Handle is the only search term that is valid. Attempting to search by name or keyword is not valid, and will return an error.




3) Verify and Add

If the search is successful, the found contact information will display at the bottom of the screen. If this is the information you wish to add into ProVision, click the "Yes" button on the right hand side of the page under "Would you like to add this RIPE contact to 6connect?". Otherwise, you may hit "No" to decline adding, or cancel and return to the index.




Edit or Delete Contact

To Edit or Delete a base contact, click on the contact's name in the contact list to go to its detail view page. From there, click "Edit".



This will take you to the detail information page, where you may edit fields as desired. When done editing, hit "Save" to save your changes, or "View" to cancel without saving and view the contacts list.



To delete the contact, click the "Delete" button while in the contact details page.



Working with the Contacts Gadget


Assigning a Contact to a Resource

Contacts may be assigned to a resource through the Contacts gadget. To add a gadget to a Resource's Entry page, see Customizing Sections and Gadgets.


Once the Contacts gadget has been added to the desired Section, go to the Resource Entry page for the Resource you wish to assign the contact to, and navigate to the Contacts gadget.

Assign the Contact

In the Contact Gadget, search for a contact by typing the first few letters of the contact name in the search box, then click on the desired contact.



Then hit "Assign".




The Contact will show in the list below.


Create a Contact Role

Once a contact has been assigned, you can create and set a role for the contact by clicking on the Action Menu (wrench icon).

Then, select "Set Role".




Under the "Add New Role" section, type in the desired tole name and click the "Add" button.




Assign a Role to a Contact

Once a contact has been assigned, you can set a role for the contact by clicking on the Action Menu (wrench icon).

Then, select "Set Role".




Under the "Select Role" section, choose the desired Role from the dropdown list, and click the "Set Role" button.




Delete a Role from the Roles List

Select "Set Role"




Under the "Delete Role" section, choose the desired Role from the dropdown list, and click the "Delete" button.



This removes the role from the "Select Role" list.


Unassign a Contact

To unassign a contact from a resource, in the Contacts gadget click the Action Menu, then select "Unassign".



View the Contact Details Page


To view the contact's details, click the Action Menu, then select "View". You will be redirected to the contact's detail page.



DNS Tab

DNSv3

ProVision's DNSv3 combines server management, group organization, and zone management under the DNS tab.



The DNS tab contains four sub-tabs: **DNS Groups, DNS Servers, DNS Zones, and DNS Records**.

The **DNS Groups** tab is where DNS Groups, zones, ACL's, and default SOA values are managed. The DNS tab **Groups List** allows you to create, view, and manage groups of DNS Servers and Zones. Using groups, you can configure and push selected combinations of zones at one time.

The **DNS Servers** tab is only accessible to Admin users, and contains functions for adding, updating, and managing DNS servers as well as scheduling server tasks. For Admin-level DNS tasks, see DNS Administration and Working with DNS Servers.

The **DNS Zones** tab lists all the zones in ProVision able to be viewed by the user, in the same format as on the **DNS Groups** page, but without the Group organization. The Zone List allows you to view, add, delete, and push individual DNS Zones.

The **DNS Records** tab list all records in ProVision, in a filterable list to expedite search, editing, and managing records. New records may also be added from this page.

- DNSv3
  - DNSv3 Overview
    - DNS Permissions
      - Permission Shortcut Button ("Perms")
    - DNS Approvals
  - DNSv3 Workflow
  - Additional Information

DNSv3 Overview

DNSv3 organizes ProVision's DNS system into a more unified and accessible interface, combining both admin and non-admin DNS tasks together under the DNS tab.

In DNSv3, zones are gathered under DNS Groups, servers are attached to those Groups, and Nameservers, Default SOA values, and ACLs are managed at a per-Group level. Users can then view and manage Groups, individual zones, default SOA values, ACLs, attach servers, and perform pushes all on the same page.

DNS Permissions

DNSv3 incorporates DNS zones and Groups into ProVision's Resource System. Zones and Groups are Resources just like Customers, Servers, Routers, or Contacts (See The Resource System for a more detailed explanation of Resources in ProVision).

This allows for DNS zones and Group permissions to be managed similarly to other ProVision resources, where users with Resource permissions (Create / Read / Update / Delete) on the parent resource of the DNS Group can create groups and zones, manage those groups and zones, push (if a server is attached), and delete.

A user with full Resource permissions on a DNS Server, as well as the parent resource of a Group, may view and attach that server to a Group.

Users with Admin permissions can access the **DNS Servers** area under the **DNS** tab manage DNS server creation, edits, and deletion.

For more information on setting up permissions groups in ProVision, see Users & Permissions.

Permission Shortcut Button ("Perms")


Throughout DNS, a shortcut permissions button ("Perms") is available on a per-item level, accessible only to Admin users.

This permissions button allows for direct, point-of-use permissions adjustments to DNS Groups, Servers, Zones, and Records. It uses the same CRUD permissions and groups available in the Admin Users tab, but removes the need to remember and search for the DNS item name.

To open the Change Resource Permissions module, click on the "Perms" Button for any DNS item.



Edit the CRUD permissions for any ProVision user group by clicking the checkbox for the desired group and permission type. When done, click "Save Changes". The permission changes will be also be reflected in the Admin **User** tab Group settings.




DNS Approvals

The Approvals module stores and queues DNS actions made by selected User Groups, and sends those actions to a Pending Changes list for administrative review. Later, an administrator (or combination of administrators) can approve or reject these stored actions.

Approvals is primarily set up and managed via the Admin **Approvals** Tab. See the ProVision Admin Guide - Approvals Tab for details on setting up and using Approvals from the Administrative viewpoint.

In the **DNS** Tab, a "Resources Awaiting Approval" module will display near the top of DNS Groups, DNS Zone Lists, and DNS Servers pages, if a change has been submitted on that page that is pending approval.



Users who submitted a change for approval will see the details of their change request in this module.

Admin users with permissions to approve or reject the request will have the option to Approve or Deny the change.

DNSv3 Workflow

DNSv3 revolves around Groups. Zones are gathered under Groups, servers attached to Groups, and pushes may be done on a per Group level. Thus, the first workflow step in DNSv3 is to set up one or more DNS Groups. A "Default Group" is automatically provided in ProVision, but other Groups may be desired to organize zones and default values.

To create a new DNS Group, click the "Add Group" button from the **DNS Groups** tab. Enter the desired default values for the Group, and save. If only using the Default Group, ensure the default parameter values are set as needed. For more information, see Working with DNS Groups.


After Groups have been set up, DNS servers should be added or settings verified. Admin users may add DNS servers from the **DNS Servers** tab "Add Server" button. Input the server information and save. Existing servers may be reviewed and edited by clicking on the server name in the DNS Server List. Once a server is created in ProVision, it may be attached to any DNS Group under the Group's "Attached Servers" module. Attaching a server to a Group will allow for zones in that group to be pushed to the attached server(s). See Working with DNS Servers.

Next, add zones to your groups. Zones may be manually added under each group by clicking the "Add Zone" button in the DNS Groups or DNS Zones tabs, or it may be imported via DNS Importers into a selected Group. Add the zone and record information, and save. See Working with DNS Zones for additional information.

Zones may only exist once per Group, but may be duplicated under multiple Groups. Zones may also be moved from Group to Group as needed.

At this point, all major components of the ProVision DNS system have been added - from here management tasks take over. Zones may be updated and moved to or from Groups; Groups may be edited with different default values or servers, and pushes maybe be performed for an individual zone, a full Group, or for an entire server. Pushes may be manual or scheduled for a future time through the Scheduler.

DNS WORKFLOW




Additional Information

- Working with DNS Groups
- DNS Zones Overview
- Working with DNS Zones
- Working with DNS Records

- DNS Administration
- Importing Your Data
- Import DNS Zones

Working with DNS Groups


DNS Groups



The **DNS** tab **Groups List** allows you to create, view, and manage groups of DNS Servers and Zones. Using groups, you can configure and push selected combinations of zones at one time.

- DNS Groups
  - DNS Groups List Interface
- Working with DNS Groups
  - Add a Group
    - Create a Group
    - Navigating a Group
  - Edit a Group
    - Edit a Group Name
    - Edit Attached Servers
    - Edit a Group's Default Parameter Values
      - Edit Group Advanced Settings
      - Edit Nameservers
      - Edit Push Policy
      - Edit SOA Values
      - Save Changes
  - Add Zones to a Group
  - Pushing a Group
    - Manual Group Push
    - Scheduled Group Push
  - Delete a Group
  - Export a Group
  - Using the Templates Group / Cloning Zones to a Group
    - Create your template zone
    - Clone Template to a Different Group
  - Additional Information

DNS Groups List Interface



1) Add Group Button: Opens a dialog for creating a DNS Group

2) Resources Awaiting Approval Module - Group Level: Lists pending DNS Group level Approval events either submitted by, or able to be approved/rejected by, the current user.

3) Group Container: The Group container header shows the group name. Expand or close the group container by clicking on the expansion arrow (>) on the far right of the header. Clicking on the X will delete the Group and all zones included in the group. Rename the group by clicking on the name, then typing the desired changes and clicking outside of the name.

Group Actions:



4) Add Zone Button: Opens a dialog for creating a DNS zone under that group.

5) Push Group Button: Pushes all zones in the group.

6) Schedule Push Button: Schedules a push of all zones in the group to the selected day and time. Requires the scheduler tab / cron tasks to be enabled.

7) Export Zones: Exports all zones in the group into a .zip file.

8) Perms (Admin): Provides a shortcut for Admin users to change the group/user permissions for the DNS Group.

9) Resources Awaiting Approval Module - Zone List Level: Lists pending DNS Zone List level Approval events either submitted by, or able to be approved/rejected by, the current user.

10) Zone List: Forward and reverse zones included in the Group.

11) Forward / Reverse Zones Tabs: Shows zone list containing only forward or reverse zones, respectively.

12) Zone Name (Sortable): The name of the zone. Clicking on the zone name will open the zone details window, showing individual records. Clicking on the "Zone Name" header will sort the zone list by ascending or descending by name.


13) Last Pushed: The date and time the zone was last pushed.

14) Last Modified (Sortable). The date and time the zone was last modified. Clicking on the "Last Modified" header will sort the zone list by most / least recent modification date.

15) Records: How many records are in the zone.

16) Zone Status: Will notify if the zone or server connection contains errors, after a check has been performed (by clicking on the "Check" button). Clicking on the "Contains Errors" message will provide additional details on the error.

17) Actions: The actions that may be performed on each zone:



18) Delete: Deletes the zone from ProVision and removes the entry in ProVision conf file on the remote server(s) (the user will also receive a prompt to confirm they wish to complete the action)

19) Push: Pushes the zone to the associated server.

20) Move: Moves the zone to a different Group.

21) Check: Performs a check on the zone, notifying the user if errors or warnings are present for the zone.

22) Perms (Admin): Provides a shortcut for Admin users to change the group/user permissions for the zone.

23) Attached Servers: Sets the server that zone and group pushes will be sent to. Click on the header title or > to expand or collapse. Admins and users with server/group parent permissions may view, attach, or detach a server from the group.

24) Group Default Parameters: Click on the header title or > to expand or collapse. Edit default group settings including nameservers, SOA values, and Push Policy.

25) Applied ACLs: Click on the header title or > to expand or collapse. Add or detach ACLs to the group.

26) Catalog Zone Settings: Click on the header title or > to expand or collapse. Enable / Disable Catalog Zones. Enabling Catalog Zone exports all zones inside the Group into a new catalog zone, so that slave servers can receive zone changes.

27) Scheduled Tasks: If a scheduled push has been set up for the group, the task information will show in a "Scheduled Tasks" module. Click on the header title or > to expand or collapse. Review or delete scheduled group pushes.

Working with DNS Groups


DNS Groups allow for organizing multiple zones together and linking those zones with one or more servers. Default nameservers, SOA values, and ACL's are set at the Group level, so different Groups may have their own default values. Zones may be pushed individually, as a Group, or at the server level.

ProVision automatically designates a Default Group for zones to be imported or added to, as well as a "templates" group for holding pre-DNSv3 templates or to hold new zones created as templates. Creating additional Groups is completely optional.

Add a Group

DNSv3 automatically contains two Groups - one Default Group to contain existing or imported zones, and a Templates Group, containing zones mimicking DNS Templates. Additional Groups may be added or removed at any time, and zones may be freely moved or duplicated between different groups as needed.


To create a new Group, from the **DNS** Tab, select the **DNS Groups** sub menu. Then, click the "Add Group" button next to "DNS Groups List".



This will open the "Create New Group" dialog.

Create a Group

In the "Create New Group" dialog, enter the desired Group Name, select a parent resource, enter the default SOA values, and add a default Nameserver (type the NS, then click "Add").




Click the "Save Changes" button when complete. The new group will be added to the DNS Groups List.

Navigating a Group

Open the Group container for the new Group by clicking on the expansion arrow at the top right corner of the header.

Information for Attached Servers, Group Default Parameters, Applied ACLs, and Catalog Zones settings may also be viewed and edited by clicking on the expansion arrows for each section.




Edit a Group

Edit a Group Name

Edit the name for a Group by clicking inside the Group's Name. A highlight box will appear around the name, and a cursor inside the box.



Edit the text as desired using your mouse or arrow keys to navigate through the text. When complete, click anywhere outside of the name box, and a confirmation dialog will appear.



Click "Confirm" to save your changes, or "Close" to exit without saving.


Edit Attached Servers

Users may attach or detach servers from a group if they have either of the following permission types:

- TLR Admin permissions
- Full permissions on both the DNS Server(s) and the Parent Resource set for the DNS Group

If either condition is met, the user may view and attach/detach the applicable server(s) to a Group.


To attach a server, expand the "Attached Server" module, and click on the Attach Server list.



Select the desired server, then click "Attach".




The server is now attached to the group, and future zone and group pushes will be sent to the attached server.



From here, users have the option to Detach the server if desired, by clicking the "Detach" button.

Admin users may edit pemissions for the server using the "Perms" button, if desired (see: DNS Tab DNSv3 Permissions for additional information).



Edit a Group's Default Parameter Values

Under the desired Group, expand the "Group Default Parameters" module by clicking on the expansion arrow.



Save your changes!


Important - to ensure that your changes are saved while working in Group Default Parameter, click the "Save Group Defaults" button under the Default SOA Values section - this save button will save any changes made to Advanced Settings, Default Nameservers, or Default SOA Settings.

Push Policy changes can be saved by clicking "Save Push Policy".


Edit Group Advanced Settings

Open the "Advanced Settings Inherited by the Zones" module by going to any DNS Group and opening the "Group Default Parameters".

The Advanced Settings module will be at the top of Default Parameters area. To expand it, click on the expansion arrow on the right side of the header bar.




Once expanded, settings may be entered for DNSSEC, Dynamic Updates, Master-Slave Handling, Lists, and free lines.



Save your changes!

Important - to ensure that your changes are saved, click the "Save Group Defaults" button under the Default SOA Values section - this save button will save any changes made to Advanced Settings, Default Nameservers, or Default SOA Settings.




Edit Nameservers


Default Nameservers are automatically added to any newly created zone files.

You may choose not to set a default nameserver, however, an empty Nameservers list can cause invalid zones.

Change a Nameserver by typing the new NS record into the Nameserver box, then click "Add".




Delete the previous Nameserver by clicking on the red "X" to the right of the NS Record.



Change the order of multiple Nameservers by left-clicking (holding the mouse button down) over the NS Record to move, dragging to its desired placement, then releasing the mouse button.

The NS record will drop into its new location, with the order updated.




Save your changes!

Important - to ensure that your changes are saved, click the "Save Group Defaults" button under the Default SOA Values section - this save button will save any changes made to Advanced Settings, Default Nameservers, or Default SOA Settings.


Edit Push Policy

Edit the push policy by selecting the radio next to the desired push behavior ("Group Centric", "Zone Centric", or "Server Centric") and click "Save Push Policy".



Edit SOA Values


To edit the Default SOA values, simply click inside the value to be changed and type or select your new value. Be sure to also verify the desired Parent Resource for the Group, as the resource selected determines the Group's permissions.



Save Changes

Save all Nameserver, Advanced Settings, and SOA value changes by clicking on the "Save Group Defaults" button at the bottom of the section.

Closing without saving will cause all changes to be lost.




Add Zones to a Group

To add a new zone to a Group, click the "Add Zone" button inside the desired Group.



Fill in the zone name, select a parent resource (by default, the Group is selected), select a populate type, and fill in any optional fields.

For more detail on each of these options, see Working with DNS Zones - Add a Zone.



When complete, hit the "Save Changes" button.

Pushing a Group

Before pushing a group for the first time, verify the settings in the following areas are correct:


- Under "Attached Servers", verify that the correct server is attached to the DNS Group.
- Under "Group Default Parameters" verify SOA Settings, Nameservers, and the Push Policy are set.

Manual Group Push

After verifying the attached server and group settings, manually push the Group by clicking the "Push Group" button under the desired Group.



A DNS Push Status window appears, showing each zone in the Group as it is pushed to the attached server. If successful, a green "Finished DNS Pushing Request" will appear as the final message. If errors occur, an error message will show with details on the issue. When complete, hit the "Close" button.




Scheduled Group Push


Scheduled pushes may be set up through the "Schedule Push" button for the Group.



Click "Schedule Push" for the Group, then select a date, time (12 hour, with AM / PM toggle), add a notification email address, and click "Save changes".




The Scheduled task will be shown in both the Group details (under "Scheduled Tasks") and the Admin Scheduler task list.




The task may be deleted prior to running by clicking the "delete" button, but will automatically be removed once completed.

Delete a Group

Delete a non-Default Group by clicking on the "X" to the left of the Group's name in the DNS Groups List.



A confirmation message will appear, click "Confirm" to save your changes, or "Close" to exit without saving.




The Default Group may not be deleted.

Export a Group

All zones under a DNS Group may be exported to a .zip file by clicking the "Export Zones" button at the top of the Group module.


The exported .zip file may be used with ProVision's BIND DNS Zone Upload / Import tool.



Using the Templates Group / Cloning Zones to a Group

By default, a "templates" group is included in DNSv3.


Any pre-DNSv3 DNS Templates will be included in this group, as well as any newly created zones to be used as template zones.



The template group functions the same as any other DNS Group, but gives a holding place for zones designed as templates separate from other zones.

Create your template zone

Add a template zone by clicking the "Add Zone" button, giving the zone a descriptive name to clearly identify as a template, select the populate type, and fill in any optional data. (see Working with DNS Zones - Add a Zone.)




Once the zone has been created, it will show in the templates group zone list, and is now selectable as a base for the "clone existing zone" option when creating a new zone.

Clone Template to a Different Group

Go to a different group, and click "Add Zone". Enter in the new zone name and parent.

Under "Populate Type", select "Clone existing zone" and select /search for the template zone you created.



Edit the optional fields as needed, and click "Save changes".


Additional Information

For more information on DNSv3 tasks, see:

- Working with DNS Zones
- DNS Zones Overview
- DNS Administration
- Working with DNS Servers
- Approvals

Editing DNS Zones

DNS Zones



DNS Zones are accessed under the **DNS** tab, **DNS Groups** or **DNS Zones** sub-tabs. The **DNS Zones** sub-tab features the DNS Zone List - a straightforward list of all zones existing in ProVision, including those not attached to DNS Groups. From here, you can create a new zone, view all Forward, Reverse, and Catalog zones, delete, push, check, view pending approvals, or edit permissions (admin only) on a zone.


This page focuses on a general UI overview of the DNS Zones and Zone View pages.

For detailed instructions on how to perform specific zone tasks, see Working with DNS Zones.

- DNS Zones
- DNS Zone List Interface
    - Sort / Filter the Zone List
    - Resources Awaiting Approval
    - View Zone Details (View Zone Page)
- The View Zone Page Interface
    - Error Notification
    - Zone Actions
    - Comments
    - Pending Approvals
    - Advanced Settings
    - DNS Records
        - Filter Records
    - Scheduled Tasks
    - Attached Servers
    - Zone Backups
    - Current Zone Export
    - Addiitonal Information:

DNS Zone List Interface


The DNS Zone List shows all zones existing in ProVision, organized into three tabs - Forward, Reverse, and Catalog Zones. By default, the zones load in ascending alphabetical order with 25 zones per page. To switch between the two lists, simply click on the tab for the desired zone type.




Sort / Filter the Zone List

The Zone list may be sorted by either "Zone Name" or by "Last Modified" time.


To sort the Zone List, click on the up/down arrows next to either column header to toggle between ascending/descending order.



To filter the Zone List, click on the filter icon next to "Actions".



Then, type in all or part of the zone name, or select zone status. Click "Filter."




The zone list will filter the zones to only those fitting the selected criteria.

Resources Awaiting Approval

If the Approval system is in use, pending zone approval items will be shown in a "Resources Awaiting Approval" module above the Zone List.


Users who submitted a change for approval will see the details of their change request in this module.

Admin users with permissions to approve or reject the request will have the option to Approve or Deny the change.



View Zone Details (View Zone Page)

To view details or manage a zone, click on the zone name from any Zone List to go to the Zone View page.




The View Zone Page Interface

Zones may be edited by clicking on the Zone name in any zone list in which it appears - from the DNS Zones Zone List, zones listed under DNS Groups, under DNS Server attached zones list, or from the DNS Gadget.

Clicking on the zone name opens up the View Zone page, from where comments may be added, records added or updated, servers attached to the zone, advanced settings edited, backups restored or the zone pushed / exported.

This section focuses on a general UI overview of the Zone View page.

For detailed instructions on how to perform specific zone tasks on this page, see Working with DNS Zones.




Areas of the Zone View page include:

- DNS Zones
- DNS Zone List Interface
    - Sort / Filter the Zone List
    - Resources Awaiting Approval
    - View Zone Details (View Zone Page)
- The View Zone Page Interface
    - Error Notification
    - Zone Actions
    - Comments
    - Pending Approvals
    - Advanced Settings
    - DNS Records
        - Filter Records
    - Scheduled Tasks
    - Attached Servers
    - Zone Backups
    - Current Zone Export
    - Addiitonal Information:

Error Notification


If errors are detected for the zone, an error notice will be given at the top of the group tab for the zone. To review the error, click on the message, and it will list the number of errors present, and details if available.

Records will errors will be highlighted in red in the records list.




Zone Actions

Zone actions that may be taken include pushing the zone ("Push Zone Now"), scheduling a zone push ("Schedule Push") or exporting the zone to a .zone file ("Export Zone").



Comments

To add a comment to a zone, click anywhere inside the comment area and begin typing. The comment will be saved when an area outside of the comment box is clicked, deselecting the comment area.




Pending Approvals

If the Approvals system is used, pending approval events for the zone or records will appear in an expandable module under the zone comment.


Users who submitted a change request will see the action and data details for their request.

Admin users who can approve/reject the change will see all details plus buttons to Approve or Reject the change. See Approvals for additional information.



Advanced Settings

Open the zone "Advanced Settings" section by clicking on the header or the expansion arrow (>).



Here, you will find options for:

Parent Resource: Sets the zone's Parent Resource, which affects the permissions access for the zone. By default, the parent is set as the DNS Group the zone is in.

Enable DNSSEC: Toggle "On" or "Off" to enabled DNSSEC for the zone, if supported by the attached server.

Enable Dynamic Updates: Toggle "On" or "Off" to enabled Dynamic Updates for the zone, if supported by the attached server.

Also-notify List: Add IPs to also-notify list of the attached DNS sever, if supported.

Allow Update List: Add IPs to the allow updates list of the attached DNS sever, if supported.

Allow Transfer List: Add IPs to the allow transfer list of the attached DNS sever, if supported. Slaves are automatically added if exporting a zone to a master server.

Allow Notify List: Add IPs to the allow notify list of the attached DNS sever, if supported.

Zone Permissions (Admin): Directly adjust User Group CRUD permissions for this zone.

Free Lines: Enter free lines to append to the zone section of the server configuration for the attached server (ISC BIND only). Use with caution - this can cause configuration errors if mistakenly included.

Server Specific Free Lines: Select a DNS server and click "Add New" to add server-specific Free Lines.

Save Button: Be sure to click "save" when edits are complete, or changes will not be saved.


DNS Records

The DNS Records list on the View zone page contains options to add a new record of the selected type, edit record information, delete a record, check record, or edit permissions (admins only).



Filter Records

Filter the records list by clicking the "filter" icon next to "Record Data".




Then, select the desired record type, host / value names, or status. Then, click "Filter".

DNS records may also be reviewed and managed from the **DNS Records** sub-tab.

Scheduled Tasks

If scheduled tasks (zone pushes) have been set up for the zone, they will appear under a "Scheduled Tasks" section.

Tasks here will also show in the Admin Scheduler task list.




The task may be deleted by clicking the "delete" button.

See Working with DNS Zones for details on Scheduling zone pushes.

Attached Servers

Servers attached directly to the zone, or inherited from the zone's parent DNS Group will be shown here.

Additional servers may be attached by selecting the server name, type (default, master, slave), and clicking the "Attach" button, as long as the user has permissions on both the zone and the server to attach. After attached, users with sufficient permissions may detach, push, or edit permissions on the server.



To detach a server from a zone, look for the server under the "Attached Servers" list, then click "Detach" under actions for that server.


Servers that are attached via inheritance from a DNS Group will not be able to be detached at the zone level.

Zone Backups

If a zone has had changes sucessfully pushed, a "Zone Backups" section appears near the bottom of the page, showing the date and time of the backup.



To view details, or restore the zone to the previous version, click on the row of the desired date/time backup, and the "Zone Restore" module will open.




From here, you may restore individual records by clicking on them, or restore the entire zone by clicking the "Restore Zone" button.

To exit without saving, click the "Close" button.

Current Zone Export

To view or download current zone information, expand the "Show Current Zone Export" module. Then, select the DNS server to pull from and select either "View Here" or "Download".



"View Here" will display a read only text data display of the zone information directly in the module.

"Download" will download a .zone file for the zone from the selected server.


Addiitonal Information:

For more information on working with DNS Zones, Groups, and Servers, see the following sections:

- Working with DNS Groups
- Working with DNS Zones
- DNS Administration
- Import DNS Zones
- Approvals

Working with DNS Zones - Common Tasks

Working with DNS Zones



This page details some common DNS tasks performed from the **DNS** tab.

DNS Zones are accessed under the **DNS** tab, **DNS Groups** or **DNS Zones** sub-tabs. Separate zone lists exist under each DNS Group.

DNS Records are accessed from either the View Zone page (for records under that zone), or globally under the **DNS Records** sub-tab. For Details on working with records in either area, see Working with DNS Records

For a more general overview DNS Groups and Editing Zones, see Working with DNS Groups and DNS Zones Overview. This page focuses on specific DNS zone tasks.

DNSv3 Zone Directory

In DNSv3, zone files in the server directory will have a number appended, similar to 'example.com._123.zone'. This number is the Resource ID associated with the zone, and is used in ProVision to identify the zone and differentiate zones that may have the same name, but under different DNS Groups. This append does not affect any zone functionality otherwise.

- Working with DNS Zones
- Working with DNS Zones
  - Add a Zone
    - Optional Fields
  - Edit a Zone (View Zone page)
    - Add a comment
    - Edit Advanced Settings
  - Move Zones to a Different Group
  - Pushing Zones
    - Push Now (from Group List)
    - Push Now (from View Zone page)
    - Schedule Push (from View Zone page)
    - Schedule Push (Admin Scheduler):
    - Group Push:
    - Server Push:
  - Export a Zone
  - Import Zone / Import Records
    - Enable Saving Import Files (Admin Setting - Optional)
    - Import Zone File
      - Importing Zone file with Comments
    - Download Imported Zone File
  - Delete a Zone
  - Addiitonal Information:


Working with DNS Zones

Add a Zone


Add a new zone while in the **DNS Groups** tab by selecting "Add Zone" under the desired Group.



You may also add new zones from the **DNS Zones** tab, by clicking "Add Zone" next to **Zone List.**



The "Create New Zone" dialog will pop up.



Enter the name of your new zone and select a parent resource, if desired. The DNS group will already be selected.


DNSv3 allows you to populate the zone with three options:

- Empty Zone - create the zone as an empty zone, and manually create records
- Populate by AXFR Transfer - transfer zones from an outside server
- Clone an existing zone - use an existing zone as a template, and manually edit as needed

From there, you may either save your changes and complete zone creation, or add in optional field details.

Optional Fields

Expand the "Optional Fields" section by clicking on the chevron (>) or the "Optional Fields" header.



Under this section, add in optional values for Zone Host, Email, Serial , Refresh, Retry, Expiry, or TTL.


When finished, click "Save Changes".

To exit without saving, simply click "Close".

Edit a Zone (View Zone page)

Zones may be editing by clicking on the Zone name in any zone list in which it appears - the **DNS Zones** Zone List, **DNS Groups** Zone List, or zones listed as attached to a server under **DNS Servers**.

Clicking on the zone name from any zone list opens up the View Zone page.




Here, comments may be added, records added or updated, servers attached to the zone, advanced settings edited, backups restored or the zone pushed / exported. For a general interface overview of the View Zone page, see DNS Zones Overview.

For detailed information on working with DNS Records from the View Zone page Record List or the **DNS Records** sub-tab, see Working with DNS Records.

Add a comment


To add a comment to a zone, click anywhere inside the comment area and begin typing. The comment will be saved when an area outside of the comment box is clicked, deselecting the comment area.



Edit Advanced Settings

Open the zone "Advanced Settings" section by clicking on the header or the expansion arrow (>).


Under this area, you can change settings such as Parent Resource, DNSSEC, Lists, Zone permissions, and free lines.




Edit fields as needed, and click "Save" when done.

Move Zones to a Different Group

Zones may be moved to a different Group than the one created under, by clicking the "Move" button in the zone's Actions menu.



The "Move Zone" modal will appear - select the new Group to move to the zone under, and click "Save Changes" to complete.




Pushing Zones

Zones may be pushed individually ("Push Zone Now"), as a scheduled future push ("Schedule Push"), or pushed as part of a Group or Server Push.


Push Now (from Group List)

To immediately push a single zone, navigate to the DNS Group the zone is under, then click the "Push" button in the Actions column for the zone.

You may also look for the zone in the **DNS Zones** tab Zone List, and then likewise, click the "Push" button in the zone row.




The "Push Status" modal will appear, showing status and any errors that occur. When a successful zone push is complete, a green "Finished DNS Pushing Request" message will appear, and the window may be closed.



Push Now (from View Zone page)

The View Zone page, accessed from clicking on the zone name in the Group zone list, includes a "Push Zone Now" button that immediately attempts to push the zone to the attached server(s).




Click on "Push Zone Now", and the "Push Status" modal will appear, showing status and any errors that occur.


When a successful zone push is complete, a green "Finished DNS Pushing Request" message will appear, and the window may be closed.

Schedule Push (from View Zone page)


The View Zone page includes an option to schedule a zone push, similar to scheduling a Group push.



Click "Schedule Push" for the zone, then select a date, time (12 hour, with AM / PM toggle), add a notification email address, and click "Save changes".



The Scheduled task will be shown in both the Zone View page (under "Scheduled Tasks") and the Admin Scheduler task list.



The task may be deleted prior to running by clicking the "delete" button, but will automatically be removed once completed.

Schedule Push (Admin Scheduler):

Scheduled zone and server pushes may also be set up by Admin users from the **Scheduler** tab. For more information, see the Scheduler Tab documentation.

Group Push:

All zones contained in a DNS Group may be pushed at the same time, by pushing the DNS Group.

For information on working with DNS Groups, including performing a manual or scheduled Group push, see Working with DNS Groups - Pushing a Group.

Server Push:


Admin users may push all zones on a server from the **DNS** Tab -> **DNS Servers** page.

For information on working with DNS Servers, including performing a manual or scheduled server push, see Working with DNS Servers - Pushing a Server.

Export a Zone

Individual zones may be exported to a .zone file by clicking the "Export Zone" button on the View Zone page.

Individual .zone files may later be compressed into a .zip, and used with ProVision's BIND DNS Zone Upload / Import tool.




Import Zone / Import Records

A zone file (.zone) may be imported into a ProVision zone to populate record data. Note: To import the record data, the zone must already exist in ProVision - although it may be an empty placeholder zone if necessary.

Enable Saving Import Files (Admin Setting - Optional)

Before you import a zone file, you may (optionally) select to save the import file to the zone. Saving the file allows you to later re-download it directly from ProVision.

To enable saving import files, go to Admin Preferences DNS Settings sub-tab. From there, select "Import Settings" in the DNS Global Settings module.




Toggle "Keep Import File" into the ON position, then select "Save Changes".


Import Zone File

To import a zone file to populate record data in ProVision, go to the View Zone page for the zone. The zone must already exist in ProVision, although it may be empty

Click "Import Zone" on the View Zone page.




A Zone Import dialog box will open. Next to **Zone File:**, click "Choose File" and select your .zone file to import. Then, select an import policy to follow.




When done, Click "Import Zone".

Importing Zone file with Comments

DNS Zone Import will also import comments contained in the .zone file, such as an internal change log (as seen in the image below).



During import, these comments are added to ProVision's zone comments field:



Download Imported Zone File


If "Keep Import File" has been enabled, the original zone import file will display in the View Zone page under "Zone Backups and Attached Files".



To download the original file, click "Download" for the import file.

Delete a Zone

Users with resource delete permissions over the zone may delete a zone record by clicking the "Delete" button under "Actions" for the desired zone entry in any Zone List.




Addiitonal Information:

For more information on working with DNS Zones, Groups, and Servers, see the following sections:

- DNS Tab
- Working with DNS Groups
- Working with DNS Records
- Editing DNS Zones (The View Zone Page)
- DNS Administration
- Import DNS Zones
- Approvals

Working with DNS Records

Working with DNS Records



DNS Records may be managed either from the View Zone page (for the records under the respective zone) or globally through the **DNS Records** sub-tab.

- Working with DNS Records
  - Working with Zone Records - View Zone Page
    - Add Zone Records
    - Import Zone Records
    - Edit Zone Records
    - Delete Zone Records
    - Check a Record
    - Attach / Detach Servers to a Zone
    - Restore a Zone / Record from Backup
  - Working with Records - DNS Records sub-tab
    - Filter Records
    - Work with Records
    - Add a New Record
  - Additional Information

Working with Zone Records - View Zone Page


Add Zone Records

From the View Zone page, under DNS Records, look for the line "Add a new ___ Record".

Select the desired record type from the dropdown list, then click "Add".



Fill in the information for the new record, selecting options for adding to groups or skipping validation.



When done, click "Save Changes".

Import Zone Records

To import a zone file to populate record data in ProVision, go to the View Zone page for the zone. The zone must already exist in ProVision, although it may be empty


Tip

You may wish to enable "Save Import File" in Admin Settings DNS Settings prior to importing zone files, so that the file is available for later download. See Working with DNS Zones or Import DNS Zones.

Click "Import Zone" on the View Zone page.



A Zone Import dialog box will open. Next to **Zone File:**, click "Choose File" and select your .zone file to import. Then, select an import policy to follow.




When done, Click "Import Zone".

Edit Zone Records

To edit an existing zone record, click on the record line in the DNS Records list.

The Edit Record dialog will open, allowing you to fill in record details.



Fill in the Host, Value, TTL, and comment if desired.

An option exists to "Skip Validation" - check to select if you wish to bypass validation for the record.

If previous versions of the record exist, the revision log will be visible under "Record revisions".

When edits or reviewing is complete, click "Save changes", or "Close" to exit without saving.

Delete Zone Records

Delete a zone record by clicking the "Delete" button under "Actions" for the desired record entry.



Check a Record

Check a record for errors by clicking the "Check" button under "Actions" for the desired record entry.



A dialog box will appear, with details on any errors.

You may clear the error if desired, recheck, or close the box.

Attach / Detach Servers to a Zone

Under the "Attached Servers" section of the View Zone page, next to "Attach Server:", select the desired server to attach and choose the server type (Default, Master, Slave), then click the "Attach" button.




To detach a server from a zone, look for the server under the "Attached Servers" list, then click "Detach" under actions for that server.

Restore a Zone / Record from Backup

If a zone has had changes successfully pushed, a "Zone Backups" section appears near the bottom of the page, showing the date and time of the backup.



To view details, or restore the zone to the previous version, click on the row of the desired date/time backup, and the "Zone Restore" module will open.




From here, you may restore individual records by clicking on them, or restore the entire zone by clicking the "Restore Zone" button.

To exit without saving, click the "Close" button.

Working with Records - DNS Records sub-tab

The DNS Records sub-tab provides a global list records for expedited searching, filtering, adding, and editing of DNS Records.




From the DNS Tab, click on the "DNS Records" sub-tab button, or select it from the DNS dropdown menu.

All DNS records available in ProVision displays in a single Record List, along with Host, Type, Value, and Last Queried information.

Filter Records

Search for specific records by filtering by Host, Type, Comment, Value, Last Query, Last Modified, Record TTL, or Status.


After entering your filter criteria, click "Filter".



Work with Records


For each record, you may:

- Click the "Check" button to run an DNS Monitor error check on the record
- Review or change record permissions by clicking "Perms" (Admin only)
- Delete the record by clicking "Delete"
- Review or Edit record details by double-clicking on the row for the desired record.
    - Review record revision dates or enter your desired edit, then click "Save changes" to complete.




Add a New Record

Next to "Record List", select the desired record type, then click "Add Record".



Enter the record information for the record type. When done, click "Save Changes".



Additional Information


For more information on DNSv3 tasks, see:

- Working with DNS Zones
- DNS Zones Overview
- DNS Administration
- Working with DNS Servers
- Approvals

DHCP Tab

The DHCP Tab

ProVision's **DHCP** Tab combines server management, group organization, and pool management under one tab.



The **DHCP** tab contains four sub-tabs: **DHCP Groups, DHCP Servers, DHCP Pools, and DCHP Logging**.

The **DHCP Groups** tab is where DHCP servers and pools are managed as a part of DHCP Groups. The **DHCP** tab **DHCP Groups List** allows you to create, view, and manage groups of DHCP servers and pools. Using groups, you can configure and push selected combinations of pools at one time.

The **DHCP Servers** tab is only accessible to Admin users, and contains functions for adding, updating, and managing DHCP servers as well as scheduling server tasks. For Admin-level DHCP tasks, see Working with DHCP Servers.

The **DHCP Pools** tab lists all the pools created in ProVision able to be viewed by the user, in the same format as on the **DHCP Groups** page, but without the Group organization. The Pool List allows you to view, add, delete, and push individual DHCP Host and Subnet Pools.

The **DHCP Logging** tab provides a link to ProVision's logging system, where you can filter to view DHCP-only logs.

- The DHCP Tab
  - Permissions
  - Additional Information

Permissions

DHCP Management integrates with ProVision's resource and permissions hierarchy, as well as the IP Management system. Individual DHCP servers can be assigned via Resource Permissions to different internal user groups, to be managed by only the appropriate parties.

Additional Information


See the following sections for detail on working within the DHCP Tab:

- Working with DHCP Groups
- Working with DHCP Pools
- Working with DHCP Gadgets

For more detail on advanced DHCP topics and the DHCP API, see API Module - DHCP.

Working with DHCP Groups

DHCP Groups




The DHCP tab **DHCP Groups List** allows you to create, view, and manage groups of DHCP Servers and Pools. Using groups, you can configure and push selected combinations of zones at one time.

- DHCP Groups
  - DHCP Groups List Interface
- Working with DHCP Groups
  - Add a Group
  - Edit a Group
    - Edit a Group Name:
    - Edit a Group's Settings:
      - Edit Parent Resource
      - Edit Failover Name
  - Add Pools to a Group
    - Add a Subnet Pool
      - Smart Assign
      - Direct Assign
    - Add a Host Pool
      - Smart Assign
      - Direct Assign
  - Pushing a DHCP Group
    - Manual Group Push
    - Scheduled Group Push
  - Delete a Group
  - Additional Information


DHCP Groups List Interface

Navigation: Move between the DHCP Groups, DHCP Servers, DHCP Pools, and DHCP Logging pages via the subtab buttons below the main navigation bar.



1) Add Group Button: Opens a dialog for creating a DHCP Group

2) Group Container: The Group container header shows the group name. Expand or close the group container by clicking on the expansion arrow (>) on the far right of the header. Clicking on the X will delete the Group and all zones included in the group. Rename the group by clicking on the name, then typing the desired changes and clicking outside of the name.




Group Pool Actions:

3) Add Pool Button: Opens a dialog for creating a DHCP Pool under that group.

4) Push Group Button: Pushes all pools in the group to the associated DHCP server.

5) Schedule Push Button: Schedules a push of all pools in the group to the selected day and time. Requires the scheduler tab / cron tasks to be enabled.

6) Pool List: Subnet and Host Pools included in the Group.



7) Subnet / Host Pools Tabs: Shows zone list containing only forward or reverse zones, respectively.

8) Pool Name (Sortable): The name of the pool. Clicking on the pool name will open the pool details page. Clicking on the "Pool Name" header will sort the zone list by ascending or descending by name.

9) Last Modified (Sortable): The date and time the pool was last modified. Clicking on the "Last Modified" header will sort the list by most / least recent modification date.

10) Subnet (or IP): The subnet or IP of the subnet/host pool, respectively.

11) Range Min (or MAC): The starting range address for subnet pools, or the MAC for host pools.


12) Range Max: For the subnet list, the ending range address for the pool.

13) Actions: Clicking on the "Actions" header will reveal sortable filters for selected fields. Buttons under the Actions column indicate actions that may be performed on each pool:


14) Delete: Deletes the pool from ProVision.

15) Push: Pushes the pool to the associated server.

16) Attached Servers: Click on the header title or > to expand or collapse. View, attach, or detach a DHCP server from the group.




17) Group Settings: Click on the header title or > to expand or collapse. Edit default group settings including the Parent Resource and Failover name.



18) Save Settings Button: Saves any changes made to the DHCP Group Settings options.

22) Scheduled Tasks: If a scheduled push has been set up for the group, the task information will show in a "Scheduled Tasks" module. Click on the header title or > to expand or collapse.



From here, you may review or delete scheduled group pushes.

Working with DHCP Groups

DHCP Groups allow for organizing multiple pools together and linking those pools with one or more servers. Pools may be pushed individually, as a Group, or at the server level.

ProVision automatically designates a Default Group for pools to be imported or added into. Creating additional Groups is completely optional.

Add a Group

Create DHCP Groups by clicking the "Add Group" Button, then add subnet or host pools under the group by clicking "Add Pool" for the desired Group.

Pools may be pushed individually, as a part of a DHCP Group, or through pushing an entire DHCP Server.


To create a new Group, from the **DHCP** Tab, select the **DHCP Groups** sub menu. Then, click the "Add Group" button next to "DNS Groups List".



This will open the "Create New Group" dialog.

Enter the desired Group Name and select a parent resource.


Click the "Save Changes" button when complete.



The new group will be added to the DHCP Groups List.

Open the Group container for the new Group by clicking on the expansion arrow at the top right corner of the header.

Information for Attached Servers and Group Settings may also be viewed and edited by clicking on the expansion arrows for each section.




Edit a Group

Edit a Group Name:

Edit the name for a Group by clicking inside the Group's Name. A highlight box will appear around the name, and a cursor inside the box.




Edit the text as desired using your mouse or arrow keys to navigate through the text. When complete, click anywhere outside of the name box, and a confirmation dialog will appear.



Click "Confirm" to save your changes, or "Close" to exit without saving.

Edit a Group's Settings:

Under the desired Group, expand the "Group Settings" module by clicking on the expansion arrow in the upper right corner of the header.



Edit Parent Resource

Change the parent resource for the DHCP Group by searching and selecting the desired resource from the dropdown box.


Edit Failover Name

Edit the Failover name by typing the name directly in the Failover Name input. If the Failover name is not empty, the pools will be exported in Failover mode. NOTE: This is for ISC BIND only.

When done with your edits, be sure to click the "Save Settings" button.


Add Pools to a Group

To add a new pool to a DHCP Group, click the "Add Pool" button inside the desired Group.



Add a Subnet Pool

To add a new subnet pool to a DHCP Group, select "Subnet" as the Pool Type. Select the parent resource and type in a Subnet Name.



Next, choose an assignment type - you may either have ProVision smart assign a block for the pool that matches your provided criteria, or directly assign a specific block.

Smart Assign


To Smart Assign a DHCP pool, select "Smart" for the Assignment type, choose IPv4 or IPv6 for the IP type, then select a netmask.

All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria. If desired, toggle "Assign Default Gateway" on.

When done, click "Save Changes". ProVision will choose the first block matching all criteria to assign to the pool.

If no block matches the given criteria, a message will state so. Try either removing some criteria, or ensure that blocks exist in IPAM (with subassignments enabled!) with the given attributes.

Direct Assign




To Direct Assign a DHCP pool, select "Direct" for the Assignment type, choose IPv4 or IPv6 for the IP type, then type in the desired IP Address.

All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria, if duplicate blocks exist. If desired, toggle "Assign Default Gateway" on.

When done, click "Save Changes". If the typed block exists in ProVision with subassignments enabled, and meets any additional criteria, that block will be assigned to the pool.

Add a Host Pool

To add a new host pool to a DHCP Group, select "Host" as the Pool Type. Select the parent resource, and add a Hostname and MAC Address.



Next, choose an assignment type - you may either have ProVision smart assign a block for the pool that matches your provided criteria, or directly assign a specific block.

Smart Assign


To Smart Assign a DHCP pool, select "Smart" for the Assignment type and choose IPv4 or IPv6 for the IP type.

All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria.

When done, click "Save Changes". ProVision will choose the first block matching all criteria to assign to the pool.

If no block matches the given criteria, a message will state so. Try either removing some criteria, or ensure that blocks exist in IPAM (with subassignments enabled!) with the given attributes.

Direct Assign




To Direct Assign a DHCP pool, select "Direct" for the Assignment type, choose IPv4 or IPv6 for the IP type, then type in the desired IP Address.

All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria, if duplicate blocks exist.

When done, click "Save Changes". If the typed block exists in ProVision with subassignments enabled, and meets any additional criteria, that block will be assigned to the pool.


Pushing a DHCP Group

Before pushing a group, expand the "Attached Servers" section and verify that the correct server is attached to the DHCP Group.



Manual Group Push

After verifying the attached server, manually push the Group by clicking the "Push Group" button under the desired DHCP Group.




A DHCP Push Status window appears. If successful, a green "Finished DHCP Pushing Request" will appear as the final message.

If errors occur, an error message will show with details on the issue. When complete, hit the "Close" button.




Scheduled Group Push


Scheduled pushes may be set up through the "Schedule Push" button for the Group.



Click "Schedule Push" for the Group, then select a date, time (12 hour, with AM / PM toggle), add a notification email address, and click "Save changes".



The Scheduled task will be shown in both the Group details (under "Scheduled Tasks") and the Admin Scheduler task list.




The task may be deleted prior to running by clicking the "delete" button, but will automatically be removed once completed.

Delete a Group

Delete a non-Default Group by clicking on the "X" to the left of the Group's name in the DHCP Groups List. When you delete a DHCP Group, pools under the group will not be deleted.They will no longer be associated with a DHCP Group, and can be managed from the DHCP Pools list.



A confirmation message will appear, click "Confirm" to save your changes, or "Close" to exit without saving.



The Default Group may not be deleted.

Additional Information

For more information on DHCP tasks, see:

DHCP Tab

Working with DHCP Pools

Working with DHCP Gadgets

Administrative Tasks:

DHCP Administration

Working with DHCP Servers

Working with DHCP Pools


DHCP Pool Management

DHCP Pool specific tasks are managed from two main areas in ProVision - the **DHCP Pools** list, and the **Pool Details** page.

The DHCP Pools List is accessed from the **DHCP** tab, then clicking on the **DHCP Pools** subtab button.

Clicking on the Pool name from any DHCP Pool List will open the **Pool Details** page for the specific pool.

DHCP Pools List



The **DHCP Pools** list provides the same pool-level functionality as the DHCP Groups pool lists, but includes all pools regardless of Group attachment.

From this page, you may create, view, edit, and push subnet or host pools.


Clicking on the pool name will open the Pool Details page, and clicking on the Subnet will open IPAM Mange for the assigned pool block.

- DHCP Pool Management
- DHCP Pools List
  - Add a DHCP Pool
    - Create Subnet Pool
      - Smart Assign
      - Direct Assign
    - Create a Host Pool
      - Smart Assign
      - Direct Assign
  - Edit / Manage a Pool (Pool Details page)
    - Add / Edit a comment:
    - Edit Pool Range
    - Edit IP Assignment
    - Add / Remove a Pool Reservation
    - Edit Advanced Settings:
    - Detach Server from a Pool
  - Pushing DHCP Pools
    - Manual Pool Push (DHCP Pools List)
    - Manual Pool Push (Pool Details page):
    - Schedule Push (from Pool Details page):
    - Schedule Push (Admin Scheduler):
    - DHCP Group Push:
    - DHCP Server Push:

- Delete a Pool
- Addiitonal Information:

Add a DHCP Pool


Add a new DHCP Pool from the Pool List by clicking the "Add Pool" button at the top of the page.



When the "Create New Pool" dialog appears, you may choose to create either a Subnet or Host Pool. Either pool type may have a block smart assigned or manually direct assigned.

Create Subnet Pool

To add a new subnet pool to a DHCP Group, select "Subnet" as the Pool Type. Select the parent resource and type in a Subnet Name.



Next, choose an assignment type - you may either have ProVision smart assign a block for the pool that matches your provided criteria, or directly assign a specific block.

Smart Assign


To Smart Assign a DHCP pool, select "Smart" for the Assignment type, choose IPv4 or IPv6 for the IP type, then select a netmask.

All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria. If desired, toggle "Assign Default Gateway" on.

When done, click "Save Changes". ProVision will choose the first block matching all criteria to assign to the pool.

If no block matches the given criteria, a message will state so. Try either removing some criteria, or ensure that blocks exist in IPAM (with subassignments enabled!) with the given attributes.

Direct Assign




To Direct Assign a DHCP pool, select "Direct" for the Assignment type, choose IPv4 or IPv6 for the IP type, then type in the desired IP Address.

All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria, if duplicate blocks exist. If desired, toggle "Assign Default Gateway" on.

When done, click "Save Changes". If the typed block exists in ProVision with subassignments enabled, and meets any additional criteria, that block will be assigned to the pool.

Create a Host Pool

To add a new host pool to a DHCP Group, select "Host" as the Pool Type. Select the parent resource, and add a Hostname and MAC Address.



Next, choose an assignment type - you may either have ProVision smart assign a block for the pool that matches your provided criteria, or directly assign a specific block.

Smart Assign


To Smart Assign a DHCP pool, select "Smart" for the Assignment type and choose IPv4 or IPv6 for the IP type.

All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria.

When done, click "Save Changes". ProVision will choose the first block matching all criteria to assign to the pool.

If no block matches the given criteria, a message will state so. Try either removing some criteria, or ensure that blocks exist in IPAM (with subassignments enabled!) with the given attributes.

Direct Assign



To Direct Assign a DHCP pool, select "Direct" for the Assignment type, choose IPv4 or IPv6 for the IP type, then type in the desired IP Address.


All other fields are optional - Resource, Region, IPAM Rules, and VLAN may be selected to further narrow the block criteria, if duplicate blocks exist.

When done, click "Save Changes". If the typed block exists in ProVision with subassignments enabled, and meets any additional criteria, that block will be assigned to the pool.

Edit / Manage a Pool (Pool Details page)


Additional Pool Management options are available from the **Pool Details** page. Pools may be edited by clicking on the Pool name in any **DHCP Pools** list in which it appears.

From this page, users may edit assignment, range, settings, reservations, or servers for the pool.



Add / Edit a comment:

To add a comment to a pool, click anywhere inside the comment area and begin typing. The comment will be saved when an area outside of the comment box is clicked, deselecting the comment area.



Edit Pool Range

The pool range may be manually edited by typing the desired range start and end values into the "Range" section, then click the "Save" button.




Edit IP Assignment

To change the current IP assignment for the pool, click the "Change" button next to "IP Assignment".



In the "New IP Block" dialog, select the Assignment Type, IP Type, and Netmask. Optional fields include Resource, Region, IPAM Rule, and VLAN as filtering criteria if desired.




When complete, click "Save changes".

If no block meets the selected criteria, an error message will appear - try removing filter criteria, or verify that subassignable blocks meeting the criteria have been created in IPAM.


If successful, the IP assignment will change to a block meeting the provided attributes.

Add / Remove a Pool Reservation

Add a new pool reservation by entering the Name, IP, and MAC Address into the fields under "Pool Reservations", and click the "Add" Button.




Once created, a reservation may be removed by clicking the "Delete" button next to it.



Edit Advanced Settings:

Open the zone "Advanced Settings" section by clicking on the header or the expansion arrow (>). Edit fields as needed, and click "Save" when complete.




Attach Group / Server to a Pool

Servers may be attached to a pool either from a DHCP Group association, or directly from the Pool Details Page.


Attach the pool to a DHCP Group by clicking in the DHCP Group search box, selecting a Group, then clicking "Save" next to "Attach to Groups". The pool will inherit the DHCP server associated with that group.

To directly attach a DHCP server to a pool, select the server from the "Attach server" dropdown, then click the "Attach" button.



Detach Server from a Pool

To detach a server from a pool, look for the server under the "Attached Servers" list, then click "Detach" under actions for that server.




To detach a server inherited from a Group, the pool must be removed from the group. To do that, click the "x" next to the group name in the "Attach to Groups" box, then click "Save".

Pushing DHCP Pools


Pools may be pushed manually ("Push", "Push Pool Now"), as a scheduled future push ("Schedule Push"), or pushed as part of a DHCP Group or DHCP Server Push.

Before pushing a pool for the first time, view the "Attached Servers" section in the **Pool Details** page and verify that the correct server is attached to the DHCP Pool, either directly or via a DHCP Group.



Manual Pool Push (DHCP Pools List)

Pools may be manually pushed by clicking the "Push" button for the pool from any **DHCP Pools** list.




The "DHCP Push Status" modal will appear, showing status and any errors that occur.



When a successful push is complete, a green "Finished DHCP Pushing Request" message will appear, and the window may be closed.

Manual Pool Push (Pool Details page):

The Pool Details page, accessed from clicking on the zone name in the Group zone list, includes a "Push Pool Now" button that immediately attempts to push the pool to the attached server(s).



Click on "Push Pool Now", and the "DHCP Push Status" modal will appear, showing status and any errors that occur.


When a successful push is complete, a green "Finished DHCP Pushing Request" message will appear, and the window may be closed.

Schedule Push (from Pool Details page):


The Pool Details page includes an option to schedule a push, similar to scheduling a Group push.



Click "Schedule Push" for the pool, then select a date, time (12 hour, with AM / PM toggle), add a notification email address, and click "Save changes".



The Scheduled task will be shown in both the Pool Details page (under "Scheduled Tasks") and the Admin Scheduler task list.



The task may be deleted prior to running by clicking the "delete" button, but will automatically be removed once completed.

Schedule Push (Admin Scheduler):

Pools may also be pushed via scheduled DHCP Group or DHCP Server pushes. Server pushes may be set up by Admin users from either the **DHCP Servers** section, or the **Scheduler** tab.

For more information, see the Working with DHCP Servers or Scheduler Tab documentation.

DHCP Group Push:

All pools contained in a DHCP Group may be pushed at the same time, by pushing the DHCP Group.

For information on working with DHCP Groups, including performing a manual or scheduled Group push, see Working with DHCP Groups - Pushing a Group.


DHCP Server Push:

Admin users may push all pools on a DHCP server from the **DHCP** Tab -> **DHCP Servers** page.

For information on working with DHCP Servers, including performing a manual or scheduled server push, see Working with DHCP Servers - Pushing a Server.

Delete a Pool

Users with delete permissions over the pool may delete it by clicking the "Delete" button under "Actions" from any DHCP Pool List.



Addiitonal Information:

For more information on working with DNS Zones, Groups, and Servers, see the following sections:

DNS Tab

Working with DNS Groups

Editing DNS Zones (The View Zone Page)

DNS Administration

Import DNS Zones

Working with DHCP Gadgets

Working with DHCP Gadgets

There are two DHCP Gadgets available to integrate onto a Resource Entry Page - the DHCP Management Gadget, and the DHCP Customer Configuration Gadget.

For an overview of Gadgets and how to attach them to Resource pages, see Gadgets and Adding a Gadget to a Section .

- Working with DHCP Gadgets
- DHCP Management Gadget (Legacy)
    - Before You Begin:
        - Attach / Enable the DHCP Gadget
        - Managing DHCP Server Configurations
        - Group Management
            - Working with DHCP Groups
        - Connection Configuration
        - Server Details
        - Scan Server
        - DHCP Pools
            - DHCP Pool Search:
        - Create a New DHCP Pool - Subnets
        - Create a New DHCP Pool - Host
        - Current Pushed Configuration
        - Saving/Pushing DHCP Server Configurations
- Working with the DHCP Customer Configuration Gadget
        - Setting up the DHCP Customer Configuration Gadget
        - Using the DHCP Customer Configuration Gadget
    - Additional Information

DHCP Management Gadget (Legacy)


Note: As of ProVision 7.0.0, the DHCP Management Gadget is a legacy feature.

While it is still available to be used, we recommend checking out the updated **DHCP** Tab and using the DHCP Groups, DHCP Servers, and DHCP Pools pages as the primary DHCP management system.


Before You Begin:

Attach / Enable the DHCP Gadget

Verify that the DHCP Gadget is attached to the Resource Section. Then, you can enable the gadget by selecting the radio button next to "On", and click "Update".



Once enabled, the DHCP Management Gadget will show sections for "Group Management", "Connection Configuration", "Server Details", "Scan Server", "DHCP Pools", and "Create a New DHCP Pool". Once pushes or unpushed configuration changes occur, a "Current Pushed Configuration" or "Unpushed Configuration" section will be available for review.



These sections will be reviewed in detail further on in this section.

A Note on DHCP Aggregates


ProVision versions prior to 7.0.0 required creating or identifying specific IPAM blocks as "DHCP Aggregates" using the "DHCP Available" status to assign DHCP pools from.

As of 7.0.0, these statuses have been removed, and any IPAM block may be used to assign DHCP pools from, as long as they are subassignable and meet the assignment criteria provided by the user.

This applies to all DHCP Management functions - the DHCP Management Gadget, DHCP Customer Configuration Gadget, and all DHCP Tab areas.

Managing DHCP Server Configurations


Once DHCP functions are enabled for a Resource Section, you will be able to manage configurations per Resource by expanding the relevant areas on the Resource's Entry page.



Group Management

This section of the DHCP Management Gadget allows you to create and manage DHCP Groups.

DHCP groups help you to organize all of your Pools and Servers together into a single place, and push pools linked to a DHCP Group to all of the servers attached to that Group. It also allows for the designation of a DHCP Failover Peer for ISC BIND servers.



Working with DHCP Groups


Step 1: Create DHCP Servers

Ensure that all necessary DHCP servers are created via the **DHCP** Tab **DHCP Servers** page. See Working with DHCP Servers for additional information.


All DHCP servers listed under the DHCP tab will be available to select to attach to DHCP Groups (in the format of "ResourceID - DHCP Module").

Step 2: Create DHCP Groups

Select a DHCP server page with the DHCP Management Gadget from, and expand the Group Management section. Note: Any DHCP server page with the Manangment Gadget is fine to use, as the Group Management section will globally update to be the same in any DHCP Management Gadget. As of ProVision 7.0.0, DHCP Groups may also be created and managed from the DHCP Groups page under the **DHCP** Tab.



A "Default Group" should be available immediately, or you can click the "Add Group" button to create a new DHCP Group. Type in the desired Group Name and select a Parent Resource for the Group, then click "Create Group".



Your new Group will be available in the DHCP Management Gadget. To delete the DHCP Group, click the "X" next to the Group name.

Step 3: Attach DHCP Servers to Groups

All DHCP servers listed under the ProVision DHCP Tab will be available to select and attach to the Group. They are identified by their resource ID number, so if necessary, check the server's resource ID number in the resource information Gadget.



Select the desired server from the "Attach Server" selector, then click "Attach". The server is now attached to the group and available for pushes.



If needed, a server may be removed from a DHCP Group by clicking the "Detach" button.

Step 4: Identify Failover Peer (Optional - ISC Bind Only)

If a DHCP failover peer is configured for the server, enter the server name and click the "Save" button. In the event that the primary server fails to push, the push will be sent to the failover peer instead.




Step 5: Link Pools to DHCP Groups

From the Existing Pools list under the DHCP Pools section, click the Action Menu for the pool you wish to link to a DHCP Group. From there, click "Link to Group".



If multiple DHCP Groups exist, a dialog will pop up for you to select the desired Group to link the pool to. Select the DHCP Group, then click "Confirm" to add the pool to the Group.




Once linked, the DHCP Pool will show under the "Linked Group Pools" area of the DHCP Pool section. From here, if desired, you may remove the pool from the group by clicking the Action Menu and "Remove Link".



Step 6: Push the DHCP Group


Lastly, click the "Push" button for the DHCP Group to push the linked pool(s) for the Group to the linked DHCP Module, and then push all DHCP servers linked to the Group.



While pushing, a status box will appear to show status and any errors, if applicable.


Connection Configuration

In this gadget area, you may enter in the information that will be used for ProVision to communicate to the DHCP Server.



Server Details

Server details and advanced options may be entered under this portion of the gadget.



Server Command: Config Test

A note on the Server Command: Config Test option:

This command is run after the newly-written DHCP Config file has been transferred to the server but before the server is restarted. Due to the wide variety of DHCP install configurations that can arise on different systems, it is best if the Config Test option is as explicit as possible. For example:

sudo /usr/sbin/dhcpd -t -cf /etc/dhcp/dhcpd.conf


This command explicitly requests the DHCP daemon start in test-only mode (-t) with a specific config file (-cf). This config file should be the location supplied in the "DHCP Config File Path" section.

Scan Server

Scan Server provides a "Scan Now" button, which scans the DHCP server and returns found IPs under DHCP Pools.



The returned IPs are divided by Pools and IPv4/IPv6. Returned fields include MAC address, IP address, and name. The percentage utilization of IP space out of the available DHCP Pool space is also included at the top of the list.



Hostname	MAC	IPv4	IPv6
Unknown Host	08:d8:33:93:87:70	10.1.10.35	
sep58bfea1164be	58:bf:ea:11:64:be	10.1.10.136	
Unknown Host	00:0e:8f:88:5b:8f	10.1.10.82	
philips-hue	00:17:88:24:2e:8b	10.1.10.85	
Unknown Host	00:0c:29:62:6c:57	10.1.10.59	
directv-hr44-b1550683	10:77:b1:55:06:84	10.1.10.30	
Unknown Host	00:80:a3:91:47:ae	10.1.10.55	
lifx bulb	d0:73:d5:00:06:a6	10.1.10.86	
sonoszb	00:0e:58:1c:e0:0a	10.1.10.108	
lifx bulb	d0:73:d5:00:ae:e2	10.1.10.96	
lifx bulb	d0:73:d5:00:a8:43	10.1.10.87	
Unknown Host	f4:b8:5e:00:7b:f3	10.1.10.89	
Unknown Host	74:29:af:d6:ba:8d	10.1.10.32	
Unknown Host	ec:e0:9b:b7:f3:15	10.1.10.51	
lifx bulb	d0:73:d5:00:20:51	10.1.10.81	
sonoszp	00:0e:58:ff:8e:82	10.1.10.109	
npi4305e9	4c:0f:6e:90:7a:da	10.1.10.75	
Unknown Host	74:75:48:08:bb:b1	10.1.10.77	
Unknown Host	a0:02:dc:1c:c4:aa	10.1.10.103	
Unknown Host	94:10:3e:4c:82:c9	10.1.10.79	
Unknown Host	00:25:90:02:ff:42	10.1.10.58	
living-room	c8:69:cd:2c:38:56	10.1.10.44	
kitchen	c8:69:cd:37:c9:bc	10.1.10.66	
iphone6splus	7c:01:91:d1:34:f3	10.1.10.104	
macbook	a8:66:7f:15:6b:85	10.1.10.39	
iphone1	d8:bb:2c:7a:61:8e	10.1.10.37	
mac-mini	20:c9:d0:96:4e:9d	10.1.10.107	
bedroomappletv2	6c:94:f8:e1:b0:14	10.1.10.54	
mac-air	9c:f3:87:b1:5b:b6	10.1.10.90	
livingroom	a4:67:06:64:b3:97	10.1.10.49	
aarons-imac	b8:09:8a:ba:dd:4f	10.1.10.34	
iphone-88	5c:ad:cf:03:3b:66	10.1.10.45	
ipad2	2c:1f:23:49:1f:93	10.1.10.84	
Unknown Host	34:46:6f:0a:c5:a1	10.1.10.33	
02aa01ac351309sc	18:b4:30:0c:c5:27	10.1.10.31	
Unknown Host	00:11:32:16:29:ef		2607:fae0:6000::514c
Unknown Host	20:61:73:79:6e:ff		2607:fae0:6000::5e35
Unknown Host	88:1f:a1:2a:d7:71		2607:fae0:6000::5065

If the scan is unable to be completed, an error message will appear in the DHCP Management section.

DHCP Pools

In this area, the admin can specify what DHCP Pools are linked to the DHCP server or DHCP Groups.

This includes any host reservations as well as DHCP Pools as defined in the next section.

Use the Action menu on Existing Pools to Link to Server, Link to Group, or Delete Pool

The Action menu for Linked Pools will show the option to Remove Link from Pools.



Additional edits may be made to pools by clicking on the Pool name. This allows the Pool name, assignment, and lines to be changed. Be sure to hit "Save" after making changes.



DHCP Pool Search:

Both Linked and Existing DHCP pools have field-specific search options to filter the DHCP pool list(s). Select the search term type from the dropdown list, type the search term in the search box, then hit "Search".




For both Linked and Existing pools, search terms include:

Name: The full or partial name of the pool (ex: "Lab")

MAC: The full (ex: 00:11:22:33:44:55:66:77) or partial (:22) MAC address, for pools that were created as "Host" type. MAC address searches must include a colon.

IP: Search by IP Block by providing the CIDR assigned to the pool. *(ex: 10.0.0.0/24)*

For Existing Pools, additional filter terms may be included to further filter the IP search by Region or assigned Resource.



After entering your search terms, click "Search", and the pool list will filter to the results.

Create a New DHCP Pool - Subnets

When Assigning a Subnet (via dropdown) the IP Assignment selection will pull the data from any IPAM block meeting your defined criteria. You can use either a Smart or Direct assignment depending on your preference. For Smart Assign pool creation, existing IP Rules may be applied to reserve additional addresses out of the pool range. To create an IP Rule, see IPAM Rules.

DHCP Pools and IP Rules


For DHCP Pools, ProVision automatically reserves the first and last address of the pool for Gateway and Broadcast addresses, respectively.

If an additional IP Rule is applied, the rule will begin with the second address in the block.

For example: if a DHCP Pool is created using 10.0.0.64/29 with an IP Rule of "Reserve First Three", the resulting pool range would be 10.0.0.68 through 10.0.0.70, as the first four as well as the final address would be reserved.

Enter the name of the Pool / Subnet, and select the assignment criteria:

For **Smart Assign**: select IPv4 / IPv6, Mask, then optional Region, Resource assignment, Domain - VLAN, and IP Rules criteria, add free lines if desired, then click "Add Pool".



For **Direct Assign**: select IPv4 / IPv6 and enter the block in CIDR format, add free lines if desired, then click "Add Pool".




Create a New DHCP Pool - Host

When reserving Hostname/MAC data, change the Dropdown to "Host". This will also give you an option to assign from an existing DHCP block (smart assign) or a specific IP address (direct assign).

Enter the name of the Hostname and MAC address, then select the assignment criteria:

For **Smart Assign**: select IPv4 / IPv6, then optional Region, Resource assignment, Domain - VLAN, and IP Rule criteria, add free lines if desired, then click "Add Pool".




For **Direct Assign**: select IPv4 / IPv6 and enter the block in CIDR format, add free lines if desired, then click "Add Pool".



Current Pushed Configuration

Expanding "Current Pushed Configuration" allows you to view the detailed text (read-only) of the last sucessfully pushed configuration.

Current Pushed Configuration does not reflect any un-pushed changes or failed pushes.




Saving/Pushing DHCP Server Configurations

It is recommended that you save your configuration after changes. Save your changes by clicking the "Save Configuration" button at the bottom of the DHCP Management Gadget.

When you Push a Configuration (by clicking "Push Configuration") the configuration is automatically saved.



Working with the DHCP Customer Configuration Gadget



The DHCP Customer Configuration Gadget allows users to assign IP aggregates to the DHCP server pools and generate DHCP Server Configuration changes.

These configurations are then sent to the associated DHCP server Management Gadget as "Unpushed Configurations", where they may be held until a manual or schedule push occurs.


Setting up the DHCP Customer Configuration Gadget

Before using the DHCP Customer Configuration Gadget, the following should be set up in ProVision:


- The associated DHCP server should be created in ProVision and set up in the DHCP Management Gadget (See: DHCP Tab).
- Add the DHCP Customer Configuration Gadget to the desired Section. You may want to create a specific "DHCP Customer" Section for DHCP customer entries (See: Customizing Sections).
- Have, or set up IPAM Aggregates with subassignable blocks from the **IPAM** Tab with the desired IP space type, RIR, Region(s), Tags, and any desired VLAN criteria. Regions are a required field when assigning IPs from the DHCP Customer Configuration Gadget.

Using the DHCP Customer Configuration Gadget


Step 1) Link the Gadget with the desired DHCP Server



Step 2) Assign IP's for Pools from DHCP Aggregates



Step 3) Set up configuration information - add Option 82 Elements, Circuit ID, and notes. Use the "Preview" field to confirm the accuracy of the data, and select the status as "Activate" or "Terminate".
Once saved, the updated configuration will be sent to the DHCP Management Gadget.



Step 4) an admin user may manually push the updated configuration from the DHCP Management Gadget, or use a scheduled DHCP push task to automate the pushes.


See Gadgets - DHCP Customer Configuration for more details.

Additional Information

For more detail on advanced DHCP topics and the DHCP API, see API Module - DHCP.

IPAM Tab

IPAM



The **IPAM** tab contains three sub-tabs: **IPAM**, **VLAN**, and **Logging**.

The **IPAM** tab provides a listing of top-level aggregate blocks, tools to add, merge, sparse allocate, and manage aggregates, as well as multiple data visualizations. The blocks under each aggregate may be individually assigned, edited, swip'ed, and managed from the IPAM Manage page for the aggregate. For detailed information on specific aggregate and block tasks, see Working with IP Aggregates, Working with IP Blocks, and Working with IP Rules. For administrative level tasks, see IPAM Administration.

The **VLAN** tab shows an overview of domains and VLANs on the left sidebar, and IPAM Utilization data organized by each domain / VLAN pair. From here, Admins may add, remove, and edit domains and VLANs. Standard users may add/remove VLAN associations with blocks (as long as they have permissions on those blocks), and browse VLAN Manage (similar to IPAM Manage). See Working with VLANs for details.

Logging provides a quick link to ProVision's logging system, where you can filter to view IPAM-only logs.

- IPAM
- IPAM Tab Overview
  - Advanced Button
  - Add Aggregate
  - Map View
    - Map View Overview
    - Enabling Map View
    - Working in Map View
  - Aggregate Blocks List
    - Search / Filter Aggregates
  - Top-Level Aggregate / Host Utilization Box Overview
- IPAM Workflow
  - IP Management
    - Add Aggregates
    - Manage Aggregates
    - Assign Aggregates
    - Delete Aggregates
  - IP Assignment Lifecycle
    - IP Block Status
  - Additional IPAM Features
    - ProVision IPAM-As-WHOIS
      - Setup
        - Running the Server manually
        - Quering the WHOIS server

        - Installing the WHOIS server as a service
        - systemd
        - init.d
    - GEO IP Exporter
- Working with IPAM Aggregates
- Additional Information


IPAM Tab Overview

Advanced Button




Opens the **IPAM Manage** screen for all blocks under all aggregates. See Working with IP Blocks for more information on working in IPAM Manage.

Add Aggregate



The "Add Aggregate" button opens a new page to add an aggregate block with options for RIR, VLAN, Tags, Region, Resource, and enabling Sub-Assignments.




When done, click "Add Aggregate". The IPAM Tab home page will automatically load, and the new aggregate will be listed under the Host Utilization and Aggregate Blocks list of the IPAM Tab for further management.

Map View

Map View Overview

Map View shows aggregate locations / recent assignments in geographical format, based on the region assigned to those aggregates. Clicking on a location icon will bring up a current utilization graph and a link to that aggregate's IPAM Manage page if in Aggregates view, or recent assignment details if in Recent Assignments view.



Google Geocode API Key Requirement for Map View

Due to changes in Google's licensing and Geocoding API, the geolocation method used for Map View in ProVision versions pre-v7.1.0 is no longer supported.

A Google Geocoding API Key is now required for geolocation data to be accessible by ProVision, and for IPAM Maps to properly determine a Region's location. As a result, IPAM Map View in versions older than 7.1.0 may not accurately display or update location information.


6connect is exploring adding additional map integration options for ProVision. Any customers who require an alternative geocode option supported apart from Google Geocode API key, please contact us at feedback@6connect.com.

Enabling Map View

The IPAM aggregate map view may be enabled / disabled from the IPAM Configuration page. Once enabled, a map module will be able to be expanded in the IPAM Tab.

The following criteria must be met for Map view to correctly show data:

- Map View enabled on the IPAM Configuration page



- A Google Geocoding API Key provided in the Edit Regions page. See Edit Regions for additional detail.

  Step 1: Obtain a Google Geocoding API Key


  To get a Google Geocoding API Key, follow the instructions listed here:

  How to get a Google Geocoding API Key

  Note: In order to obtain a Google Geocoding API Key, a company must have a subscription enabled to Google Cloud Platform Console.

  Step 2: Assign the API Key to IPAM Regions

  Once assigned a Google Geocoding API Key, paste the API key into the IPAM regions page under "Google Geocode API Key" and click the "Apply" button.



- Regions created with a valid "Address" (location) field. See Edit Regions for additional detail.

  The "Address" field may be a street address, city, airport code, or geo-coordinates.

  Valid addresses (according to Google's API) will show a green check mark next to the address field, invalid addresses (unable to be mapped) will show a yellow exclamation mark.



Region Code	Name	Address	Action
SFO	San Franscisco	SFO	Update
5520	Berlin	5520 West 76th St., Berlin, Germany	Update
701	Indy	701 West henry St., Indianapolis, IN	Update
London	London	London, UK	Update
Rome	Rome	.....	Update
CHI	Chicago, IL	Chicago, IL, USA	Update

Miscellaneous Terms as Addresses

Being that the validity of the "Address" field is determined by Google's API, unexpected location mapping may occur if a company name or other non-location specific term is used in the Address field.

Google treats the item as a search term and returns the most likely location result back - but it might not be what you were expecting! When in doubt, check the address term by pasting it into Google Search, and verify that the top result returns your desired location.

- Regions enabled in IPAM Columns and assigned to aggregates / blocks for the IPAM Map view to populate data. See Edit IP Block Attributes for additional detail.

Working in Map View

The map view may be set by either selecting a predefined map area from the "Maps Settings" "Positioning" dropdown (US, US & Europe, South America, All), or chose a custom area set by zooming / navigating to the desired map area.



To save the currently viewable area as the Default view, click the pin icon to "Save current position as Default".




Map View Settings:

Visualization: Select "Aggregates" to view all available aggregates with region data, or "Recent Assignments" to view block assignments made within the past 30 days.

Positioning Dropdown: Select a predefined area for the map view range: US, US & Europe, South America, or All.

Save current Position as Default: Click the pin icon to save the current map view range as the default view.

Aggregate Detail Box:




Provides utilization data and a shortcut link to the IPAM Manage screen for that aggregate if in "Aggregates" view, or assignment details if in "Recent Assignments" view.

Aggregate Blocks List

Provides a searchable / filterable listing of all aggregate blocks in the left sidebar, links IPAM Manage for the aggregates, and Merge Aggregate functionality.


If a note has been entered for a top-level aggregate (the topmost parent block), the note will display under the aggregate listing.




Search / Filter Aggregates

Search for and filter IPAM Aggregates from the Aggregate Blocks List:


- Select "All", "IPv4", IPv6", or "DHCP" to sort the list by type (You may also access the type filters by right clicking anywhere in the Aggregate Blocks box)
- User the filter / search box to search by CIDR
- Filter by Region or RIR by clicking the "more filters" link, then selecting an item from the dropdown menus.
- Single click on the CIDR to zoom to the aggregate details in the Utilization list
- A shortcut to IPAM Manage for an aggregate is provided by clicking the "open" link that appears when hovering over an aggregate block in the list.



To reset the list, right click anywhere in the Aggregates Blocks list and select "Reset View".



Top-Level Aggregate / Host Utilization Box Overview



The Top-Level Aggregate Host Utilization box provides detailed information on that aggregate, including:


- **CIDR**: Single-click to IPAM Manage for the aggregate
- **RIR information:** displays the aggregate's RIR, as set at creation (1918, ARIN, RIPE, LACNIC, AfriNIC, APNIC)
- **Aggregate Chart Views**: Four Aggregate chart views are available, - **Pie**, **Bar**, **Tree**, and **Grid** view. Switch between each chart by clicking on the respective icons in the Aggregate header (marked above).
- **Aggregate Actions (Gear Icon):**
  - **Edit:** Opens IPAM Manage for the aggregate. See Working with IP Blocks for information on working in IPAM Manage. Clicking on the Block CIDR in the header also opens the IPAM Manage page.
  - **Delete**: Deletes the Aggregate (provides a warning).
  - **Enable / Disable Sparse Allocation** (IPv6 only): Enable or disable Sparse Allocation for an IPv6 aggregate. Enabling will automatically generate a Numbering Authority Sparse Allocate Domain for use with the aggregate.
  - **Sparse Allocate** (IPv6 only): Appears only when Sparse Allocation is enabled for an IPv6 aggregate. Opens a menu to select or create a resource to assign a block to, using the sparse allocate algorithm to disperse the assignment(s) throughout the aggregate. See: Working with IP Aggregates
- **Region(s):** Displays the primary region(s) associated with the aggregate, either at aggregate creation or from regions associated with blocks under that aggregate. Clicking on the region link for an aggregate will open IPAM Manage for the aggregate, filtered to view blocks associated with that region.
- **Utilization:** Utilization displayed as both a pie chart and detailed percentages. Utilization statuses include:
  - **Available:** A status of "Available" indicates the block is free and able to immediately be assigned or allocated to a resource.
  - **Allocated:** Allocated blocks have been assigned to an overarching resource, but have subassignments enabled and may have smaller blocks assigned out of them to other Resources, such as customers or DHCP Pools.
  - **Assigned:** A status of "Assigned" indicates that the block has been assigned to a Resource, with no subassignment capability, and is unavailable.
  - **Holding:** Blocks in "Holding" have recently been unassigned, and are held for a set duration in the IPAM Holding Tank, unless otherwise overridden, reassigned, or reclaimed from Holding.
- **Resources:** The top five Resources assigned under that aggregate with the most assigned block space.
- **Recent Assignments:** The five most recent block assignments under that aggregate, with the CIDR, assigned resource link, and assignment date.

IPAM Workflow

IP Management

IP Management is comprised of four basic functions: adding aggregates into ProVision, managing those aggregate blocks, assigning them to a resource, and deleting the aggregates.

ProVision provides multiple ways for you to achieve each step, depending on your needs. For example, if your organization currently uses spreadsheet data to track aggregates, ProVision provides tools that can import your existing spreadsheets for bulk updates, saving you time. Need to just quickly assign a single IP? Direct Assign will allow you to do so with just a few clicks.



Add Aggregates

Adding new aggregate may be done manually, automatically from a RIR import, or imported from a .csv file.

- **Manually:** Create a new aggregate via the IPAM Tab. See: Working with IP Aggregates.
- **Import from RIR:** ProVision will automatically identify your RIR / organization and show available aggregates, or you can enter in an ORG ID or IP. See Import Aggregate .Blocks
- **Import from .csv:** Normalize your data as detailed in Importing Your Data - Normalize your Data, and then use ProVision's IP Import from .csv tool.

Manage Aggregates

Edit, Split, Merge, and connect with RIRs to architect the aggregates as needed and update WHOIS information, if applicable.

- For aggregate level actions, like splitting, merging, and editing, see Working with IP Aggregates - Common Tasks .
- RIR Integration requires LIR setup. See LIR Management and Use and RIR Integration: SWIP/RPSL .
- Editing individual blocks under an aggregate can be done from either IPAM Manage or the IPAM Gadget. See Working with IP Blocks and Working with IP Rules.

Assign Aggregates

Aggregates may be assigned to a Resource at their creation/import, or assigned later manually or via Smart / Direct Assign.

- To assign at manual aggregate creation, just select a resource from the dropdown in the IPAM Tab - Create Aggregate dropdown. See: Working with IP Aggregates.
- To assign during import, either include the resource assignment as a field in your .csv, or edit the import during the review step to assign a resource. See IP Import from .csv.
- Manual assignments may be done at any time in IPAM Manage or Smart/Direct Assign. See: Working with IP Aggregates and Working with IP Blocks.

Delete Aggregates


Delete an aggregate from the aggregate box in the IPAM Tab. See: Working with IP Aggregates.

IP Assignment Lifecycle

In ProVision, the IP assignment lifecycle starts with an available block which is free to be assigned to any IPAM-enabled resource holder. There are multiple methods that may be used to assign a block to a resource holder: Smart Assign, Direct Assign, or Manual Assign (Smart Browse). See Working with IP Blocks for details on assigning blocks.

Once an IP block is assigned, blocks can be further subassigned via the same methods, if desired, by using the "allow subassignments" toggle when editing an assigned block. If a block has subassignments enabled, but has not yet been subassigned, it is listed as "Allocated" - essentially held by the parent resource, but not fully assigned.

When an assigned block is un-assigned it proceeds into the Holding Tank: a special resource where blocks are held until either a set time has elapsed or until they are manually reclaimed to 'available' status. If a subassigned block is unassigned, it too proceeds to the Holding Tank if not overridden, and then reverts back to allocated to the original parent resource.



IP Block Status

- **Available:** A status of "Available" indicates the block is free and able to immediately be assigned or allocated to a resource. Available blocks may be assigned via any assignment method - manual, smart assign/browse, and direct assign.
- **Assigned:** A status of "Assigned" indicates that the block has been assigned to a Resource, with no subassignment capability, and is unavailable.
- **Allocated:** Allocated blocks have been assigned to an overarching parent resource, but have subassignments enabled and may have smaller blocks assigned out of them to other Resources, such as customers or DHCP Pools. Allocated blocks count as "Available" for reporting functionality until subassigned, but are shown as their own category on the IPAM Utilization charts. Once subassigned, the block is considered "Assigned".
- **Holding:** Blocks in "Holding" have recently been unassigned, and are held for a set duration in the IPAM Holding Tank, unless otherwise overridden, reassigned, or reclaimed from Holding.

For more information on performing tasks in this IP Assignment Lifecycle, see the following documentation sections:

Working with IP Blocks

IPAM Administration

Additional IPAM Features

ProVision IPAM-As-WHOIS

ProVision supports utilization as a WHOIS server via REST API requests. You can query Resources, Contacts, and IP Blocks, just like a traditional WHOIS server, only ours serves data from the ProVision database.

This feature provides an alternate route to provide ProVision data to legacy workflows on your network. If a team is used to query WHOIS, they can query Provision. If a system needs to talk to WHOIS, it can talk to ProVision-as-WHOIS.

Setup

The ProVision WHOIS Server is a thin client for our REST API that listens on port 43 and accepts WHOIS requests that gets forwarded to our API. It is written in Python 3 using the **socketserver** module, and uses the ProVision endpoint **/api/ipam/whois** to receive all requests from the WHOIS server.

The main business logic is located in **services/WhoisService.php**

Running the Server manually

The server is located at **whois_server/main.py** in the ProVision repository.

Running the server can be done with: **sudo python3 main.py** (We need root because we are binding to port 43)

Quering the WHOIS server

1. install whois if not present (sudo apt-get install whois)
2. whois -h 127.0.0.1 <query>

Installing the WHOIS server as a service

Different Linux distributions might have different ways to setup a service that runs on startup.

systemd

There is a Unit file for systemd in the repository: **whois_server/provision_whois.service** that is used when a service is created in systemd env.

1) Edit the file to setup the proper path to the python server/file

```
ExecStart=/usr/bin/python3 /root/whois_server/main.py
WorkingDirectory=/root/whois_server/
```

2) Copy the file to **/etc/systemd/system** (on CentOS this directory should be: **/lib/systemd/system/**) -

sudo cp whois_server/provision_whois.service /etc/systemd/system/provision_whois.service

3) Start the service with **service provision_whois start**

4) Verify that is working with **service provision_whois status** and making a test query **whois -h 127.0.0.1 <query>**

The systemd services are run as root, so there shouldn't be issues with binding to port 43.

init.d

There is also init.d file located at **whois_server/provision_whois**

1) Edit the file to setup the proper path to the python server/file

```
DAEMON_OPTS="/var/www/projects/whois/app.py"
```

2) Copy the file to **/etc/init.d/**

3) **chmod +x /etc/init.d/provision_whois -v**

4) Verify that is working with **service provision_whois status** and making a test query **whois -h 127.0.0.1 <query>**

GEO IP Exporter

ProVision supports the entering and export of IETF format-compliant GeoIP data for resources which have assigned IP blocks.

The Geo IP Exporter may be enabled as a scheduled task (See: Scheduler Tab) that, at run time, searches the ProVision instance for resources which have IP addresses and an address provided in the Contact Info Gadget, then saves the resulting .csv to the ProVision root directory.

If a resource has an assigned IP address, and either Geo IP location data or a Mailing Address entered in the Contact Info Gadget, then the data will be included in the .csv output. If an IP address is not associated with the resource, or if neither Geo IP / Mailing Address has been provided, the resource will be skipped.


This feature includes updates to the following areas:

- Updates to the Contact Info Gadget to provide Geo IP fields
- A Geo IP Export Scheduler Task
- Writes files to the ProVision root directory


For additional information, expand the walkthrough below:

1) Enter GEO IP data to Resources

Add GEO IP location data to a Resource by selecting "Edit" for the Contact Info Gadget.




Enter a separate address to denote as the GEO IP location, or you may select "Same as Mailing Address":




2) Set up the Geo IP Export Scheduler Task

Create a Scheduler task to export GEO IP data:




3) Run the Scheduler Task / File Access

Run the GEO IP scheduler task, either via "Run Now" or as a scheduled run - the task will search for resources with an assigned IP address, and either Geo IP location data or a Mailing Address entered in the Contact Info Gadget, and add the data to the .csv output.



Once the task has completed, the GEO IP data will be written to the ProVision root directory as "geoip_feed.csv":



Working with IPAM Aggregates


For additional information on performing IPAM tasks and working with aggregates and blocks, continue on to Working with IP Aggregates and Working with IP Blocks.

Additional Information

- Working with IP Aggregates
- Working with IP Blocks
- Working with IP Rules
- VLAN

Working with IP Aggregates

Working with IP Aggregates



IPAM Aggregates

IP Aggregates are edited and managed from the **IPAM** Tab and IPAM Manage page.

Aggregates may be viewed, filtered, created, and deleted from the **IPAM** Tab, and setting IPAM alerts and using Aggregate Templates are performed in IPAM Manage.


For an overview of the IPAM Tab, see IPAM Tab. For information on working with individual blocks, continue to Working with IP Blocks.

- Working with IP Aggregates
- Working with IP Aggregates - Common Tasks
  - Add an Aggregate
  - Delete an Aggregate
  - Merge Aggregates
  - Sparse Allocate in an IPv6 Aggregate
    - Sparse Allocation Schemes
    - Enable/Disable Sparse Allocation
    - Sparse Allocate
  - Manage an Aggregate
    - Open IPAM Manage for an Aggregate
  - Aggregate Actions
    - Auto Split Aggregate
    - Clean Up Aggregate
    - Set Aggregate Alerts
- Working with IP Blocks
- Additional Information


Working with IP Aggregates - Common Tasks

Add an Aggregate

On the main **IPAM** Tab, click the "Add Aggregate" button. A new page will open to fill in details for a new aggregate block.



Enter in the desired IPv6 / IPv6 CIDR and RIR, at minimum. Region, Tags, Resource, Domain, VLAN, and subassignment status are optional, if desired.




If creating the aggregate for a specific use, keep in mind that certain uses may require additional information is provided in the aggregate, such as requiring 1918 space (DHCP Pools), a region to be provided (DHCP Customer Configuration Gadget), or a resource to be assigned with subassignments enabled. In such cases, it may be useful to assign a specific IPAM tag to associate with that use to assign at aggregate creation (such as "DHCP")

When done, click "Add Aggregate", and you will be redirected back to the IPAM Tab home page. The Aggregate will be listed under the Host Utilization and Aggregate Blocks list of the IPAM Tab.

Delete an Aggregate

Aggregates may be deleted from the Gear Icon in the top right corner of their Host Utilization box display.




A warning dialog box will appear confirming the deletion, and noting whether assigned blocks exist in the aggregate that would also be deleted.


Merge Aggregates

Adjacent Top Level Aggregates may be merged into a single aggregate, if meeting validity criteria (adjacent, but not overlapping).


To do so, right click anywhere on the Aggregate Blocks list, and choose "Select Aggregates" from the menu.



Then, click the check boxes for the two aggregates you wish to merge, and then right click and select "Merge Selection".




A confirmation dialog box appears to confirm the blocks to merge, and proceed with testing to see if the merge is valid. Click "Test Merge" to proceed.



ProVision will pre-test the merge, and if valid, give you the option to proceed.

Otherwise, an error message will display detailing why the aggregates are unable to be merged.



Complete the aggregate merge by clicking "Merge".

To Exit out of the selection prior to merging, select "Close".


Sparse Allocate in an IPv6 Aggregate

Sparse allocation evenly distributes assignments throughout an IPv6 range, using either a manually configured or automatically generated "Sparse Allocate" Numbering Authority domain algorithm to calculate the next block to assign.

Sparse Allocation Schemes

Admins may select a system default Sparse Allocation scheme to use for IPv6 Sparse Allocation. Available values are Leftmost, Center, and Rightmost. If not otherwise specified, Leftmost is the ProVision Default.


To edit the Sparse Allocation Scheme, select the desired scheme in IPAM Configuration, then enable sparse allocation for the desired IPv6 aggregate. The Sparse allocation scheme is applied to the aggregate when sparse allocation is enabled for the aggregate, thus, pre-existing sparse allocation schemes will not be altered by later changes.



If you wish to change the scheme for an existing sparse allocated-enabled aggregate, you must


1) Disable sparse allocation for the aggregate 2) Edit the selected scheme 3) re-enable sparse allocate for the aggregate.

To verify which scheme is applied to aggregates, you may view the aggregate and scheme details in the Numbering Authority Sparse Allocate listings.



Enable/Disable Sparse Allocation

Sparse allocation options are accessed from the IPv6 Aggregate's Action Menu (gear icon). The top right corner of the Utilization module for the IPv6 aggregate will display whether sparse allocation is enabled or disabled for the particular aggregate.




Enable or disable Sparse Allocation for the aggregate by clicking on the aggregate menu, and select to Enable / Disable Sparse Allocation for the aggregate. A "Sparse Allocate" Numbering Domain will automatically be generated for the aggregate in the Admin IPAM Admin area of ProVision, using the currently set Sparse Allocation Scheme setting.


Once enabled, the "Sparse Allocate" option will be available for the aggregate.

Sparse Allocate

To Sparse Allocate assign the next IP generated, select "Sparse Allocate" from the aggregate action menu.



Then, select the resource to assign (or create a new one) and click "Assign".




The resource will be assigned according to the distribution algorithm and may be further managed in IPAM Manage for the aggregate.

Manage an Aggregate

Managing an aggregate is mostly performed in the IPAM Manage screen for the aggregate.

From IPAM Manage, you can perform the aggregate template actions of Auto-Split / Clean-Up, Set IPAM Alert information, export the block list, as well as manage individual blocks.

For detailed information on using the IPAM Manage screen and managing at a block level, see Working with IP Blocks.




Open IPAM Manage for an Aggregate

Open the IPAM Manage screen for a block by:


- Searching for the block in the Global search, and clicking on the resulting CIDR
- Clicking the "Open" link in the aggregate blocks list from the **IPAM** tab.



- Clicking on the CIDR header of the Aggregate Block Host Utilization module, or selecting "Edit" from the module's Gear Icon from the **IPAM** tab.




- Clicking on the CIDR listed in the Aggregate Info box in IPAM Maps



Aggregate Actions

Open up aggregate level actions in IPAM Manage by clicking on the "Actions" link in the Manage Aggregate header.


Three options are available - Auto Split, Clean Up, and Manage Alerts.



Auto Split Aggregate

Auto Split an available aggregate into blocks of a specific size, up to a specific quantity of blocks by selecting "Size" and "Limit" under "Auto Split".


The block limit must be a power of two, or an error will appear. When done, click "Split".



Clean Up Aggregate

Clean up an Aggregate into fewer blocks of a specific size, by selecting your desired block size and clicking "ignore assignments" (if blocks have assignments that would prevent merging).

When done, click the "Clean Up" button. All blocks will be merged to the set size and reset to available.




Set Aggregate Alerts

Enable or clear aggregate alert emails for the aggregate by setting an email address and utilization percentage level.

When the aggregate is utilized to the set percent, an email alert will be sent to the provided address.

Note: the "IPAM Alerts" task must be created and set to the desired notification frequency in the Admin Scheduler Tab in order for the emails to be sent.



When done, click "Save Alert". To clear an existing alert, hit "Clear Alert", and the alert information will be removed and status saved.

Working with IP Blocks

For additional information on performing IPAM tasks and working with blocks, continue on to Working with IP Blocks.


Additional Information

For additional information on working with the IPAM system in ProVision, see the following areas:

- IPAM Tab
- Gadgets (IPAM and IPAMv2 Gadgets)
- Working with IP Rules
- IPAM Administration

Working with IP Blocks

IP Block Management




Managing IP Blocks

IP Blocks are edited and managed in either IPAM Manage or the IPAM Gadget.

From either area, you can perform standard block-level actions such as assign, unassign, split, merge, edit attributes, track NAT associations, and more.

The primary difference between the two areas is that IPAM Manage shows all blocks (or all blocks under an aggregate), regardless of assignment or status, where the IPAM Gadget shows only the blocks assigned to the specific resource that you are currently viewing on the Resource Entry Page. However, the IPAM Gadget has more advanced assignment options and criteria available (Direct Assign, Smart Assign, Smart Browse).


IPAM Manage Features



IPAM Manage is accessed from: the **IPAM** Tab Edit Aggregate / Aggregate CIDR; **IPAM** Tab Advanced button; and most block CIDR Links in ProVision. Here, you can:

- Sort, Filter, and Export the block list
- Auto-Split and Clean-up templates available for aggregates
- View all blocks (IPAM Advanced), or all blocks under an aggregate, regardless of assignment
- Shows blocks from all statuses - available, in holding, assigned, subassignable
- Perform Single and Multi-block assignments and edits

IPAM Gadget Features



The IPAM Gadget is accessed from the **Resource Entry Page** IPAM Gadget, once it has been enabled for the section. Here, you can:

- View only the blocks assigned/assigned-and-subassignable under the Resource that you are currently viewing.
- Sort and Filter the block list
- Advanced assignment functions - Direct Assign, Smart Assign, and Smart browse with additional field criterial available.
- Perform single and multi-block edit, and assign subassignable blocks.

Both IPAM Manage and the IPAM Gadget have customizable column names, order, and visibility, as well as options for user-defined meta columns (for details on setting up customization of the IPAM Manage / IPAM Gadget block list, see IPAM Parameters Edit Columns).

Aggregate-Level Actions


Some aggregate-level actions are performed in IPAM Manage, such as setting IPAM alerts and using Aggregate Templates.

These actions are detailed on the IPAM Tab page under *Working with IPAM Aggregates.* This page will focus primarily on block-level actions and management.

- IP Block Management
- Working in IPAM Manage
  - Open IPAM Manage for a specific Aggregate
  - Open IPAM Manage for all Aggregates/Blocks
  - Viewing Blocks in IPAM Manage
    - Sort Blocks
    - Filter Blocks
    - View Parent Blocks / Hierarchy Tree
    - Important Blocks
- Working with IP Blocks - Common Tasks
  - IPAM Block Action Menu - Overview
  - Split or Merge Blocks Manually
  - Split or Merge Blocks Using Templates
  - Edit IP Block Attributes
    - Edit Attributes Overview:
    - IPAM Auto AS-Resource
  - Assign IP Space
    - Assign Space from the IPAMv2 Gadget
    - Direct Assign
    - Smart Assign / Smart Browse
  - Manually Assign Space from IPAM Manage

- Sub Assigning IP Space
- Unassign IP Space
- Working with NAT Blocks
    - Track IP NAT Associations
        - Working with NAT'ed Blocks
        - Enable NAT
        - Create NAT Association
        - Configure NAT to Router(s)
    - NAT Rotate Dynamic IPs
        - Before you Begin
        - Add Dynamic Tags to Blocks
        - Set up Scheduler Task
- Additional Information

Working in IPAM Manage



In IPAM Manage, you can manage aggregate level actions, such as Split , Clean Up, Alerts, and Export, as well as viewing and managing individual blocks. In IPAM Manage - Advanced, aggregate-level actions are not available.


Open IPAM Manage for a specific Aggregate

Open the IPAM Manage screen for a block by:


- Searching for the block in the Global search, and clicking on the resulting CIDR
- Clicking the "Open" link in the aggregate blocks list from the **IPAM** tab.



- Clicking on the CIDR header of the Aggregate Block Host Utilization module, or selecting "Edit" from the module's Gear Icon from the **IPAM** tab.



- Clicking on the CIDR displayed in the IPAM Map - Aggregates view.



Open IPAM Manage for all Aggregates/Blocks

Open IPAM Manage for all blocks under all aggregates by clicking the "Advanced" button at the top of the **IPAM** tab.



This will open IPAM Manage for all blocks in ProVision, with all the same filters, block edit functions, and search capabilities as in 'standard' IPAM Manage for an aggregate, but with no aggregate-level actions available.

When working in IPAM Manage - Advanced, be aware of the following:


- Due to the large volume of combined data that may be available, filter/search results may take slightly longer than load than a standard aggregate level view.
- Users should take care to ensure that they are working with the correct block(s), as duplicate 1918 space is permitted and blocks may be difficult to distinguish.

Viewing Blocks in IPAM Manage

Sort Blocks

Sort the IPAM Manage blocks list by clicking on any column name the in list with the up-down arrows icon ().


The list will sort between ascending and descending order for that field.



Filter Blocks

Filter the block list in IPAM Manage by toggling the "Filter +" link in the top right corner of the aggregate header.

A flyout will appear with filter criteria options. Type in or search for the term under your desired field, and hit "Apply". When done, click "clear". To hide the filter flyout, just click the "filter -" link again.




Type in or search for the term under your desired field, and hit "Apply".

When done, click "clear". To hide the filter flyout, just click the "filter -" link again.

View Parent Blocks / Hierarchy Tree


To view parent blocks / IP block hierarchy, click on "Switch to Parent View" at the top of the block list.




You may also enter Parent View from the "Filter" menu, by checking the "Select All Masks" checkbox and clicking "Apply".

Once all masks are enabled to view, the block list changes to include the "Parent" blocks, showing all masks throughout the assignment tree.

A parent block with children will show "Has Children" in the column where assignment status is shown, its immediate child resource (if applicable) and the block CIDR will show as a clickable link.




Clicking on the CIDR for a block that has children will open "Block Tree" view, showing the hierarchy of blocks and their assignments.




Important Blocks

"Important" IP blocks display with a yellow background highlight. By default, any block that has been manually assigned, unassigned, or had other high-level manual interactions performed will be automatically marked as "Important".



Blocks may be manually marked or unmarked as "Important" from either the "Edit Block" interface (by opening "Edit" for the block, then selecting the toggle for "Mark this block as important"), or from the API .



If multiple blocks are selected with mixed "important" statuses, then the toggle will display in the "Off" position. To update all selected blocks to flag as important, switch the toggle to "On", and save changes. To switch all to the "Off" position, you may either toggle all blocks to "On", save changes, then switch all blocks back to "Off" and re-save, or adjust your selection to only include the blocks that need the Important Flag removed. (Tip: Use the list filter to show only "important" blocks!)


Working with IP Blocks - Common Tasks

Individual Blocks may be managed from either IPAM Manage, or the IPAM Gadget. (if assigned to a resource, and the IPAM Gadget is enabled on the Resource's Entry Page).

In general, standard actions from the Action Menu will be performed the same in either area, with "Assign" being the exception.

IPAM Block Action Menu - Overview

Most actions performed with block managed are contained under the IPAM Manage - Action Menu. Open the Action Menu by left clicking on the Gear Icon, or right clicking anywhere on the block's row. The same Action Menu is also available to manage blocks via the IPAM Gadget.



The Action Menu contains the following options:


- **Edit:** Opens the blocks "Edit Attributes" page, used to add, change, or remove data associated with a block. Can also be opened by double clicking on a block's row.
- **Split:** Splits the selected single block into two equal smaller blocks, of the next smallest mask, e.g. a /24 will be split into two /25s. The Split option is not available for blocks that are already of the smallest available size (IPv4 /32s or IPv6 /128s), for blocks in "Holding", or for blocks that are already assigned and do not have subassignments enabled. If more than one level of splitting is needed, use "Templates - Auto Split" instead.
- **Merge:** The opposite of Split. Merge combines two blocks of equal size into the next largest mask, e. g., two /25s will be merged into one /24. Merge is only available for adjacent blocks of the same size that are "Available", in "Holding", or is subassignable.
- **Assign**: Assigns the block to a ProVision Resource, making it unavailable for other assignment actions and certain block actions (unless edited to be subassignable).
- **Unassign:** Unassigns the Resource from the current block, and moves the block into the Holding Tank. The block may then be eligible for certain actions such as direct assignment, merge, and split - but not for automated assignments until it is removed from Holding and regains the "Available" status. Unassigning a subassigned block will first place the block in "Holding", and then restore it to the parent assignment. (Tip: You can "Unassign" twice in a row to bypass "Holding", or select "Unassign, Skip Holding".)
- **Unassign, Skip Holding**: Unassigns the Resource from the current block, and bypasses the Holding Tank, restoring the block to "Available" status (or to the parent assignment if the block was subassigned).
- **RIR Integration:** Provides SWIP/RPSL functions for ARIN and RIPE blocks through simple reassigns, sending the updated block assignment information back to the coordinating RIR (ARIN or RIPE). See LIR Management and Use and RIR Integration: SWIP/RPSL.
- **IP Rules:** Create or Associate an IP Rule to the block to reserve portions of the block from assignment. See IPAM Rules.
- **Templates:** Provides options to 'Auto-Split' a standard block (that is available for standard "split" functionality) down to a certain mask and limit, or "Clean Up"(Auto-merge) a Parent Block to a certain mask level.
- **Logs:** Shows recent log event actions associated with that block.
- **Configure NAT:** Only displays for NAT'ed blocks. Configures the NAT'ed block to the selected router.
- **Email:** If a Contact is associated with the Resource assigned to the block, an email form with display to email the Contact with the template options provided in Admin Settings.

Split or Merge Blocks Manually

To split a block manually, click on the Action Menu (Gear icon), or right-click anywhere in the row for the available block you wish to modify.

In the menu that appears, select the "Split" function.

To aggregate blocks, select "Merge" from the same menu.




The Split option is not available for blocks that are already of the smallest available size (IPv4 /32s or IPv6 /128s), for blocks in "Holding", or for blocks that are already assigned and do not have subassignments enabled. If more than one level of splitting is needed, use "Templates - Auto Split" instead.

Merge is only available for adjacent blocks of the same size that are "Available", in "Holding", or is subassignable.


Split or Merge Blocks Using Templates

Templates for a block are available under the Action Menu (wrench icon or right-click) for that block. Templates are only usable from IPAM Manage.



There are two templates available: Cleanup (Only available for parent blocks) which auto-aggregates the block, and Auto-split.

Select the available template action, the mask, and the limit. When done, click the "Apply" button.




You can also use the "Templates" option from the Action Menu on the IPAM Manage screen for the specific block.

Edit IP Block Attributes

You may edit a block / multiple blocks from either IPAM Manage or the IPAM Gadget, with the same options available.

Select the "Edit" option from the Action Menu (or double click on the block row) for a given block to get the Edit Attributes menu.



To edit multiple blocks at a time, shift-click each block you wish to edit - they will highlight in blue. Once selected, right-click on any highlighted block to open the multi-edit attributes screen.



Once selected, right-click on any highlighted block to open the multi-edit attributes screen.

From here you can set a variety of attributes for a given block. These values are also customizable from the Admin screen - see IPAM Administration and IPAM Parameters to customize, enable, or disable the available parameters.


If a field that you know is supported in ProVision appears to be 'missing' from the IPAM Mange, IPAM Manage filters, or Edit Attributes screens, check the following:

Have an Admin verify that the field is set to "enabled" in Admin IPAM Admin Edit Columns. Any field disabled here will be hidden throughout ProVision, and some functions are dependent on certain fields being enabled - for example, filtering by Mask in IPAM Manage requires the "Host" field to be enabled.

In IPAM manage, verify that the column widths of each field are set wide enough to display the column header

Check for a scroll bar - when all attributes are enabled, many screens will require scrolling down or to the right in order to see all of the available data.

After editing the desired attributes for the block, simply hit "Save".



Edit Attributes Overview:

RIR: The RIR associated with the aggregate / block.

LIR: If LIRs are set up in IPAM Admin for the associated RIR, they will be selectable in this dropdown. See LIR Management and Use.

Domain: The VLAN Domain to associate with the block. To set up domains in ProVision, see VLAN - Working with Domains.

VLAN: VLAN information for the block, must have domain selected to view available VLANs.

Generic: This is a customizable text field that can be used to track information specific to your needs. It can be filtered in the IPAM Manage screen. The header, display, and enable/disable settings for this field are set under IPAM Configuration in the IPAM Administration section.

ASN: The ASN to associate with the block. ProVision auto-generates AS-Resources when an ASN is provided for the field in standard ASN format.

Region: Select the region from the drop down menu. Regions can be added and customized in the IPAM Admin section of ProVision - see IPAM Administration and IPAM Parameters.

Tags: Tags can be set under Edit Tags in the IPAM Administration section.

Notes: Freeform text field for additional information you wish to capture.

Resource: The resource assigned to the block.

NAT: The corresponding public or private block CIDR that is associated with the current block.

Metadata1 - Metadata 10: User-defined text fields, as set in IPAM Administration Edit Columns.

Allow Sub-assignments: When editing a block that has been assigned, toggling this setting to "On" allows for further subassignments, indicated by a blue arrow next to the assignment in the Manage screen. Note: Subassign status cannot be changed if a block has children.


Propagate Attributes to Children: Toggle this setting to "On" when editing a parent block to carry through attribute changes to all children of that block *for that edit*. This is not a persistent setting - it only applies to the specific edit you are in the process of making.

To view parent blocks, and which children would be affected, ensure that top level or all masks are selected in the Filter menu in the IPAM Manage screen. See Working with IP Blocks for more information.


Note: The VLAN of a child cannot be different from that of its parent, so for mutil-level situations (Parent -> Child -> Grandchild), VLAN should be updated at the top tier parent level.

IPAM Auto AS-Resource

ProVision automatically creates an AS resource for ASN's entered into IPAM Manage (formatted as "AS1234" or "1234").



An ASN in IPAM Manage will link to the created resource, which will display all IP Blocks in ProVision with that ASN value. SystemAS resources may not be edited, however they may be deleted by an admin if desired.



Assign IP Space


There are two areas where you can assign IP Space: in the IPAM Gadget for the particular Resource, or through IPAM Manage for manually assigning a block to a resource.

The IPAM Gadget allows for more detailed assignment options including Direct Assign, Smart Browse, and Smart Assign with advanced options, and is the primary tool for space assignment.

Assign Space from the IPAMv2 Gadget

The IPAM Gadget is accessed from a Resource Entry page, once enabled for the Section (to add Gadgets, see Customizing Sections and Add Gadgets to your Section).

For additional details on the IPAMv2 Gadget, see Gadgets.




You have three options for assigning IP space using the IPAM Gadget: Direct Assign, Smart Assign, and Smart Browse.

Direct Assign

Direct Assign is used when you know the exact CIDR that you wish to assign to the Resource. You can use "Simple" direct assign, for straightforward assignments of a CIDR to the Resource, or "Advanced", used in cases where duplicate blocks may exist and you need additional criteria to differentiate between them.

Simple Direct Assign:

Expand the "Direct Assign" module of the IPAMv2 Gadget by clicking the "Expand" arrow on the right side of the header.




Type the desired CIDR to assign in the CIDR input box, then click "Assign". A message will appear to confirm success, or provide details on an error.


Advanced Direct Assign:

In some cases, you make need the ability to further specify a block to direct assign - such as if you have duplicate 1918 blocks. The "Advanced Options" filters allow for further detail to be provided to ensure ProVision assigns the specific block that is intended.

Expand the "Advanced Options + " link to the right of the "Direct Assign" module header.



Then, add in the desired CIDR, and set your additional filter criteria, such as RIR, region, LIR, VLAN, and so forth. When done, hit "Assign".




Smart Assign / Smart Browse

Smart Assign and Smart Browse are used when you have criteria that you need to meet for the assignment, and any block meeting that criteria is acceptable for assignment.

With Smart Assign, you enter criteria such as IP Type, Size, RIR, Region, and Tag information, then ProVision's automation will automatically assign a block meeting that critieria, if any exist. Smart Browse uses the same criteria, but provides a browsable list of blocks meeting that criteria for you to select from.

Expand the "Smart Assign" module in the IPAMv2 by clicking the expansion arrow in the right side of the Smart Assign header.

For a basic assignment, enter at least the IP type, RIR, and block size.




IP Tag filters are optional. IP Tag filters exist in three modes:

Standard - checks to see if the selected tag is associated with the block

Strict: limits results to blocks with exactly the selected tag(s)

Exclude - blocks without the selected tag(s)


For Advanced Options, Click the "Advanced Options +" expansion link in the top right of the header. Additional filter criteria will be available to apply to both Smart Browse and Smart Assign.



Then click "Smart Browse" or "Smart Assign".

For Smart Assign, you will receive a message indicating a successful assignment, or information regarding an error. If no blocks are available meeting the criteria, the message will say so. In this case, try removing one or more of your filter criteria and try again.


For Smart Browse, a screen will pop up showing blocks meeting your criteria. Browse to the block you want to assign, and click either "Assign this block", or "Assign from this block"(splits a larger block down).



Successful assignments will be added to the "IP Blocks" list in the IPAMv2 Gadget, and are able to be managed in the IPAM Gadget, IPAMv2 Gadget, or IPAM Manage Screen.

Manually Assign Space from IPAM Manage


You can also assign blocks manually using the "Assign" function from the IPAM Manager screen (accessible from the IPAM Tab). Open the Action Menu for a block, then select "Assign".



Assignments may also be performed for multiple blocks at a time, by shift-clicking the desired blocks, and right-clicking on any highlighted row to open the multi-block menu (choose "Assign Selected Blocks") :



Then, search for / select the Resource to assign the block. A filter tool is provided to narrow the list to a particular Section type.



When the correct resource has been selected, click the "Assign" button. If needed, a new resource can be created by clicking the "New Resource" button.

After assigning, you can further edit the block attributes or subassign space.

'Reserving' IP Space

If you need to create a 'reserved' pool from which to assign blocks, you can achieve this by creating a "Reserved" Section. Create a Section called "Reserved", add the IPAM gadget to it, then create an Entry with that Section to be the address group. From there, use the IPAM gadget and the IPAM Manage page to assign and unassign IP space from that pool.

For more details, see the FAQ entry: "How do I 'reserve' IP Space?"


Sub Assigning IP Space

To allow sub assignments, just toggle the "Allow sub assignments" button to "On" under Edit block.


Once the allow sub assignments box is checked, the block may be further split and assigned to other resources.

Split blocks may also be re-claimed to the originally assigned resource and re-aggregated. When "allow sub assignments" is checked, the block is counted as allocated, but not assigned - various statistics in IPAM, on the dashboard, and reporting will reflect this.


Sub assignments can be useful for tracking IPs assigned to a customer with multiple subsidiaries, or locations.



If a block is subassignable, a blue arrow will display in the "Assigned To" field in IPAM Manage.



In the IPAM gadget, subassignable blocks display a blue arrow in the 'Address' field.




Unassign IP Space

When a block is assigned, you will have the option of unassigning the block from the resource and returning it to the Holding Tank.


To unassign the block, simply open on the Action Menu for the block in either IPAM manage or the IPAM Gadget, and select "Unassign".

You may also chose "Unassign, Skip Hold", which unassigns the block and immediately returns it to available, bypassing the holding tank.



After unassigning blocks / skipping holding, newly available blocks will be merged upon next page refresh. Blocks which had been subassigned will revet back to the parent resource.

To return IP space in the Holding Tank to the Available Pool, process the Holding Tank via the Admin screen under **IPAM Admin** (this will only process blocks that were present for the specified number of days).



For more information on the Holding Tank, see Holding Tank Management.


For a fast method of unassigning all blocks from a particular resource, you may also bulk-unassign IPs from the Resource List! See Working with Entries

Working with NAT Blocks

Track IP NAT Associations

Track NAT associations between public and private (1918) blocks via the IPAM "NAT" Field.

The "NAT" field accepts a single IPv4 CIDR to associate with the current block, and automatically updates the corresponding block with the NAT association.



Working with NAT'ed Blocks


Use caution when managing NAT'ed blocks or aggregates - major actions that change either block's assignment or size (assign, unassign, split, merge, autosplit/cleanup) removes the NAT association.

In this case, complete the necessary high-level block tasks, and then re-save the NAT CIDR association to either block.

Enable NAT

Enable the NAT field by navigating to IPAM Admin Edit IPAM Columns.

From there, ensure that the NAT column is checked (enabled), and customize the column location if desired. Be sure to click "Update" to save any changes.




Create NAT Association


Ensure that the two appropriate IP Aggregates (one public, one 1918 private space) containing the desired blocks to NAT have been added into ProVision. (See: Working with IP Aggregates)

After verifying the aggregates and blocks, you may add the NAT association:


Open IPAM Manage for either aggregate, then open "Edit Block" for the specific block you wish to NAT. (See:Working with IP Blocks)




In the Edit Block dialog, enter the IPv4 CIDR of the corresponding NAT block. When complete, click "Save".



Once the NAT field has been saved, the association will display in the NAT Column.




The corresponding block (here, the private 1918 space block) will automatically have the NAT associated applied.




Configure NAT to Router(s)

To push the NAT association to a router, go to the IPAM Manage Action Menu, and select "Configure NAT" for the NAT'ed block(s) (For information on adding a router to ProVision, see Peering Routers).

Open the Action Menu for the NAT'ed block(s) and select "Configure NAT".



Then, select the router. Add the custom configuration / interface information for the router and click "Configure".



NAT Rotate Dynamic IPs

NAT'ed block assignments may be automatically rotated to other available IPs via the "Rotate Dynamic IPs" scheduler task available in the Admin **Scheduler** tab.

"Rotate Dynamic IPs" reassigns single IPv4 NAT addresses (/32s) after 'x' days (since last config push) to an available address denoted by blocks associated with the Dynamic_Available tags.

Prior to using this task, two blocks (one public, one private) must be NAT'ed in IPAM, the NAT Config pushed to a router, and appropriate blocks tagged with "Dynamic_Base" and "Dynamic_Available".

Before you Begin

Before setting up NAT Dynamic IP Block Rotation, ensure the follow has been completed:


- The public/private IP blocks exist in ProVision (as /32s) and have been set up with NAT Metadata and matching IP Tags
- The NAT'ed blocks have been configured with a router
- The Aggregate(s)/IP's exist in ProVision with sufficient "Available" space to use for Rotating the NAT'ed block(s)
- IPAM Tags match between the NAT'ed blocks and intended available blocks

Add Dynamic Tags to Blocks

After NAT blocks and aggregates have been set up in ProVision with sufficient size, matching IPAM tags, and NAT metadata, you can identify which blocks to use for dynamic rotation by adding the "Dynamic_Base" and "Dynamic_Available" tags.

Go to IPAM Manage and:


- Add the IPAM tag "Dynamic_Base" to the /32 block(s) currently NAT'ed.
- Add the IPAM tag "Dynamic_Available to the aggregate or blocks which match the NAT'ed blocks, and are available for rotation use. If used on a block larger than the Dynamic_Base block, the available block will be automatically split.



Set up Scheduler Task

Go to Admin Scheduler, Add the scheduler task "IPAM - Rotate Dynamic IPs".

Enter a number for the days to wait (since last configure) until rotation.



Enter scheduled start / end dates, repeat settings, and click "Save" when complete.

The scheduled task will look for NAT'ed, /32 "Dynamic_Base" blocks that have last configuration times older than the provided day count, and rotate those IPs to "Dynamic_Available" blocks. Dynamic_Available blocks larger than than the Dynamic_Base block will be automatically split.

Additional Information

For additional information on working with the IPAM system in ProVision, see the following areas:

- Gadgets (IPAM and IPAMv2 Gadgets)
- Working with IP Rules
- IPAM Administration

Working with IP Rules

Working with IP Rules

- Working with IP Rules
  - IP Rules
    - Creating a new rule
      - IP Rule Positions
    - Apply an existing rule
    - Remove a rule from a block
- Additional Information

IP Rules


IP Rules allow users to exclude IP addresses from being assigned (via Smart Assign or Direct Assign) based on the address position in the block (i.e., first address, last address, nth from last).

IP Rules can be accessed from IPAM Manage or the IPAM Gadget, in the block's Action Menu (wrench icon). IPAM users may view rules applied to a block, apply an existing rule to a block, or create a new rule for a block. Only one rule may be applied per block, and rules applied to a parent block affect the child blocks below it in the tree.


Admin users may view all existing IPAM Rules, the blocks affected by each rule, and delete rules through the IPAM Admin - IP Rules page.

Creating a new rule


From the IPAM Manage screen or IPAM Gadget, click on the Action Menu (wrench icon) for the block you wish to apply a rule. Select "IP Rules".



The IP Rules screen will pop up. From here, you can view existing rules applied to the block (or the parent block), search for and apply an existing rule, or create a new IP Rule.



To create a new rule, leave the "Search Rule" input empty, and hit the "Continue" button.



The Manage Ruleset screen will appear, prompting you to enter a Ruleset name, and select positions to reserve.

Type in the desired name for the new rule, and one or multiple positions (denoted by integers separated by commas) into the box below the name.

When complete, click the "Save" button, or hit "Cancel" to exit without saving. The Rule preview screen will appear.

IP Rule Positions

Reserved addresses are set by their position in the block. Positions start at '1', for the first address in a block, and step up by one for each subsequent IP address. The last position in a block is '0', representing the last address, and steps down a negative integer for each position from last - so the last three addresses in a block would be represented by (0, -1, -2). When reserving multiple positions, the typed order of the positions does not matter.

Position examples:

(1) - Reserves the first IP

(0) - Reserves the last IP


(1,2,3) - Reserves the first three IPs

(0, -1, -2) - Reserves the last three IPs.

(1,2,3,0,-1,-2) - Reserves the first three and last three IPs

Review the list of excluded IP addresses affected by the rule, then click "Apply" to finalize the selection.

If desired, you can exit out of applying the rule by clicking "Discard", and closing the screen.




Once changes are applied, the rule will show the name, affected CIDR(s), affected IPs, and an option to remove the rule.




Apply an existing rule

From the IPAM Manage screen or IPAM Gadget, click on the Action Menu (wrench icon) for the block you wish to apply a rule. Select "IP Rules".




The IP Rules screen will pop up. From here, you can search for existing rules by typing a few letters of the Rule name in the search box, then selecting the desired rule.



Once selected, hit the "Continue" Button.

Review the list of excluded IP addresses affected by the rule, then click "Apply" to finalize the selection.




If desired, you can exit out of applying the rule by clicking "Discard", and closing the screen.

Once changes are applied, the rule will show the name, affected CIDR, affected IPs, and present with an option to remove the rule.



Remove a rule from a block

From the IPAM Manage screen or IPAM Gadget, click on the Action Menu (wrench icon) for the desired block. Select "IP Rules".



The details for the existing rule applied to the block will be shown. To remove the rule from the block, click the "Remove" button and confirm.

The rule will still be able to be re-applied and usable by other blocks, simply no longer applied to the current block.



Additional Information


For additional information on working with IP Blocks and IP Rules, including Admin-level tasks, see the following areas:

- IPAM Tab
- Working with IP Blocks
- IPAM Administration
  - IPAM Parameters
  - IPAM Rules (Admins)

VLAN

VLAN

To access the VLAN pages, go to the **IPAM** Tab, and then either select VLAN from the IPAM dropdown menu, or click the VLAN sub-tab button.



ProVision's VLAN Management is located under the **IPAM** Tab, and has three main VLAN sub-areas: **VLAN Home**, **VLAN Manage**, and **VLAN Advanced**.

The **VLAN Home** page shows an overview of domains and VLANs on the left sidebar, and IPAM Utilization data organized by each domain / VLAN pair. From here, users may add domains, VLANs, add/remove VLAN associations with blocks, perform domain / VLAN management tasks, and access additional VLAN areas - **VLAN Manage** and **VLAN Advanced**.

VLAN Manage lists all of the IP blocks currently associated with that VLAN, and allows you to perform all of the IP block actions available in IPAM Manage for those blocks. For information on working with individual blocks and using IPAM Manage functions inside VLAN Manage, please refer to Working with IP Blocks.

VLAN Advanced shows a global view of all domains and VLANs present in ProVision, and the associated metadata. VLAN advanced is the primary area from which to manage domains (edit / delete domain), and concisely view VLAN data side-by-side. It also provides access to manage VLANs, add domains, and add vlans to a domain.

VLAN Feature Overview:

- Supports custom domain ranges and exclusions, using ProVision's Numbering Authority
- Create domains and add VLANs directly from the VLAN Home page
- Associate domains with Routers
- Customizable VLAN Metadata Columns (IPAM Admin VLAN Columns)
- Action shortcut panels in VLAN Utilization and VLAN Manage - Utilization View, Quickview, Assign IP, and Edit VLAN
- Integrates administrative functions directly into the VLAN Tab.

- VLAN
  - VLAN Feature Overview:
- VLAN Manager Overview
  - VLAN Workflow:
    - 1) Create Domain(s)
    - 2) Add / Edit VLANs
    - 3) Add IP Blocks to VLANs
    - 4) Manage Domains and VLANs
- VLAN Home Page
  - VLAN Sidebar
  - VLAN Utilization Area
    - Open VLAN Manage
    - View VLAN Panels
    - Remove VLAN
    - VLAN Manage / VLAN Utilization Action Panels
      - Utilization
      - Quickview
      - Assign Blocks to VLAN
        - Direct Assign to VLAN
        - Smart Browse to VLAN
        - Assigning from Smart Browse
      - Edit VLAN
- VLAN Manage Page
- VLAN Advanced (Global View)
  - VLAN Advanced (Global View) Actions
  - Additional Information

VLAN Manager Overview

The VLAN Manager allows users to add domains and VLANs to their ProVision instance, and associate them with IP Blocks. Customizable VLAN columns - including up to ten user-defined metadata columns - allow you to rename column headers, set the display order, select which columns are visible, and display your own information fields.

Permissions and VLAN

The Permissions structure in VLAN includes the following items of note:

The following VLAN tasks requires Admin-level permissions:

- Adding new Numbering Authority ranges for VLAN use
- Editing IPAM / VLAN Columns
- Adding, editing, and removing domains
- Adding, editing, and removing VLANs

Non-Admin users may:

- View the VLAN Home page and utilization data, however, only resources that the user has view permissions for will display under the "Resources" and "Recent Assignments

VLAN Workflow:

1) Create Domain(s)

The workflow starts with creating a domain in the **IPAM** Tab VLAN section of ProVision, by clicking the "Add Domain" button and entering domain information.

VLAN domains may be created as pre-set Numbering Authority ranges, or defined manually. Two default Numbering Authority VLAN ranges are provided, one for a Cisco Standard domain, and another for a Cisco Extended domain. Admins may create new Numbering Authority ranges at any time to support other router types, range extents, or exclusions. Those ranges will then be available as options when adding a new domain from the VLAN area. If you select to create a new domain by defining a manual range, you may enter the range extents, any exclusions, and associate a specific router if desired.

2) Add / Edit VLANs

VLANs may be added to the domain at the time the domain is created (via the "Add VLANs" input area) or added to an existing domain later via the "Add VLANs" button. You can add one VLAN, multiple VLANs, a large range of VLANs, or a mixed selection at the same time.

Once a VLAN has been added to a domain in ProVision, the VLAN may be edited to add a VLAN name or metadata information, and have IP blocks associated with it.

3) Add IP Blocks to VLANs

Once a VLAN has been added to a domain in ProVision, IP blocks may be associated with ('assigned to') that VLAN. There are multiple methods to set the VLAN for a block:

- **Individual block edit** - Edit one or more blocks and set the domain and VLAN fields to the desired values. Direct edit may be performed from IPAM Manage, VLAN Manage, and the IPAM Gadget, by selecting Edit Block.
- **Direct Assign a block** - Open the Assign Blocks panel, expand Direct Assign, and type in the CIDR to assign to the VLAN. Advanced options are available to distinguish between duplicate blocks. The Assign Block panel is available from the VLAN's Utilization Box, and/or the VLAN Manage header bar.
- **Smart Browse for blocks** - Open the Assign Blocks panel, expand Browse Assign, and enter filter criteria to create a list of blocks meeting that criteria. Then, select one or blocks from the list to assign to the VLAN. The Assign Block panel is available from the VLAN's Utilization Box, and/or the VLAN Manage header bar.

After assigning a block to the VLAN by any method, that block will immediately display in VLAN Manage for that VLAN, in the VLAN's Quickview panel, and the VLAN Utilization display panel will be updated to include the new block.

4) Manage Domains and VLANs

Managing VLANs and blocks under the VLANs may include standard IPAM tasks, such as editing blocks, splitting / merging blocks, or allocating/ assigning / unassigning the blocks to a resource. All of these functions, and more, may be performed from either VLAN Manage or IPAM Manage.


Other tasks, such as editing VLAN names, metadata, or adding/removing VLANs from a domain are performed from the VLAN action panels on the VLAN Home page, or from VLAN Manage.

Editing domains - including renaming, adding metadata, and deleting - may be performed from VLAN Advanced.

VLAN Home Page


The **VLAN Home** page is accessible from the **IPAM** Tab. Navigate between IPAM, VLAN, and Logging by clicking on the sub-tab buttons at the top of the page.

- Navigate between IPAM, VLAN, and Logging by clicking on the sub-tab buttons at the top of the page
- Open VLAN Advanced (Global View), by clicking the Advanced button
- Add new domains or VLANs by clicking Add Domain or Add VLAN
- Domains and VLANs are listed in a searchable, filterable, paginated sidebar with access to additional navigation and common tasks
- Expand or collapse domains in the VLAN Utilization area, and view pages of VLANs
- Access common VLAN management tasks from the VLAN Utilization box - either from action panels or the gear menu




VLAN Sidebar

The VLAN Sidebar lists domains and the VLANs under those domains, and is similar to the IPAM aggregate sidebar. The VLAN sidebar provides options for searching and filtering domains and VLANs, as well as menu options for navigation shortcuts to perform basic actions.



Above: VLAN Sidebar - Domain Menu




Above: VLAN Sidebar - VLAN Menu

- The VLAN sidebar contains search, filters, and right-click menu options
  - Filter the VLAN sidebar to display either "Added" VLANs, "Active" VLANs that have blocks assigned, or "Named" VLANs with user-provided names
  - Search the VLAN sidebar for a particular domain, VLAN Number, or VLAN name by typing into the search/filter field "Filter VLANs"
  - Right click to open context menus for both domains and VLANs

- Domain Sidebar Actions
  - Click on a domain name to show/hide the VLANs contained under that domain
  - Click "manage" next to the domain name to open VLAN Advanced for that domain
  - Right click on a domain to open options to:
    - Edit Domain- Opens VLAN Advanced Edit Domain panel for that domain
    - Add VLAN - Opens the Add VLAN page for that domain
    - Remove Domain - Deletes the domain and all VLAN data under it

- VLAN Sidebar Actions
  - Click on a VLAN number/name to navigate to its location(QuickNav) in the VLAN Utilization area of the page
  - Click on "open" next to a VLAN to open VLAN Manage for that VLAN
  - Right click on a VLAN to open options to:
    - QuickView - QuickNavs to the VLAN's Utilization area listing, and opens the VLAN's Quickview panel
    - Assign Blocks to VLAN - QuickNavs to the VLAN's Utilization area listing, and opens the VLAN's Assign Blocks panel
    - Edit VLAN - QuickNavs to the VLAN's Utilization area listing, and opens the VLAN's Edit VLAN panel
    - Remove VLAN - deletes the VLAN, removing the VLAN assignment from any blocks assigned to it

VLAN Utilization Area




The VLAN Utilization area lists domains and the VLANs under those domains (both able to be expanded/collapsed), with each active VLAN (one that has assigned blocks) displaying the Utilization panel by default.

Inside the Utilization Box for each VLAN, you may do the following:


Open VLAN Manage

Open VLAN Manage for the VLAN by either clicking on the VLAN Name in the header, or clicking on the gear icon and selecting "Manage VLAN" from the menu.



View VLAN Panels


The four VLAN panels (Utilization, Quickview, Assign Block, Edit VLAN Metadata) may be open or closed by clicking on each respective icon in the header bar. Additionally, you may open any non-default panel by going to gear icon and selecting the action option from the menu. These panels are also available in VLAN Manage.



For detail on each panel, see the following section on this page: VLAN Manage / VLAN Utilization Action Panels

Remove VLAN

Remove (delete) the VLAN by clicking on the gear icon and selecting "Remove VLAN". This removes the VLAN from the domain, removes the VLAN association from any blocks assigned to that VLAN, and permanently deletes the VLAN's metadata. VLANs may also be deleted from the VLAN sidebar and VLAN Advanced areas.




VLAN Manage / VLAN Utilization Action Panels

These action panels are available from both the VLAN Home page Utilization Boxes and VLAN Manage, and may be opened or closed by clicking on the associated header bar icons. Each panel allows you to view data specific to that VLAN, or perform common management actions.

Utilization


The Utilization panel displays breakdowns for all blocks assigned to the VLAN by both status (available, allocated, assigned, holding) and by resource. Recently assigned blocks are noted under the "Recent Assignments" section, and links are provided to the Resource Entry page for each resource listed. To open or close the Utilization panel, click on the "Pie" icon in the grey header bar.



Quickview


The Quickview panel provides a condensed, filterable list of all blocks assigned to that VLAN, separated into three columns - IPv4 blocks, IPv6 blocks, and grouped by resource.

To open or close the Utilization panel, click on the "Eye" icon in the grey header bar.




While in the Quickview panel, you may easily search for a block by typing the all or part of the CIDR into the IPv4 or IPv6 Filter boxes - useful for verifying an assignment or quickly scanning ranges.

You may also remove a block from the VLAN with a single click of the "Remove" button.



Assign Blocks to VLAN


Blocks may be assigned to the VLAN from the Assign Blocks panel, opened or closed by clicking on the plus-sign icon. Two assignment options are available - Direct Assign to VLAN, if you know the specific block to assign, and Smart Browse to VLAN, where you can specify filter conditions and select one of more blocks meeting those conditions.



To open either option, click on the appropriate header bar to expand the module. Expand the area below for more details on Direct Assign to VLAN and Smart Browse to VLAN:

Direct Assign to VLAN

To Direct Assign a specific block to the VLAN, expand the "Direct Assign to VLAN" module, then enter the CIDR to assign into the "CIDR" box, and click "Add IP Block" .




If blocks exist with the same CIDR (such as in duplicate 1918 space), you may differentiate between the two by clicking on the "Advanced Options" link and providing additional filter criteria to use to assign a specific block.

Smart Browse to VLAN

Smart Browse to VLAN is used to search for a general list of blocks available to assign to the VLAN that meets certain criteria.

Expand the "Smart Browse" module by clicking on the header bar .

Then, enter your filter criteria. At minimum, block "Type", "Size", and "RIR" must be provided; "Region" and "Tags" are optional.



If further filtering is needed, you may click on "Advanced Options" to open the "LIR", "Custom Code" (here: as "GRT"), and assigned "Resource" fields to use.

Once you have entered your filter criteria, click on the "Smart Browse" Button to display your results.


Assigning from Smart Browse

The Smart Browse results list will display a list of blocks that a) meet your filter criteria, and b) do not already have a VLAN assigned.


You may assign individual blocks immediately ("Add IP Block"), or select multiple blocks and delay assignment until after your final selections are complete ("Assign Selected").

Immediate Assignment:

To assign an individual block immediately from the list to the VLAN, click "Add IP Block" for the desired block.



After clicking "Add IP Block", the block will immediately be assigned to the VLAN, and an "Assigned" status will display for the block in the Smart Browse list.




From here, you may assign additional blocks, clicking "Close" to exit when complete.

If the "Assigned" status displays for all blocks you intend to assign, then you may skip clicking "Assign Selected"- as nothing else remains to assign - and instead click "Close" exit.

Delayed Assignment / Selecting Multiple Blocks:

If you wish to assign multiple blocks to the VLAN at the same time, or mark a single block to assign later while continuing to browse the list, you may select a block to mark for later assignment and then assign all selected blocks at once.

To select a single block, left click on row for the block, taking care not to accidentally click on a blue link. Note that the row will have a yellow highlight indicating it is selected:




To select additional blocks, shift-click on each row you wish to mark for assignment. You may freely scroll through the results to review your selection.

When done, click Assign Selected. All highlighted blocks will be assigned to the VLAN at the same time, and the Smart Browse window will close.

Edit VLAN

The Edit VLAN panel allows you to view and edit the data associated with the VLAN (Note: not all VLAN fields may be editable).

To open or close the Edit VLAN panel, click on the "List" icon in the grey header bar.



Typically, editable VLAN fields include the VLAN Name and any enabled VLAN "Metadata 1-10" fields enabled in VLAN Columns. To change the information in these fields, click inside the relevant box, type your change, and then click "Save Changes". The information provided in these fields will also display in the "VLAN Advanced" Global View.

VLAN Manage Page

VLAN Manage lists all blocks associated with a VLAN, using an interface that matches IPAM Manage and provides the same block management functionality as in IPAM Manage.


In addition, you can access common VLAN management areas, such as Add Domain and Add VLAN, and manage the VLAN through four action panels - Utilization, Quickview, Assign Block, and Edit VLAN.

VLAN Manage has the same interface options as IPAM Manage:


- Sort the block list by clicking on column names
- Resize columns by dragging the vertical divider between column names to the left or right
- Edit column order, visibility, names, or add custom metadata columns from IPAM Admin VLAN Columns
- Double-click to open the Edit Block dialog for any block in the list
- Right-click on a block (or click on the gear icon) to open the IPAM Action Menu
- Shift-click to select multiple blocks, and then right-click for multi-block menu options
- Filter the block view by clicking on "filter >", then selecting filter criteria. When done, click Apply.
- Export the list to .csv
- View "Parent View", showing the parent blocks with an option to display the block's tree

VLAN Manage also has the same action panels as in the VLAN Home page - Utilization Boxes:

- Open VLAN Action panels from inside VLAN manage to review data or perform standard tasks, including:
    - VLAN Utilization Charts (Pie Icon)
    - Quickview (Eye Icon)
    - Assign Blocks to VLAN (Plus Sign)
    - Edit VLAN (List icon)




VLAN Advanced (Global View)




VLAN Advanced displays a list of all domains / vlans added to ProVision. Here, you can perform domain level management tasks, view data on added VLANs, including domain, VLAN Name, applied numbering domains, associated routers, and any enabled VLAN metacolumn data.

From this page, you may add domains or vlans, edit a domain (by clicking the "List" icon), and perform various actions from the VLAN Action Menu (right click on a VLAN entry).

VLAN Advanced (Global View) Actions

- Sort the list by clicking the column header(s)
- Filter the list by clicking on the "filter >" link on the rightmost side of the grey list header, then select the filter criteria and click Apply
  

- Search for a specific domain name, vlan name, vlan number, router, or metadata field value by typing the search term into the search box, then hit *enter* or click the Search icon.
- Export the list to .csv by clicking "export to CSV" in the list header
- Edit or remove a domain by clicking on the Edit Domain panel (list icon)
  

- Add domains or VLANs by clicking Add Domain or Add VLAN buttons at the top right of the page

Additionally, you may right click on any VLAN while in this view to open a VLAN action menu with the following options:



- Edit VLAN (opens the Edit VLAN panel for that VLAN)
- Edit domain (opens the Edit Domain panel for the VLAN's domain)
- Manage VLAN (links to the VLAN Manage page for the VLAN)
- Remove VLAN
- Remove domain


Additional Information

For detailed information on working with domains and VLANs, continue on to:

- Working with Domains
- Working with VLANs

Working with Domains

Working with Domains



This page provides detailed instructions on performing specific tasks in ProVision's VLAN Manager. Before reading this section, please ensure that you are familiar with navigating to the VLAN areas, including the VLAN Sidebar, VLAN Utilization area, VLAN Manage, and VLAN Advanced. For a broader overview of the VLAN system, its workflow, and basic navigation through the available VLAN pages, please refer to the VLAN page.

- Working with Domains
- Working with Domains
    - Viewing / Managing Domains
        - VLAN Sidebar
        - VLAN Utilization
        - VLAN Advanced (Global View)
    - Add Domain
        - Add a Domain - Numbering Authority Type
        - Add a Domain - Manually
    - Edit Domain
    - Remove Domain
- Additional Information


Working with Domains

Viewing / Managing Domains

You may view active domains from the VLAN Home Sidebar, the VLAN Home Utilization area, or from VLAN Advanced.

VLAN Sidebar

The VLAN sidebar lists the domains and VLANs that have been added to ProVision. Here, you can search for domains / VLANs by name, filter by Added/Active/Named status, and access common tasks.




VLAN Sidebar Domain Actions:

- Click on a domain name to show/hide the VLANs contained under that domain
- Click "manage" next to the domain name to open VLAN Advanced for that domain
- Right click on a domain to open options to:
    - Edit Domain - Opens VLAN Advanced Edit Domain panel for that Domain
    - Add VLAN - Opens the Add VLAN page for that domain
    - Remove Domain - Deletes the domain and all VLAN data under it

VLAN Utilization


The VLAN Utilization area displays all domains and VLANs added to ProVision in collapsable modules. Here, you may view all VLANs under a domain with their utilization data, and perform VLAN level managements tasks.




VLAN Advanced (Global View)

VLAN Advanced displays a sortable and filterable list of all the domains / VLANs added to ProVision and the associated metadata.

Open VLAN Advanced by clicking the Advanced button.



From this page, you may add domains or VLANs, edit a domain (by clicking the "List" icon), export the list, and perform various actions from the VLAN Action Menu (right click on a VLAN entry).



VLAN Advanced (Global View) Actions:

- Sort the list by clicking the column header(s)
- Filter the list by clicking on the "filter >" link, then select the filter criteria and click Apply
- Search for a specific domain name, VLAN name, VLAN number, router, or metadata field value by typing the search term into the search box, then hitting *enter* or click the Search icon.
- Export the list to .csv by clicking "export to CSV" in the list header
- Edit or remove a domain by clicking on the Edit Domain panel (list icon)
- Add domains or VLANs by clicking the Add Domain or Add VLAN buttons


Additionally, you may right-click on any VLAN while in this view to open a VLAN action menu with the following options:



- Edit VLAN (opens the Edit VLAN panel for that VLAN)
- Edit domain (opens the Edit Domain panel for the VLAN's domain)
- Manage VLAN (links to the VLAN Manage page for the VLAN)
- Remove VLAN
- Remove domain

Add Domain

Add a new domain by clicking the Add Domain button at the top of the VLAN Home page.



This opens the "Add Domain" page. Here, you can choose to add a domain by using a pre-set Numbering Authority range, or by creating a new range manually.

Numbering Authority Ranges

Two default Numbering Authority VLAN ranges are provided, one for a Cisco Standard domain, and another for a Cisco Extended Domain. These default ranges use Cisco Standard and Cisco Extended range extents and exclusions:


Name	Reuse values	Type	Actions
Cisco Router VLAN Numbering Domain Template	Yes	Multi-range **Ranges**: 1-1001 **Excluded Ranges**: 1002-1005	Get Next Value · View Assigned Values · Delete
Cisco Router VLAN Extended Numbering Domain Template	Yes	Multi-range **Ranges**: 1-4094 **Excluded Ranges**: 1,3968-4047,4094	Get Next Value · View Assigned Values · Delete

Admins may create new pre-set Numbering Authority ranges at any time to support other router types, range extents, or exclusions. Those ranges will then be available as options when adding a new domain from the VLAN area.

Add a Domain - Numbering Authority Type

In the Add Domain section, under Domain Information, enter a new domain name and select a router (optional). For routers to be selectable in this list, they must already be set up in ProVision.


Under Domain Range, select to use an existing Numbering Authority range for your domain. If desired, you may choose to add VLANs to the domain at the same time, by specifying the VLAN or VLAN range(s) - any exclusions will automatically be skipped.



When done, click Add Domain. The new domain will be added to the VLAN Sidebar, along with any added VLANs.

Add a Domain - Manually


To add a new manual domain range, enter the domain name and router selection (optional), and select Manual for the Domain range Type. Once Manual has been selected, fields will display to enter the range extents (such as 1-1000), and range exclusions (here, 1, 5-7). If desired, you may choose to add VLANs to the domain at the same time, by specifying the VLAN or VLAN range(s) - any exclusions will automatically be skipped.




When done, click Add Domain. The new domain will be added to the VLAN Sidebar, along with any added VLANs. In addition, the manually created range will become a new Numbering Authority range, and able to be used as a template for a future domain.

Edit Domain

From the VLAN sidebar, right-click on the domain to edit and select Edit Domain. This opens the VLAN Advanced Edit Domain panel for that domain.



You may also access the Edit Domain panel directly from **VLAN Advanced** clicking on Edit Domain (List icon) and selecting the desired domain.




Here, you can edit the domain name, the associated router, view its range and range exclusions, and add VLANs to the domain. Enter your desired change(s), then click Save Changes.


Remove Domain

Deleting a domain may be done from either the VLAN Sidebar or from the VLAN Advanced Edit Domain panel.

To delete a domain from the sidebar, right click on the domain name and select Remove Domain.



To delete the domain from the Edit Domain panel, open VLAN Advanced for the Domain, then click Delete Domain.



When deleting a domain, both the domain and all VLANs under it will be deleted. Any IP blocks associated with the deleted domain will have its Domain and VLAN association removed.

Additional Information

For information on working with VLANs, continue on to:


- Working with VLANs

For a higher level overview of ProVision's VLAN Manager, see:

- VLAN

Working with the VLAN Manager

Working with VLANs



This page provides detailed instructions on performing specific tasks in ProVision's VLAN Manager. Before reading this section, please ensure that you are familiar with navigating to the VLAN areas, including the VLAN Sidebar, VLAN Utilization area, VLAN Manage, and VLAN Advanced. For a broader overview of the VLAN system, its workflow, and basic navigation through the available VLAN pages, please refer to the VLAN page. For domain level tasks, see Working with Domains.


- Working with VLANs
- Working with VLANs
    - Add VLANs to a Domain
    - Remove VLANs
    - Edit VLAN (Edit VLAN Panel)
    - Add Blocks to VLANs
        - Using the "Assign Blocks" Panel
            - Assign Blocks to VLAN
                - Direct Assign to VLAN
                - Smart Browse to VLAN
                - Assigning from Smart Browse
        - Add / Update VLAN to Blocks from IPAM Manage or VLAN Manage:
        - Add / Update VLAN to Blocks from IPAM Gadget:
    - Remove Blocks from a VLAN
        - Quickview
    - Working with VLAN Metadata
        - Enable / Disable VLAN Metadata Fields
        - View / Edit Metadata Field Information
- Additional Information

Working with VLANs


Add VLANs to a Domain

After creating domains, VLANs need to be added for that domain out of the pool of available VLANs.

From the VLAN Home page, click Add VLAN.



Select the domain, and then enter the individual or range of VLANs to add. Optionally, you may enter VLAN metadata field values, if metadata fields are enabled.




When done, click Add VLAN.


Remove VLANs

Removing VLANs may be performed from multiple areas:


- On the VLAN Home page sidebar, by right clicking on the VLAN and selecting Remove VLAN from the menu



- From the VLAN Utilization Box for the VLAN, by clicking the gear icon and selecting Remove VLAN




- From VLAN Advanced, by right clicking on the desired VLAN in the list, and selecting Remove VLAN



Deleting a VLAN permanently removes the VLAN from the domain, and removes the VLAN association from any blocks assigned to that VLAN, and permanently deletes the VLAN's metadata.


Edit VLAN (Edit VLAN Panel)

You can edit a VLAN by clicking on the VLAN in the VLAN List sidebar, then selecting Edit VLAN.



This opens the Edit VLAN panel for the selected VLAN. You may also click on the "List" icon in the VLAN Utilization box or in VLAN Manage to open the Edit VLAN panel.

The Edit VLAN panel allows you to view and edit the data associated with the VLAN (Note: not all VLAN fields may be editable).



Typically, editable VLAN fields include the VLAN Name and any enabled VLAN metadata fields enabled in VLAN Columns. To change the information in these fields, click inside the relevant box, type your change, and then click Save Changes. The information provided in these fields will also display in the VLAN Advanced Global View.

You cannot change the domain of the VLAN, but you may add a descriptive name or edit VLAN Metadata (if enabled).


After making your changes, click Save Changes. The named VLAN will now show both VLAN number and name when viewing domain / VLAN lists or when working with blocks.

Add Blocks to VLANs

After VLANs have been enabled for domains, you can associate those VLANs with IP blocks.

Using the "Assign Blocks" Panel

While on the VLAN Home Page, expand the desired domain in the sidebar and right click on a VLAN. Then select Assign Blocks to VLAN.




This navigates to the VLAN's Utilization Box, and opens the Assign Blocks panel. You may also access the panel directly from the Utilization Box or VLAN Manage by clicking on the plus-sign icon.

From the Assign Blocks panel, you can choose to Direct Assign a block to the VLAN, or use filter criteria to user Smart Browse to assign blocks.

Assign Blocks to VLAN

Blocks may be assigned to the VLAN from the Assign Blocks panel, opened or closed by clicking on the plus-sign icon. Two assignment options are available: Direct Assign to VLAN, if you know the specific block to assign, and Smart Browse to VLAN, where you can specify filter conditions and select one of more blocks meeting those conditions.




To open either option, click on the appropriate header bar to expand the module.

Expand the area below for more details on Direct Assign to VLAN and Smart Browse to VLAN:

Direct Assign to VLAN

To Direct Assign a specific block to the VLAN, expand the Direct Assign to VLAN module, then enter the CIDR to assign into the CIDR" box, and click Add IP Block .




If blocks exist with the same CIDR (such as in duplicate 1918 space), you may differentiate between the two by clicking on Advanced Options, and providing additional filter criteria to use to assign a specific block.

Smart Browse to VLAN

Smart Browse to VLAN is used to search for a general list of blocks available to assign to the VLAN that meets certain criteria.

Expand the Smart Browse module by clicking on the header bar .

Then, enter your filter criteria. At minimum, block type, size, and RIR must be provided; region and tags are optional.



If further filtering is needed, click Advanced Options to open the LIR, Custom Code (here: as "GRT"), and assigned resource fields to use.

Once you have entered your filter criteria, click Smart Browse to display your results.


Assigning from Smart Browse

The Smart Browse results list will display a list of blocks that a) meet your filter criteria, and b) do not already have a VLAN assigned.


You may assign individual blocks immediately (Add IP Block), or select multiple blocks and delay assignment until after your final selections are complete (Assign Selected).

Immediate Assignment:

To assign an individual block immediately from the list to the VLAN, click Add IP Block for the desired block.



After clicking Add IP Block, the block will immediately be assigned to the VLAN, and an "Assigned" status will display for the block in the Smart Browse list.




From here, you may assign additional blocks. Click Close to exit when complete.

If the "Assigned" status displays for all blocks you intend to assign, then you may skip clicking Assign Selected - as nothing else remains to assign - and instead click Close to exit.

Delayed Assignment / Selecting Multiple Blocks:

If you wish to assign multiple blocks to the VLAN at the same time, or mark a single block to assign later while continuing to browse the list, you may select a block to mark for later assignment and then assign all selected blocks at once.

To select a single block, left click on row for the block (taking care not to accidentally click on a blue link). Note that the row will have a yellow highlight indicating it is selected:



To select additional blocks, shift-click on each row you wish to mark for assignment. You may freely scroll through the results to review your selection.

When done, click Assign Selected. All highlighted blocks will be assigned to the VLAN at the same time, and the Smart Browse window will close.

Add / Update VLAN to Blocks from IPAM Manage or VLAN Manage:

When editing a block in either IP Manage (**IPAM** Tab -> Action Menu (wrench) -> Manage), or VLAN Manage (IPAM Tab - VLAN -> Action Menu (wrench)) , you can select an existing domain and VLAN to associate to the block.


VLAN Manage:

From the VLAN Manage page, click on the Action Menu (gear icon) for the desired block, the select Edit. You may also double-click on the block to open the same screen.


In the Edit Attributes dialog for the block, change the domain to the desired item, then select the VLAN. Click Save when done.

IPAM Manage:

From the IPAM Manage page, right click on the Action Menu (gear icon) for the desired block, then select Edit"




To select multiple blocks to edit, hold down the shift key and click on the blocks you wish to edit - the selected blocks will be highlighted. Right-click anywhere in the blue highlighted area, and select Edit Selected Blocks.



The Edit Block dialog will pop up for the selected block(s). Edit the domain by clicking in or typing in the domain search box, and select the desired domain.

Then, select the VLAN for the blocks from the enabled VLAN list. When done, click Save.




VLANs and Child Blocks

NOTE: Child blocks whose Parent blocks already have an assigned domain / VLAN, may not have domains and VLANs changed to be different than the Parent Block's values. If you attempt to save domain / VLAN changes to a child block under this situation, an error will occur.


i.e., Parent and Child IP Blocks must have matching domain / VLAN values.

Add / Update VLAN to Blocks from IPAM Gadget:

You may also add / edit domain /VLAN information when editing a block in the IPAM Gadget. From the IP block's Action Menu (gear icon), select Edit.



Then, in the Edit Attributes dialog, search for or type the desired domain, select VLAN information, and click Save.




Remove Blocks from a VLAN

Quickview


The Quickview panel provides a condensed, filterable list of all blocks assigned to that VLAN, separated into three columns - IPv4 blocks, IPv6 blocks, and grouped by resource.

To open or close the Utilization panel, click on the "Eye" icon in the grey header bar.




While in the Quickview panel, you may easily search for a block by typing the all or part of the CIDR into the IPv4 or IPv6 Filter boxes - useful for verifying an assignment or quickly scanning ranges.

You may also remove a block from the VLAN with a single click of the Remove button.



Working with VLAN Metadata




Customizable metadata fields are available to hold VLAN-specific information such as Location, Client, Firewall, Gateway, and more.

These fields can be enabled and disabled in **IPAM Admin** Edit VLAN Columns, and viewed / edited under Edit VLAN in the **VLAN** Tab and in VLAN Manage.

Enable / Disable VLAN Metadata Fields

VLAN metadata fields can be enabled and disabled under the IPAM Admin VLAN Columns area of ProVision.




Here, you may edit the order of columns, rename columns, and enable/disable column visibility.

Any columns that are disabled will hide the column from VLAN Manage, as well as hide the applicable field from any VLAN filters or Edit VLAN actions.

View / Edit Metadata Field Information

VLAN metadata may be viewed and edited from VLAN Home, VLAN Manage, and VLAN Advanced.

While in the IPAM Tab -> **VLAN Home** page, expand the desired domain from the left sidebar and right click on a VLAN. Then open the Edit VLAN panel.



The Edit VLAN panel may also be opened from VLAN Manage (click on the List icon), or from VLAN Advanced (right-click on the desired VLAN and select Edit VLAN).

Additional Information

For information on working with domains, see:

- Working with Domains


For a higher level overview of ProVision's VLAN Manager, see:

- VLAN

Peering v2

Peering

The **Peering** tab displays allows you to add and manage exchanges, routers, sessions, and peers. Admin users may view and manage recent emails for a company peering email address, and associate email communications with ProVision peers.



ProVision's **Peering** tab has five subtabs to manange various peering functions: **IXs** (Exchanges), **Routers**, **Sessions**, **Peers**, and **Emails**.

The **IXs** tab shows the exchange list. From here, you can edit exchange settings and view, manage, and mark peer status and communications via the exchange details page.

The **Routers** tab shows the list of routers in ProVision. From here, you can add new routers or manage existing routers.

The **Sessions** tab lists the current sessions in ProVision. You may also add new sessions, or click on a session name to show session details, from which you may configure and manage each session.

On the **Peers** tab, you can view and manage session peers.

In the **Email** tab (Global Admins only), recent email communications to and from a company peering email account may be managed.

- Peering
- Peering Overview
- Set up ProVision Peering
  - Add ASN(s) to ProVision
  - Add PeeringDB Credentials
  - Additional Options for Local Installations
- Peering Workflow
  - Peering Workflow Steps
    - 1) Add Router(s)
    - 2) Add Peer Groups
      - From Peering "Router Details" Page:
      - From the Peer Group Gadget:
    - 3) Add Session(s)
    - 4) Configure Sessions
      - Configure Sessions Individually by Exchange / Session:
      - Configure Sessions by Peers:
    - 5) Manage Communications
      - New Peer:
      - Outgoing Peer Request:
      - Incoming Peer Request:
    - 6) Repeat for new Routers, Sessions, and Peers.
- Additional Information

Peering Overview

In ProVision's **Peering** tab, you can add multiple exchanges, routers, sessions, view peer details, as well as send and receive peering requests. ProVision directly interfaces with PeeringDB's API to update exchange and peering data, to ensure up to date information.

This requires Peering users to have a PeeringDB account, and for the account credentials to be set in ProVision.

Peering Setup - Local Installations

If you are using a locally hosted instance of ProVision, verify that you have followed the instructions on the Local Installations: Peering Setup page to set up Peering for your instance.

Set up ProVision Peering

Two components need to be set up before you can begin to do common peering tasks in ProVision - set at least one ASN, and set PeeringDB account credentials.


Add ASN(s) to ProVision

Add at least one ASN to ProVision from either the **Admin Admin Preferences Peering** page, or via the **Peering** Tab -> Exchange Settings.

- Click one of the options below for details:

  From the **Admin Preferences** page, go to Peering -> **Peering Settings**.


  Next to "ASN", enter the ASN(s) you want to track in ProVision.



  For multiple ASNs, separate each ASN with a comma (e.g. "1234, 5678").

  When done, click "Save Changes" to save your changes.

  From the **Peering** Tab, go to the **IX's** subtab and then click "Settings".



  Peering Settings will display.

  Under the "Config" section, you'll see a field to add an ASN - fill in the desired ASN(s), and click "Add".


Add PeeringDB Credentials

Both Cloud customers and local installations may set the PeeringDB credentials in the ProVision **Admin Admin Preferences -> Peering** page, or via the **Peering** Tab -> Exchange Settings.

- Click one of the options below for details:


From the **Admin Preferences** page, go to Peering -> **Peering Settings**.

The current PeeringDB Account status will display next to "Peering DB Account".



To set or change the account, Enter the PeeringDB account username and password, then hit "Test" - the connection will be tested. If successful, you can then save the credentials. When you are done, click "Save Changes".


From the **Peering** Tab, go to the **IX's** subtab and then click "Settings".



Peering Settings will display.


Under the "PeeringDB Account" section, you will see account status instructions to set or change the Peering DB Account.

Click on the "Peering Admin Settings" link to go to the **PeeringDB API Connection** page to test and set the account.



This opens the **PeeringDB API Connection** page.

Enter the PeeringDB account username and password, then hit "Test" - the connection will be tested. If successful, you can then save the credentials.



Additional Options for Local Installations

Local Installations have an additional option of hard-coding the credentials in ProVision's globals.php file.

Additional Peering constants may be added into globals.php to change the PeeringDB URL between the main and beta site (some users may find the beta site to have faster response times), and to adjust the PeeringDB cache TTL.


For real-time updates, TTL may be set to 0. However, some users may experience severe lag with a TTL = 0; we recommend using a 10 to 15 minute or greater TTL if this occurs.


For details on adding / editing these peering constants, see Local Installations: Peering Setup.

Peering Workflow

After the initial Peering setup is complete (Adding ASNs and a Peering DB account), you can begin to work with the rest of the Peering tabs, including routers, peer groups, sessions, managing peers, and communications.

PEERING WORKFLOW





Peering Workflow Steps

Below is an outline of the steps needed for a basic workflow process.

- Peering
- Peering Overview
- Set up ProVision Peering
  - Add ASN(s) to ProVision
  - Add PeeringDB Credentials
  - Additional Options for Local Installations
- Peering Workflow
  - Peering Workflow Steps
    - 1) Add Router(s)
    - 2) Add Peer Groups
      - From Peering "Router Details" Page:
      - From the Peer Group Gadget:
    - 3) Add Session(s)
    - 4) Configure Sessions
      - Configure Sessions Individually by Exchange / Session:
      - Configure Sessions by Peers:
    - 5) Manage Communications
      - New Peer:
      - Outgoing Peer Request:
      - Incoming Peer Request:
    - 6) Repeat for new Routers, Sessions, and Peers.
- Additional Information

1) Add Router(s)

Adding a router is the fundamental base and first step of working with peering in ProVision. Routers may be added through the "Add Router" button in the **Peering** Tab.

For a detailed breakdown of this task, see Peering Routers.


2) Add Peer Groups

Associating the router with a peer group is necessary to link the router to a particular exchange. You may add the Peer Group information either in the "Router Details" page in Peering, or in the Peer Group Gadget prior to adding sessions.

From Peering "Router Details" Page:

Go to **Peering** Tab Routers. Click on the desired router to view the **Router Details** page. (See Peering Routers)

Here, you may add and delete and Peer Groups associated with the router - select the Exchange, Add the Peer Group Name, select the IP type, and click "Add Group".




From the Peer Group Gadget:

If you need to add a Peer Group to an existing router, you may use the Peer Group gadget.

The Peer Group Gadget allows you to add peer groups for IPv4 and IPv6 for a selected exchange from a router's Resource Entry page.

To do this, simply select the exchange, type in a Peer Group name in the text box, select IPv4 or IPv6, the click "Add Group".



Peer Groups added from this gadget will be then be available to select in the "Add Session" dialog box in the **Peering** tab.

3) Add Session(s)

After Routers and Peer Groups have been set up, the next step is Adding Sessions to ProVision.

You may add a new session through the "Add Session" button in the **Peering** tab, or you may Import Peering Sessions from an existing router.

Importing sessions requires Admin level permissions, and is accessed through the **Data Import** Tab in the Admin section of ProVision.

4) Configure Sessions

Once a session has been added, you will see it in the session list. For a newly added session, the status will show as "Not Configured". There are a few options to configure sessions:

Configure Sessions Individually by Exchange / Session:

You may configure the session through 1 click config or the Config Manager, accessed by clicking session and opening the Session Details page. 1 click config uses the default config settings, while the Config Manager allows you to manually create one time use unique settings.

Configure Sessions by Peers:

From the **Peer Details** Page, you can choose to create or configure multiple sessions.

With this option, you can view and configure all sessions for that Peer from one menu (as opposed to the Sessions list configure option, which configures individual sessions by Exchange).

Clicking on "Configure Multiple Sessions" button opens a page showing the available exchanges with routers and options to change the router, peer group, and Peer type.

Select the checkmarks for the desired sessions to configure. As a shortcut, you may also check the "Select all exchanges" option to select all sessions under all exchanges, or, check "Select all networks" next to the exchange header to select all sessions in that exchange. From there, deselect items as needed.

When your selections have been made, click "Configure Now" to immediately configure all selected sessions, or you may select "Schedule" to automatically create sessions and schedule a configuration to occur in one hour (by default). The scheduled configuration may be edited through the **Scheduler** Tab.

5) Manage Communications

Once a session has been added with a peer, you will see the peer listed Peer List under the **Peers** tab.

You'll also be able to manage communications from Exchange Communications.

You will see the list of Peers, their ASNs, Name, Request Status, Notes (log), and the Action Menu (wrench icon).

From here, you may send peer requests, mark peer status, and view notes on previous actions. The available options and flow depends on the Peer Status and whether a request is Outgoing or Incoming.

New Peer:

For an existing peer that was just added, you can mark the peer as:

a) Mark Existing Peer, or,

b) Mark Not Qualified

You may also choose to send an outgoing peer request.

Outgoing Peer Request:

To send out a peer request, select "Send Request" from the Action Menu (wrench icon) . This sends an initial peering request email to the peering coordinator for that peer. The email template pre-populates data based on peeringdb data (To address, Subject line and Peering exchange information). You have the chance to edit the email prior to sending. If Peering Emails are set up in ProVision with the same email address, a copy of the request will be saved to the Sent box.

Once a Request has been sent out, it can proceed two ways:

a) The request is accepted and Peering is established (becomes current peer)

b) The request is not accepted / responded to, and the "Resend Request" option becomes available, allowing you to repeat the request.

Incoming Peer Request:

If a request is received, you have a few options from which you may mark the peer from the Action Menu:

a) If you accept the request, you may "Mark Approved" and Peering is established (becomes current peer).

b) You may "Mark Rejected", in which case a peer status is marked rejected.

c) "Reset Status" is available at various points in the communications process, if you want to reset the peer back to the beginning state and re-establish a different status condition. This reopens the initial options from which you may select a different peer mark.

d) "Resend Request" may be available to resend a request

If Peering Emails are set up in ProVision, and the message was sent to the account as set there, the incoming request will be recieved to the ProVision inbox.

6) Repeat for new Routers, Sessions, and Peers.


To add additional Routers, Sessions, and Peers repeat steps 1, 2, or 3, and manage your newly added sessions and peer communications similarly with steps 4 and 5.

Additional Information

- Peering Exchanges
- Peering Routers
- Peering Sessions
- Managing Peers
- Peering Emails
- Peering Templates

Peering Exchanges

Working with Peering Exchanges




From this tab, you can access exchange settings to set ASN / Peering DB info, view the current exchange list and peer status, and view details for each exchange.

- Working with Peering Exchanges
- IXs Overview
  - Exchange Settings
    - ASNs
    - PeeringDB Account
  - Exchange Details
    - Exchange Details Tab:
    - Exchange Sessions Tab:
    - Communications Tab:
      - Menu Actions
  - Additional Information


IXs Overview

The Exchanges subtab features the list of exchanges currently set in ProVision, with IP type, city, peers, and active session counts.




Exchange Settings


Clicking the "Settings" Button opens the Exchange Settings page.



Here, you can add or remove ASNs, add or edit PeeringDB account settings:



ASNs




- Add an ASN by typing a valid ASN into the Config - ASN box, and then click "Add".
- Delete an ASN by clicking the red "Delete" icon for the row under Source Networks.

PeeringDB Account

If a valid PeeringDB account is already set, a message will display confirming the valid account.




If no account is set, or the current account is invalid, follow the link to the **Peering Admin Settings** page to test and add a PeeringDB account.



Enter the PeeringDB credentials and click "Test". If the account is valid, an option will appear to add it to ProVision.

Exchange Details

Clicking on an exchange in the exchange list will bring up an exchange details page, where Exchange Details, Session Details, and Exchange Communications may be viewed and managed.




The "Settings" button takes you back to the **Exchange Settings** page.

The left side of the page displays a filterable list of all exchanges currently added to ProVision - to narrow the list down, simply type the first few letters of the exchange name into the "Filter" box, and click on your desired exchange to view its details.

Exchange Details Tab:

The exchange details tab provides general information about the exchange, obtained from PeeringDB.


It includes organization information, contact information, LAN, and a list of Peers at the exchange point.



Clicking on the name of any peer in the under the "Peers at this Exchange Point" list will open the **Peer Details** page.

Exchange Sessions Tab:

The sessions tab lists ProVision sessions associated with the exchange, detailing the ASN, IP, Router, Peer Group, and session state.




From here, you may:

- Add sessions to this exchange by clicking "Add Session".
- Click on the Peer Name to go to the **Peer Details** page for that Peer.
- Click on the Router Name to view **Router Details**.
- Manage the session by clicking on the "GoTo" Arrow button at the right side of the list to open the **Session Details**.

Communications Tab:

The Communications tab is where you can manage communications actions and mark status of peers.



Filter the Communications list by typing the peer name into the filter box at the top left.

Available communication and status options are available in the Action Menu - available actions are dependent on current status, so not all actions are available at all times.

Menu Actions

Mark Approved: Marks the peer as approved. Available after receiving a request response.

Mark Existing Peer: Marks a peer as an existing one and removes the email request options.

Mark Not Qualified Peer: Marks a peer as "not qualified" and removes the email request options.

Mark Rejected: Marks the peer as rejected. Available after receiving a request response.

Reset Status: Resets the status of the peer, opening up the options to mark peer as existing, not qualified, or to send email requests.

Resend Request: Resends the peering request.

Send Request: Sends an initial peering request email to the peering coordinator. The email template pre-populates data based on peeringdb data (To address, Subject line and Peering exchange information). You have the chance to edit the email prior to sending.


Actions taken from this menu will be logged and display in the "Notes" field of the Communications list. If a Peering Email account is set up in ProVision and used to send Peering Requests from this menu, the emails will be accessible in ProVision in the Peering Emails Tab Sent Folder. See Peering Emails for additional information.

Additional Information

- Peering
- Peering Routers
- Peering Sessions
- Managing Peers
- Peering Emails

Peering Routers

Peering Routers



The **Routers** subtab is where routers may be added and managed. Routers are divided into two lists - those with Peer Groups, and those without.


From here, you can filter the router list, click on any router name to go to the **Router Details** page, or "Add Router" to add a new router.

- Peering Routers
- Working with Peering Routers
  - Add a Router
    - Router Details Page
      - Edit Router
      - Edit Peer Groups
      - Router Sessions
  - Additional Information


Working with Peering Routers

Add a Router

Add a new router by clicking the "Add Router" button, which will direct to a page to input the router details.




Enter in router details: Name, Make, Model, Hostname, IP address(es), and credentials. When done, click "Create".



The Router will be added to the Router list, and can be managed from the router details page.

Router Details Page

Clicking on a router entry in the router list will open the router details page.




From here, routers may be added as well, or you can use the filterable list in the left sidebar to select a router to view.

The router details area gives the basic router information.


Edit Router

A Router's Make, Model, IP address, Hostname, Username, and Password may be edited from the Peering Router Details page.

To edit a router field, click the "Edit" icon (pencil), and input the desired change.




When complete, click the "Save" icon. You may cancel the edit by clicking the "Cancel" icon to the left of "Save".



Router information may also be edited from the Router's Resource Entry page and /or Field Gadget. By default, not all router fields may be visible or editable - this is to prevent editing critical router identification elements while sessions may exist for those routers.

Edit Peer Groups

You may also add and delete and Peer Groups associated with the router - select the Exchange, Add the Peer Group Name, select the IP type, and click "Add Group".




To delete Peer Groups, click "Delete" for the peer group to remove. Peer Groups may also be edited via the Peer Group gadget.

Note: Adding / Deleting Peer Groups only affects ProVision, it does not add or remove from from the router itself.

Router Sessions

View all ProVision sessions associated with a router by going to that router's detail page and scrolling down to the "Router Sessions" section. Clicking on any session will open up the Session Details for that session.




Delete all sessions in ProVision for the router by clicking "Delete All Sessions" under Router Sessions.

Additional Information

- Peering
- Peering Exchanges
- Peering Sessions
- Managing Peers
- Peering Emails

Peering Sessions

Peering Sessions



The **Sessions** subtab is where current sessions may be added, managed, and updated.


The **Session List** shows all current sessions in ProVision, and their current information and session state. Update the session states for all sessions by clicking the "Update Session States" button, or manage individual sessions by clicking on the row for the desired session.

- Peering Sessions
- Working with Peering Sessions
  - Add a Session
    - Add Session Information
    - Select or Add Destination
  - Manage a Session (The Session Details Page)
    - Session Details Actions
  - Additional Information

Working with Peering Sessions

Add a Session


Add a new session by clicking the "Add Session" button.




Add Session Information

Click "Add Session" from the Peering Sessions sub-tab.

In the Create New Session Form, type the session information, selecting the appropriate exchange type for the planned Peer. If using a Local Peer, "No Exchange" is an available option.






Select or Add Destination

Under the **Destination** section, select or type in information for a peer. You may add Peer information from any of the three available methods:

- Use PeeringDB Lookup to select a PeeringDB Peer (the destination fields will be automatically populated).
- Look up an existing Local Peer under "Local Peer Lookup" by selecting the peer name and IP address (the destination fields will be automatically populated).
- Manually add a new Local or Custom Peer, by directly typing the Peer Name, ASN, and IP in the Destination fields.




After selecting the Peer Destination information, you have the option of configuring the router immediately after saving. When done, click the "Create" button.

If "Configure router after saving" is selected, the router will configure immediately after session creation and automatically load the session page when done.

While Configuring, you may either wait for the configure to complete and automatically load the session details page, or immediately view the details by clicking "View Session" while the configure continues in the background.


The new Session will be added to the Session List.



Manage a Session (The Session Details Page)

Clicking on a Session entry from any Session List, or clicking "View Session" after creating a session, will open the Session details page.

From here, new session may be created by clicking "Add Sessions" if desired, but it is primarily for session management. You may also click on the Router link to view the Router Details page, or the Peer Name for Peer Details.



The Session may be manually configured via "Config Manager", or automatically via "Configure".

"Email" opens an Email communications form, with data automatically generated from PeeringDB. Other available tasks include Admin Up/Down, Edit, and Delete session.

Session Details Actions

Edit: Edit session information such as Type, Prefixes, Notes or MD5.

Configure: 1-click configure which uses default router configuration, username, and password settings.

Config Manager: The Config Manager allows for custom configuration commands and user-level username/ password to be entered prior to pushing the config. This is a one time use configuration.

Email: Brings up the NOC (Network Operations Center), Policy, Technical, or other preset email template. The email template pre-populates data based on peeringdb data (To address, Subject line and Peering exchange information). You have the chance to edit the email prior to sending.

Admin Up: Ups a bgp session without removing it or adding it to the config.

Admin Down: Downs a bgp session without removing it or adding it to the config. On Cisco, Admin Down moves the session to Idle (Admin) state, on Juniper it deactivates the session.


Delete: Sessions of type "Peer" are removed from the router when deleted in ProVision. Other sessions will only be removed from the sessions list in ProVision.

Additional Information

- Peering
- Peering Exchanges
- Peering Routers
- Managing Peers
- Peering Emails

Managing Peers

Peers



The **Peers** subtab lists existing peers in ProVision. Here, you can add new peers and view peer details. ProVision supports Peer lookup from PeeringDB, as well as creation of "Local Peers". Local or custom Peers that are 'private' or not registered with PeeringDB may also be used for session creation.

- Peers
- Working with Peers
  - Peer List
  - Add Peers
    - Add PeeringDB Peer (Import Lookup)
    - Add Peer via Configure / Configure Multiple Sessions
    - Add a Local Peer
    - Add Peer via Session
      - Add Session Information
      - Select or Add Destination
  - Peer Details Page
  - Additional Information


Working with Peers

Peer List

The Peer list shows peers currently in ProVision, their ASN, associated exchange, and whether session exist.

Filter the peer list by typing all or part of a peer name into the "Filter" text box in the right side of the list header, and the list will narrow down to matching Peers.

You may also sort by any field by clicking on the column name in the header. To view a Peer, you may click anywhere in the row for the peer, or click the "View" button.



Organizations will show as Peers in this list if:

- There is an existing session in Provision with the organization set as the destination - applies to both "Add Session" and "Add Peer" Configure Sessions
- The organization is marked "Existing Peer" in Exchange communications

Manually added Local Peers will show in the Local Peer list, below the standard Peer List.

Add Peers

Adding a Peer can be done via many methods in ProVision, depending on whether the peer is from PeeringDB, Local, and what the peer/session status is.

In general, Peers will added from either:

- PeeringDB through "Import Peer", session creation, or exchange communications
- Local / Custom creation through "Add Peer" or session creation


The following approaches will result in a Peer being added into ProVision:

- Create a session for a peer, selecting the Peer from PeeringDB options available under the Session tab "Add Session" form.
- Create a session for a local or custom peer, selecting an existing local peer or manually entering a custom destination in the Session tab "Add Session" form.
- Manually create a Local Peer, from "Add Peer".
- Import/search for a Peer from PeeringDB, then add the peer by configuring multiple sessions.
- Add a peer without creating sessions by marking the peer as "existing" under ExchangeCommunications. The Peer will show in the Peer List, but no sessions will exist for the peer until they are created in ProVision.


Add PeeringDB Peer (Import Lookup)

Peers may be added via finding a peer from PeeringDB to import,

You can search for Peers by clicking "Import Peer" on the **Peers** or **Peer Details** pages.




The "Import Peer from PeeringDB" search module will open. Enter all or part of the peer name, then click "Search". The results will show in a list below.




From the results list, click "View" - this will open the **Peer Details** page for the Peer, where you can view the peer's information, available exchanges, existing sessions, or add the peer via configuring multiple sessions.

Add Peer via Configure / Configure Multiple Sessions

From the **Peer Details page**, click "Configure Multiple Sessions".



Clicking the configure multiple buttons opens a page where you may select and set up multiple sessions for that peer.




Select the desired exchanges, router, peer group, and type, and then choose to either "Configure Now" or Schedule the config to run later via the **Scheduler** Tab.

Configuring sessions here will create new sessions, and add the peer used to the Peer List.


Add a Local Peer

Add a new local peer by going to the **Peering** Tab Peers subtab, and clicking "Add Peer".




In the "Add Local Peer" form, enter the Peer details including Name, ASN, IPv4 or IPv6 Address, Route-Set, select an Exchange Option, and add notes if desired.

When finished, click "Create".



The Peer will be added to the "Local Peers" list, and be available to select while creating a session.




Add Peer via Session


New Peers are added when creating a session with that Peer. While creating a new Session, you may select a PeeringDB Peer, an existing Local Peer, or create a new custom Peer.

Add Session Information


Click "Add Session" from the Peering Sessions sub-tab.

In the Create New Session Form, type the session information, selecting the appropriate exchange type for the planned Peer. If using a Local Peer, "No Exchange" is an available option.






Select or Add Destination




Under the **Destination** section, select or type in information for a peer. You may add Peer information from any of the three available methods:

- Use PeeringDB Lookup to select a PeeringDB Peer (the destination fields will be automatically populated).
- Look up an existing Local Peer under "Local Peer Lookup" by selecting the peer name and IP address (the destination fields will be automatically populated).
- Manually add a new Local or Custom Peer, by directly typing the Peer Name, ASN, and IP in the Destination fields.




When complete, click "Create".

The new Session will be added to the Session List.



Peer Details Page

Clicking on a peer in the list will open the Peer Details page.



From here, you can view details for the existing peer, including available exchanges and what routers you have available on that exchange. Additional, the peer may be added by configuring new sessions via Configure Multiple Sessions.

Existing sessions for the Peer may be viewed, managed and deleted under "Sessions".




To edit, manage, or delete a single session, click on the session listing to open the Session detail page. All sessions under the Peer may be deleted by clicking "Delete All Sessions".

Additional Information

- Peering
- Peering Exchanges
- Peering Routers
- Peering Sessions
- Peering Emails

Peering Emails

Peering Emails



The Peering **Email** subtab is an Admin-only page from which a company peering account can view and manage recent emails.

The Peering Emails page is only accessible to Administrative users in the primary "Global Admins" User Group.


Ensure that Peering Administrators using ProVision's Peering Emails area are included as members of that group for full access.

- Peering Emails
- Communications Page Overview
- Messages
  - Process a Message
  - Reply to a Message
  - Delete a Message
- Communications Settings
  - Add an Account
  - Edit or Delete an Existing Account
  - Additional Information

Communications Page Overview

The Peering **Emails** subtab associates a single company peering email account (such as peering@company.com) with your ProVision instance, creating a 'shortcut' email system to keep on top of the most recent peering requests while in ProVision.

Here, you can load, view, and reply to emails received at that address, view requests sent from ProVision's Exchange Communications page, and process emails to associate the message with ProVision Peers.



Four folders are available to view, displayed on the left sidebar:

Inbox: Displays emails received at that address, barring any messages deleted from ProVision

Processed: Emails which have been associated ("Processed") with a ProVision Peer.


Sent: Emails sent from the set address from ProVision, either via "Reply" or from sending a peering request under "Exchange Details" Communications

Trash: Emails removed from ProVision folders - 'deleting' ProVision emails only affects what messages are loaded into the ProVision instance - your original messages remain intact on your original email server. So feel free to only keep only the emails relevant to peeringTo-Do list!

Messages are automatically checked for after 10 minutes, and refreshed when loading the page. When staying on the page for a period of time, you can manually check for and load new messages by clicking the "Refresh" button under the folder list.

Messages

From any message folder, click on the message to view message details.




Three actions can be performed on messages: Process, Reply, or Delete.

Process a Message

"Processing" a message in ProVision associates that message with a Peer, and moves it into the "Processed" message box. To do so, click "Process" on the message.




The "Process" email module open with a search field to select the Peer. Type in all or part of the peer name, then click "Go", or click "Cancel" if you want to skip the Processing and go back to the message.




The search results for the peer will display under the search box.

Click on the Peer result that you wish to assign from the search results, then review the peer details to verify it is the correct Peer. When done, click "Assign".




The Peer's name will be tagged to the bottom of the email message. If you need to change the associated Peer, you can click the tagged Peer to repeat the process and select a new Peer.




When done, the email will be move to the "processed" message box, to denote the message is associated with a peer.

Reply to a Message

To reply to a message, from the message details click the "Reply" button at the bottom of the message.




Type in your desired message reply, and click "Send".



The message reply will be sent to the original sender, and a copy will be saved in the "Sent" folder.


Delete a Message

To delete a message from ProVision, click the "Delete" button at the bottom of the message. The message will be removed from the Provision inbox and placed in the "Trash" folder, but remains intact on the original email server.




Communications Settings

The "Settings" page allows you to set, edit, or delete the email account associated with ProVision. From the Email Tab, click "Settings".




If no account is active, the option to add a new email account will be available.

Otherwise, if an account has already been set, details for the account will be visible as well as options to test or edit the account.




Add an Account

If an account is not currently set, status information and and the option to add a new email account will be available. Click "Add Account".




On the "Add Account" page, enter the account display name, email username/address, server, email password, and change the security and port settings if needed.




"From Address" is a field used if the email reply address is different than the username@serverhostname - in most cases, it will not be necessary.

When done, you can verify the information is correct by clicking "Test Connection" - if the account is valid and a connection succeeds, you will see a "Online" response.




When done, click "Save", and the account information will display under "Settings" and the email folder will be available.

Edit or Delete an Existing Account




An existing account may have the connection tested by clicking "Test Connection" in Account Information. Additional Actions, such as editing account details or deleting the account from ProVision may be done by clicking "Edit" for the Account.

Click "Edit" to open the



Edit the account settings as needed, test the connection if desired, and click "Update".

Delete the account by clicking "Delete" - a confirmation message will appear confirming that the account will be deleted and all emails removed from the ProVision infterface - don't worry, the original emails stay fully intact on the email server.




Additional Information

- Peering
- Peering Exchanges
- Peering Routers
- Peering Sessions
- Managing Peers

Peering Templates

Peering Templates



Peering Templates allow users to create their own reusable session configuration files. When the default ProVision session configuration template doesn't do everything required for your specific use case, you can create your own template that does. Revisions to Peering Templates are tracked, and a template may be reverted to a previous version at any time.


Peering Templates are accessible to Admin users from the **Admin Preferences Peering** page, under Peering Settings.

- Peering Templates
  - Viewing Templates
  - Add a Template
  - Delete a Template
  - Edit a Template
    - Syntax
  - Preview Template
  - Template Revisions
  - Additional Information:


Viewing Templates

View the Template List by navigating to the **Admin Preferences** page, in the Admin area of ProVision. From there, click the "Peering" sub-tab button top view Peering Settings.


Next to "Templates", click "Manage Custom Templates".



The Template List will open, displaying all existing Peering Templates.




Click on any template to open Template Details, where you can edit, delete, or preview the template.




To return to the Template List, click the "Template List" button at the top right of the page.

Add a Template


From any page in the Peering Templates area, click the "Add Template" button on the right side of the page header to start a new template.



In the Add Template form, enter a name for the template and the template body. When complete, click "Add".




The "Template Details" view displays for the newly created template, here you can update, preview, or delete the template.



The "Revision History" section is available at the bottom of the page in this view, but will only display data if previous updates have been made to the template.


Delete a Template

From the Template Details view for the desired template, click the "Delete Button". Note: The deletion is immediate and permanent - use with care!



Edit a Template

From the Template Details view, edit the template by clicking inside the template body and typing the desired changes - if you need a reminder as to syntax or variables, click the help icon (Question Mark button) at top right to open the template editing guide.



Click "Update" when done.

Syntax

Templates use the Mustache format https://mustache.github.io/mustache.5.html

Template Syntax

Basic Variables

Values on the session object are inserted when referenced by double curly braces {{ }}

```
The router name is {{router_name}}
```

When given a session object with `{router_name:'TheName'}` the line becomes

```
The router name is TheName
```

If / If-Not statements

To only include a block (or part of a line) if a variable exists, enclose that part of the template starting with `{{#variable}}` and ending with `{{/variable}}`

```
{{#color}}The color is {{color}}.{{/color}}
{{#city}}
The city is {{city}}.
{{/city}}
```

When given `{color:'blue'}` the output will be

```
The color is blue.
```

To only include a block if a variable does *not* exist, start with `{{^variable}}` and end with `{{/variable}}`


Common Variables

- source_asn
- vrf
- type_ipv6
- peer_ipaddr
- peer_asn


- peer_group
- peer_name
- ttl
- prfx_max
- prfx_alert_threshold

Preview Template

While editing or viewing a template, you may preview the template's output against a specific session by clicking the "Preview" button. A "Preview Template" section appears.




Select an existing Router/Session from the dropdown list to use to generate the preview. Once selected, the template output will display directly underneath the selected session.



Template Revisions

The Revision History area will display on the Template Details page after an update has been made to the template, with each update displaying as a separate revision item.



Click "View" under the "Actions" columns for a revision to see the template contents at that revision snapshot.



To restore the template back to that revision number, click the "Restore" button for the revision preview.

Additional Information:

For additional information on Peering, see the following areas:

- Peering Exchanges
- Peering Routers
- Peering Sessions
- Managing Peers
- Peering Emails
- Peering Templates

Reporting


Reporting

The ProVision **Reporting** tab provides reports for IPAM, Peering, DNS, Users, Resources, and DHCP.

Reports and User Permissions

Admin level users ("Admin" permissions on TLR) may view all data in all reports, as well as perform report actions such as creating, editing, copying, and deleting reports.

Non-admin / Limited permission users may view reporting, but will only be shown the data/modules for which they have permissions to view. Non-Admin users may not create, edit, copy, or delete reports.



To view reports for ProVision modules (IPAM, Peering, DNS, Users, and Resources), click on the applicable sub-tab button at the top of the page, or select it from the **Reporting** Tab dropdown menu.

- Reporting
  - Reporting Overview
  - Report Permissions, Ownership, and Coordination
  - Available Reports
    - IPAM Utilization Reports
    - IPAM Runout Report
    - Peering Reports
    - DNS Reports
    - User Reports
    - Resource Reports
    - DHCP Server Report
    - DHCP Pools Report
  - Additional Information

Reporting Overview

Reporting v2, accessible to users from the **Reporting** tab, contains reports for five ProVision modules - IPAM, Peering, DNS, Users, Resources, and DHCP.

Default reports are available for each module sub-tab, and users may create their own customized report from the existing templates. Once created, reports may be exported on-demand, or have exports scheduled to be sent to a user at regular intervals.

Reporting Features

- Thirteen default system reports for IPAM, Peering, DNS, Users, Resources, and DHCP
- Customizable user-created reports
- IPAM Utilization, Runout, and Peering Status charts
- Export reports to .csv and/or pdf
- Schedule reports to be emailed at selected intervals
- Safely view existing reports and apply filters without overwriting saved report settings, or chose to permanently save changes.
- Copy existing reports to use as editable templates
- IPAM reports include integration with IPAM metacolumn data and IPAM Column settings

Report Permissions, Ownership, and Coordination

In Reporting v2, any admin user may view, manage, and edit any individual report. Default reports will display with "System" as the owner, and may be viewed, edited, and copied, but are not deletable.

User-created reports will display with the creator's username in the owner field, and are able viewed, deleted, edited and copied. Report "ownership", as a concept, only extends to displaying the creator of the report - there are no report actions that are "locked" to any specific user or access restrictions in place per report, outside of the normal viewing permissions.

Although it is possible to edit and save both default reports and reports created by other users, it is recommended to either coordinate the changes with the report's owner, or create a new copy of the existing report to use for modifications.

Report Editing Etiquette

You may view existing reports at any time, including freely adjusting and applying filters on a temporary basis (by selecting filters clicking Apply) as well as immediately export those results, without overwriting the existing report filter settings.

However, *saving* new filter settings to an existing report (by applying the new filters -> Gear Icon Save) **permanently** overwrites the report's default filter settings.

Before saving changes to an existing report, it is recommended to perform some basic due diligence:


- If you are not the report's owner, confirm the report edit with the report owner prior to saving
- If there is a user listed as receiving scheduled exports of that report under Schedule Report Settings, verify that the report change will not negatively impact the planned use of the scheduled report(s).

Best Practices:

- Use the report Copy function whenever you are unsure of ownership or scheduled report repercussions
- If you only need a one-time export, temporarily adjust the filters on a default or existing report, and use the "Export to .csv/pdf" button
- Use the report's description field to communicate details, status, and restrictions to other users (such as "Do not edit - Report used for monthly status comparisons by Bob")

Available Reports


IPAM Utilization Reports



IPAM Utilization reports display IPv4/IPv4 utilization charts organized by RIR and SWIP status, and provide a listing of ProVision blocks meeting the applied filter criteria. The report view includes the block data for all applied IPAM Columns, in the order set under IPAM Admin IPAM Columns . IPAM Reports may be exported to .csv (limit: 100,000 records; no chart provided) or PDF (limit: 1000 records; chart included). Default reports include:

- Default Utilization: IPAM utilization report for all aggregates
- Default Utilization - 30 days: IPAM utilization report for all aggregates assigned in the past 30 days

IPAM Runout Report




The IPAM Runout Report displays IPv4/IPv6/1918 assigned/allocation pie charts, and lists available/assigned host statistics and projected runout for the selected block type(s) and region(s).

The Default report include:

- Default Runout - All Types: IPAM Runout report for all block types and regions.


Peering Reports




Two new peering report types are available - Peering Health and Peering Status. Peering Health reports display the sessions existing in ProVision, with the associated fields of Router Name, Peer Name, IP, Session Type, Session State, Peer Group, and session Created Date. Peering Status reports are set per-exchange, and display pie charts for Peer Status/Qualification Status, as well as a data table of the Peer Name, Request Status, Peer Status, Qualification Status, Message Count, and Last Message Time.

All Peering Reports may be exported to .csv (limit: 100,000 records; no chart provided). Default reports include:

- Default Peering Health Report: Displays the peering session state for all currently existing sessions in ProVision
- Default Peering Status: Displays Peer, Request, and Qualified status for the default (first available) exchange in ProVision




DNS Reports



DNS Zone reports provide a list of zones existing in ProVision, along with the fields of Zone ID, Name, Last Modified Date, Forward/Reverse Type, and Record Count information. DNS Zone Reports may be exported to .csv (limit: 100,000 records). Default reports include:

- Default DNS Zones: All DNS zones in ProVision
- Default DNS Zones - 30 days: All DNS zones in ProVision modified within the past 30 days


User Reports



Users reports provide a listing of ProVision log events associated with user actions. Provided fields include the Timestamp, User, IP, Log Level, and the Action, and the report may be filtered to include one or more users / user groups, as well as basic data filters. User Reports may be exported to .csv (limit: 100,000 records). Default reports include:

- Default User Activity - 30 days: All ProVision user activity within the past 30 days
- Default User Activity - Year to date: All ProVision user activity for the current calendar year (ISO Standard/Gregorian calendar)

Resource Reports




Resource reports provide a list of all (non-DNS) ProVision resources, and field data from the Contact, Billing, Tech Info, and Resource Field Gadget(s) associated with the resource. The report may be filtered to include one or more Sections or Categories, as well filtered by resource name. Resource Reports may be exported to .csv (limit: 100,000 records). Default reports include:

- Customer List Report: ProVision resources which are of the "Resource Holder" Section and "Customer" Category.=
- Default Resource Report: All ProVision resource entries - matching resources listed in the Resource Tab -> Entries page list, and all applicable resource fields
    - TIP: Due to the large scope of the ProVision resource system and its fields, we strongly recommend using the Default Resource Report as starting template from which to further define more specific resource reports. Simply "Copy" the Default Resource Report, apply your desired Section/Category filter combination(s), and click the Gear Icon Save to create a more manageable data set.

Note: The number of entries able to be exported limited to 100,000 rows for .csvs, and 1000 rows for IPAM pdfs. If more rows are needed, the ProVision API may be used to retrieve larger datasets.

DHCP Server Report



The DHCP Servers Report displays existing DHCP servers in ProVision, associated statistics, and last updated time. The DHCP Servers report can be filtered by Name, Domain, or by last modified date.


Default reports include:

- Default DHCP Server Report: All ProVision DHCP Servers, with no additional filters applied.

DHCP Pools Report

IM - 3705 b: Added the DHC Pools Report type to the Reporting Tab.





The DHCP Pools Report displays existing DHCP Pools in ProVision, type, ranges, IP/MAC, associated groups, and last updated time.

The DHCP Pools Report can be filtered by DHCP Server(s), name, type, or by last modified date.

Default reports include:

- Default DHCP Pool Report: ProVision DHCP Pools for the default server(s), both subnet and hosts, with no additional filters applied.

Additional Information


For more information on performing specific tasks in reporting, see:

- Working with Reports

Working with Reports

Working with Reports

The ProVision **Reporting** tab provides reports for IPAM, Peering, DNS, Users, Resources, and DHCP.



To view reports for ProVision modules (IPAM, Peering, DNS, Users, and Resources), click on the applicable sub-tab button at the top of the page, or select it from the **Reporting** Tab dropdown menu.

Default reports are available for each module sub-tab, and users may create their own customized report based from the existing templates.

- Working with Reports
  - Working with Reports - Overview
  - The Saved Reports List
  - Report View
    - Report View Filters
  - View Report
  - Create New Report
    - Step 1 - Add Report
    - Step 2 - Customize Filters
    - Step 3 - Save Report
  - Edit Report
  - Copy Report
  - Export / Schedule Report
    - Export Current View
    - Schedule Report
  - Delete Report
- Additional Information

Working with Reports - Overview


Reporting v2, accessible to admin users from the **Reporting** tab, contains reports for six ProVision modules - IPAM, Peering, DNS, Users, Resources, and DHCP. Default reports are available for each module sub-tab, and users may create their own customized report from the existing templates. Once created, reports may be exported on-demand, or have exports scheduled to be sent to a user at regular intervals.

Admin users may perform the following reporting actions:

- View reports
- Create new reports
- Edit reports
- Copy reports
- Delete user-created reports
- Export and/or schedule export of a report

For each ProVision module, these actions are accessed in two general areas - the Saved Reports list, which shows the reports existing for each report type, and Report View, which displays the data for the selected report, and where report edits, exports, and filter updates may be performed.

The Saved Reports List



The Saved Reports List shows the reports created for each module, including both default and user-created reports. Each report row displays the report name, description (optional), last modified date, last loaded date, the owner (creator), and provides action button options.

Available actions under the Saved Reports area:

- Expand and Collapse the Saved Reports List by clicking the caret ( ) in the blue bar
- Sort the list (toggle ascending / descending) for any field with an up/down arrow ( )by clicking on the column name
- Open a report by clicking on the report name link, or click View under Actions (opens Report View)
- Edit a report's name, description, or scheduled report settings by clicking Edit, under Actions. (opens Report View Actions)
- Duplicate a report, or use an existing report as a template, by clicking Copy

Report View

Report View displays the data for the selected report, using the filter options saved to the report. It it divided into three general areas - the header, graph display (if applicable), and data display.

The header area contains the following items:

- Report view header (blue bar) which contains:
  - Report view menu (gear icon) with options to Edit, Copy, Save, Export to CSV, and Export to PDF (if available)
  - Close Report View ('X' icon)
- Selected report header (grey bar), which contains:
  - The name of the currently open report
  - Report export options (export to CSV or PDF)


- Actions menu - click to toggle the edit report options open or closed)
- Filter flyout - click to toggle open or closed, and apply different filters

The graph area displays for selected reports:

- IPAM Utilizations report - displays IPv4/IPv6 Swipped and Non-Swipped by RIR bar charts, with host utilization tables
- Peering Status - displays Peer Status and Qualification Status pie charts


The data display area shows 50 rows per page of report information, including

- Report-specific field information, for fields that contain data
- Metadata columns, if enabled and containing data (for IPAM report types)




Report View Filters

While in Report View, you may view or edit the applied filters by clicking Filter > in the report header.




The filter flyout opens from the right side of the Report View, showing all fields available to filter by for that report type.

Select or enter values for the filter criteria that you wish to apply to the report, and click Apply when finished. Close the filter flyout by clicking Filter < .



Applying updated report filters allows you to adjust the report output on a temporary basis - just until the page is reloaded. This is useful for quick look-ups, or to export a partial data set.

If you wish to permanently save the updated filters to the report, saving the current state as the report's default, click the Report View menu (gear icon), and select Save.



Saving the report overwrites the previous filter set with the current filter set. This affects all users who view the report, as well as future exports and scheduled exports.

If you only need a temporary view of certain report filters, Apply the filter changes without saving the report - the report will be reset to its saved configuration the next time it is loaded.

View Report

Open a report view by clicking on the report name in the Saved Reports list, or click View under report Actions.




The Report View for the selected report will open, where you can edit, filter, and export the report.


Create New Report

Step 1 - Add Report

To create a new report, click Add Report from any reports module page. This opens the Add Report page.



Under Add New Report, select the desired report type to add, enter the name of the report, and a description. Click Save when complete.




The Saved Reports list page for that report type will automatically load, showing the newly created report.


New reports are created without any filters applied, so the next step is to open the report and apply filter customizations and report settings to the report.

Step 2 - Customize Filters


Open the report from the Saved Reports list by clicking either the report name, or the View button under Actions.




Report View opens for the report, showing the report with no filters applied. To view or edit the report filters, click filter> to open the filter flyout.



The filter flyout opens from the right side of the Report View, showing all fields available to filter by for that report type.




Some report types, such as IPAM Utilization, have additional secondary filters available for items such as metadata fields. To open or close these additional filters, click More Filters.



Select or enter values for the filter criteria that you wish to apply to the report.

For our example, "Some IPAM Report", we have selected IPv4 blocks assigned in the last 60 days, that have the "Customer" tag.




When done, click Apply, and then close the flyout by clicking Filter <. This applies the filter conditions to the report in the current view, but does not permanently save them.

Step 3 - Save Report

After applying filters to the report, review the data to ensure the filter conditions result in the desired output.

To permanently save the applied filters and settings, click the Report View menu (gear icon), and select Save. This ensures that subsequent report views and exports use the same filter set.




Edit Report


Edit a report's name, description, or scheduled report settings by clicking Edit in the Saved Reports list. The report actions panel will open.



You may also open the report actions panel from Report View. Click the gear icon, then select Edit, or open the actions + panel.



From the report actions panel, edit the report name and description under Report Settings, then click Save.




Also available under this panel is Scheduled Report Settings. Scheduling a report generates an export of the report at the set time interval, and emails the export file to the entered recipient.


To add or edit Scheduled Report Settings, enter the email address that the report should be sent to, select an interval frequency for how often the report export should be emailed, and (if available) select the report export type to send. When done, click Save. To close the actions panel, click Actions .

Copy Report

Copy a report by clicking Copy in the Saved Reports list for the report.



You may also copy a report from its Report View. Click the gear icon, then select Copy.



Export / Schedule Report

Reports may be exported immediately, as they are currently displayed in the Report View, or exported on a regular basic automatically (Schedule Report). Note: Schedule Report requires ProVision's **Scheduler** Tab to be running.


Export Size Limitations

Report exports have a maximum size limit of 100,000 rows for .csvs, and 1000 rows for pdfs. If your report data exceeds that amount, it is recommended to adjust the report filters to further reduce results, and/or split the report into multiple, smaller reports. The ProVision API may also be used to retrieve larger datasets.

If your company regularly requires exports larger than these limits, please contact support@6connect.com for assistance.

Export Current View

Export a report by opening Report View for the desired report, and then clicking Export as CSV or Export as PDF (if available). Export options are also available from the gear menu.




The applicable file type will download via your browser.

Schedule Report

Scheduling a report generates an export of the report at the set time interval, and emails the export file to the entered recipient. Open the Scheduled Report Settings by clicking Edit for the report in the Saved Reports list, or by clicking the Actions panel in Report View.

To add Scheduled Report Settings, enter the email address that the report should be sent to, select an interval frequency for how often the report export should be emailed, and (if available) select the report export type to send. When done, click Save. To close the actions panel, click Actions .




Scheduled Reports

Once Schedule Report Settings have been saved for a report, ProVision automatically generates a Scheduler Tab task entry for that report with the entered information. Once created, the email address, report interval, and time to send the report may be also manually edited from the Scheduler Tab, and the history and log event for the scheduled report task may be reviewed.

Delete Report

Delete a user-created report by clicking Delete in the Saved Reports list. Default reports (listed with "System" as the owner) may not be deleted.



Before deleting reports (especially any created by a different user), verify that both the report and its scheduled exports are no longer needed.

Additional Information

For additional information on Reporting, see the following areas:

- Reporting
- Reporting v1
- Scheduler Tab (for editing or reviewing Scheduled Reports)

User Preferences


User Preferences

The User Preferences page allows the logged in user to reset their password as well as adjust per-user settings.

- User Preferences
  - Accessing User Preferences
  - Editing Preferences


Accessing User Preferences

To access the User Preferences page, click the gear icon at the top right section of the header from any page. From there, select "User Preferences". You will be redirect to the User Preferences page.



Editing Preferences

The User Preferences page includes a section for updating the user's ProVision password, and Other Settings.



Update Password:

To update your password, type the new password in the "New Password" box, then retype under "Confirm Password" for verification. When complete, click the "Save" button.

Other Settings:

Under "Other Settings", help pop-up bubbles may be enabled or disabled. Click the check box next to "Disable Help Pop-Up Bubbles" to disable, or leave unchecked to keep enabled. When complete, click the "Save" button.

To leave the User Preferences page, click on any ProVision tab in the navigation bar.

ProVision Admin Guide


Admin Guide

The ProVision Admin Guide provides information on features accessible with Admin level permissions within ProVision. For more detailed information on features accessible in the standard user tabs , see the ProVision User Guide.

Accessing the ProVision Admin section

To access the Admin area, click the gear icon at the top right section of the header from any page.

From there, select "Admin". You will then have access the Admin section tabs of ProVision, and will see the Admin Preferences page.



Leaving the ProVision Admin section

To leave the Admin area, simply click the "Exit Admin" link in the navigation bar. You will be redirected to the Dashboard.





Table of Contents

- Admin Preferences
- Authentication Options
- IPAM Administration
- DNS Administration
- DHCP Administration
- Importing Your Data
- Users & Permissions
- API Tab
- Scheduler Tab
- Log
- Approvals
- Constraints

Admin Preferences

Overview



The Admin Preferences page is the home page of the Admin section of ProVision where general platform preferences may be set.

To access it, click the gear icon at the top right section of the header. From there, select "Admin". You will then have access the Admin section tabs of ProVision, and will see the Admin Preferences page. Each module area can be accessed by its own sub-tab button, available at the top of the page.

- Overview
    - Video Walkthrough
- Application Settings
    - License Info
    - Application Settings
    - Backup Settings
        - Manual Backup - 6connect Cloud:
        - Manual Backup - Alternate Server:
        - Backup Settings - Local Installation
    - ACP Settings
    - Logging Options
- Authentication Settings
    - General Settings
    - Remote Authentication Tester
    - Authentication Options
        - RADIUS authentication options (local install only)
        - LDAP authentication
        - SAML authentication

        - SAML Setup
        - SAML Login
    - DUO Mobile
- DNS Settings
    - DNSSEC Settings
    - DNS Dynamic Update Settings
    - DNS Import Settings
- Peering Settings
- Templates

Video Walkthrough


Note: Video at applies to versions 6.0.0 to 7.0.0. For earlier versions, see Admin Preferences Page Overview (v5.1.0+) .

Application Settings

License Info


The License page displays current product license details such as Product, Type, Versions, Expiration, Email, and the option to add/update the 6connect License Key(s).

From the Admin Settings page, ensure the "Application" sub-tab is selected, then click "Manage License".




Current license details for ProVision, and other affiliated 6connect products will display.

To add/update a License Key, paste the key provided into the "Update License Key" box, and click "Update License".



Application Settings

Application Settings is where you provide company specific info that appears in the header and Dashboard.



Time Zone: Supported Time zones are listed here: {EXT} http://www.php.net/manual/en/timezones.php. Default value is ('America /Los_Angeles') and can be modified at any time via the drop down menu

MySQL Timezone: The timezone set from the server's MySQL settings.

Company Name: Enter the preferred name for your company to be used.

Generic Name: This "short" name is used in abbreviated location for the "Customer" tab label, "Customer" and "Site" are common entries.

Header Image: Select an image file for the header

Support Email: Support Email address that displays on the Dashboard

Support Phone: Support phone number that displays on the Dashboard

Path to PHP (Local Installation): The directory path to php location


Path to Nmap (Local Installation): The directory path to nmap location

Nmap Options (Local Installation): Custom nmap options

Customer Label: The display name for the customizable label field available when creating or editing a resource.

Delete Logs after: The number of days to retain logs.

Backup Settings



For cloud users, regular backups can be set up through the Scheduler. However, prior to imports or other large changes, you may wish to manually perform a backup.

Backup Location: The backups may be sent to the 6connect cloud, or to a specific server in the Resource system. Select the radio button for the desired location.

Manual Backup - 6connect Cloud:

Select "6connect Cloud" as your backup location, then click on the "Backup Now" button. You will see a success message below the button if successful.

Manual Backup - Alternate Server:

Manual Backup: Alternate Server saves a backup msql dump to a Server Resource already set up in ProVision.

This Resource needs to have the following information provided in the server section fields in order to establish a connection: Port, Hostname, Username, and Password.

Before selecting Alternate Server Backup:


1) Ensure that the Server Resource exists in ProVision for the backup (Section = "Server"). If needed, create a new entry for the server.

2) Check that the following fields are added to the Server Section:

- Network Port (22 is typical)
- Hostname (this can also be an IP address)
- Username
- Password

See Customizing Sections and Customizing Fields for information on adding fields to sections. Hostname, Username, Password, and Network Port will all be contained under the "Existing Fields" selector when adding fields to the Section.


3) On the Backup Server's Entry page, verify that the server fields are filled in and correct for the ProVision server entry:



If needed, click "Edit" and add or update the information. See Working with Entries for additional information.

Once a Backup server has been set up in ProVision, it will be available to select under Backup Settings: Alternate Server.

Select "Alternate Server" as your backup location, then select the desired ProVision server Resource. After selecting your server, click on the "Backup Now" Button.




If successful, a mysql dump file will be sent to the selected server and a "Success!" message will appear.

Once the connection is confirmed successful, Backups to alternate servers may be scheduled on a recurring basis through the Scheduler Tab, or continued to be performed manually under Backup Settings.


Backup Settings - Local Installation

Additional settings are available for local installations:



Location of mysqldump (Local Installation): This is the location of the mysqldump directory.

ACP Settings




The ACP Settings area links an ACP instance and login credentials to the ProVision instance, and allows the ACP Workflow Gadget to execute Workflows as the provided user.

Enter the ACP URL for a licensed ACP instance, then provide the ACP Username and Password for the user that should be used to execute Workflows. To verify the account, click "Test Configuration" - you will be notified whether the account is valid.

When done, click "Test configuration" to verify the connection and then "Save Changes". Afterwards, you may proceed to configure the ACP Workflows Gadget to specify Workflows to execute in ProVision.

Logging Options



Remote Log IP: Target IP address that we will send log information to

Remote Log Port: Port number for the syslog server you will send log information to

Remote Log Method: Select TCP, UDP, SSL from the dropdown for the log delivery method

Remote Log Backup IP: Target IP address for the Backup syslog server you will send log information to

Remote Log Backup Port: Port number for the Backup syslog server you will send log information to

Remote Log Backup Method: Select TCP, UDP, SSL from the dropdown for the log delivery method


Remote Log Type: Select SysLog format or JSON output

Remote Log Facility: Select the Facility - applies to syslog only

If desired, you may select "Test Connection" to verify the connection before clicking "Save Changes".

Authentication Settings


Authentication options are accessed by clicking the "Authentication" sub-tab at the top of the Admin Preferences page.



In this area, you may set the max session idle time, as well as setup additional authentication options.


Four authentication types are available for ProVision: Radius, LDAP, SAML, and DUO Mobile.

General Settings



Maximum Session Idle: This setting (minutes) controls how long a session can stay idle before being forced to log in again.

Remote Authentication Tester



The Remote Authentication Tester checks Radius / LDAP settings for a user.

Select the Login Method (Radius or LDAP), enter the Username and Password for the user, and then click "Test Login".


Login Method: Select Radius or LDAP, according to your authentication settings.

Username: The username for the user you are testing.


Password: Password for the user you are testing.

Authentication Options

Four authentication types are available for ProVision: Radius, LDAP, SAML, and DUO Mobile. To view settings for each, select the authentication type from the list at the left of the module.



RADIUS authentication options (local install only)



Note: For implementation details, go here.

Radius Enable: Check this box to enable RADIUS functionality.

Radius Server Address: Set to the IP address of your radius server. If this is specified, it will force authentication over radius.


Radius Authentication Port: Set to the port for authentication. Default port is 1812

Radius Accounting Port: Set to the port for radius accounting. Default port is 1813

Radius Key: Set to the shared key of your radius server

To verify the settings connect, click "Test Radius Configuration". When done, click "Save Changes".

LDAP authentication



Note: For implementation details, go here.

LDAP Enable: check the box to enable LDAP functionality.

LDAP Server Address: Set the IP address of your LDAP server.

LDAP Port: Set the port for your LDAP server

LDAP Security: Select the security method of your LDAP server - SSL, TLS or None


Test Server: Click to test the connection to the LDAP server.

LDAP Auth DN/Fetch DN: These strings are used to first authentication the 6connect user and then to retrieve their permissions. The string '%LOGIN%' should be inserted in place of the user's common name both strings. (ex: cn=%LOGIN%,ou=people,dc=6connect,dc=com)

LDAP Group Attribute: If using an internal list of user groups instead of 6connect groups, enter the attribute name for the LDAP groups here. If a Group Attribute is set, it will be used first, otherwise the 6connect schema will be used.

Mapping Permissions to 6connect schema: To integrate 6connect permissions with your existing directory structure then you will need the 6connect schema. It should snap in with any existing LDAP structure and allow you to assign 6connect permissions to your existing users. You can download a copy of the schema from this section.

SAML authentication



SAML is a Single Sign On (SSO) authentication method that uses an external identity provider to authenticate a user at their first login, saving a token to the user's browser that is then used for subsequent logins, so that the user does not need to re-submit credentials.

SAML Setup

Before configuring SAML in ProVision, you must have an account set up with an Identity Provider (IdP) and ProVision users / groups set up in the IdP.

Set up the IdP

To use SAML authentication, you will need SAML set up for your instance with an Identity Provider (IdP), such as *Microsoft ADFS, OneLogin, Elastic SSO,* or others. You can view a list of available SAML IdPs at Wikipedia's SAML based products page.

Users and Permissions:

User credentials will need to be created and associated with ProVision permission group names via the IdP. All user creation, management and permissions handling occurs via the IdP, externally from ProVision.

Configure SAML in ProVision

ProVision setup for SAML is located in **Admin** **Admin Settings** Authentication Options.

Under **SAML Configuration**:

Enable SAML authentication by clicking the checkbox next to "Enable".

The following fields are required and will need to be obtained from the IdP:

- **User Attribute(Required):**
- **Group Attribute(Required):**
- **IdP Metadata(Required):**

Under **SAML Service Provider Configuration:**

- **Sign logout request:**
- **Sign redirect request:**
- **Unencrypted Assertions from IdP Will be rejected:**
- **Private Key:**
- **Certificate (Required):**

Links are provided below the configuration settings for the ProVision SP Metadata file in php and xml format, which will be needed to provide to the IdP.

You can test the configuration by clicking the "Test SAML Configuration" button, a new page will open giving health check information for your provided attributes.

SAML Login

Once the correct configuration has been established and users set up for SAML in the IdP, users will be able to use SAML logins.

Documentation Note: Depending on the IdP used, some screens may appear different from what is shown here.

Initial Login:


The initial login process occurs for the first time a user logs in, and anytime afterwards if the browser token is not present (e.g., cookies are cleared from the browser, the browser closed, or a new browser is used).

From the ProVision login page, select SAML from the authentication options dropdown - you do not need to enter Username or Password.



You will be redirected to the IdP site as set up in the Admin Configuration - here, we are using Microsoft ADFS (Active Directory Federation Services).

Log into the IdP site using your SAML credentials, and click "Sign In".



If the sign in is successful, you will be logged into the ProVision home page.


Subsequent Logins:

After the initial login via the IdP (as long as the auth token is present) users will be able to login to ProVision simply by selecting the "SAML" options from the ProVision login page without entering credentials.



The auth token may be destroyed or not available if browser cookies have been cleared, a different browser used, or the browser fully closed, depending on security settings. In these cases, the user will need to sign in again via the IdP.

DUO Mobile



To use DUO Authentication, an account must first be set up with DUO.

Once an account is set up, obtain the Integration Key, Security Key, and DUO API Host name.

Enter those items into **Admin** **Authentication Options** DUO Mobile Configuration, and click "Update" to save your changes.

You may also test the current configuration by clicking "Test DUO Configuration".


If you need to disable DUO Mobile authentication from ProVision from outside of the GUI, a command-line disable tool is available. Run:

```
php tools/disable_duo.php
```

DNS Settings

DNS Settings are accessed by clicking the "DNS" sub-tab at the top of the Admin Preferences page.

DNSSEC Settings



If using DNSSEC, select whether to enabled DNSSEC local signing, or sign zones by dnssec-tools, then enter the following information:

zonesigner path : Enter the zonesigner path that will be used for DNS. Zonesigner is required if dnssec-keygen and dnssec-signzone are not set.

Sign zones by ISC BIND Utilities: Select whether to use ISC BIND utilities to sign zones.


dnssec-dsfromkey path : Enter the dnssec-dsfromkey path that will be used for DNS. Required in all cases.

Additional Entropy

If delays occur due to lack of available entropy on servers, see the following article on how to set up additional entropy using haveged here:


https://www.digitalocean.com/community/tutorials/how-to-setup-additional-entropy-for-cloud-servers-using-haveged

DNS Dynamic Update Settings




Dynamic Update via nsupdate: Toggle to "On" if you wish to use Dynamic Updates via nsupdate, instead of ProVision's internal implementation.

DNS Backup Settings



Records Limit : The limit for the number of records a zone may have for a zone to process a backup. If the records count exceed this number, zone backups will be omitted at zone push.


DNS Import Settings



Keep Import File: Toggle to "on" if you wish to retain the zone import file inside the zone.

Peering Settings

Peering Settings are accessed by clicking the "Peering" sub-tab at the top of the Admin Preferences page.



ASN : Enter the ASN(s) that will be used for Peering, or may leave blank. Separate multiple ASNs with a comma.

VRF Support: Check to enable adding the VRF gadget to the router Section. Currently, only supports Cisco routers.


PeeringDB Cache: Displays a status notification to show whether Peering DB cache is enabled or disabled.

Templates: Create or manage custom Peering Templates.

PeeringDB Account: Click the "change" link to input PeeringDB account credentials. PeeringDB account information is required to retrieve and update peering information. Enter a valid PeeringDB account Username and Password. When done, click the "Test" button to verify the account, and save.

Templates

Email Templates are accessed by clicking the "Templates" sub-tab at the top of the Admin Preferences page.




This is where you can edit outgoing email templates for IP block assignments.

To edit, click inside the text area box, make the desired changes, then click the "Save Changes" button.

Authentication Options

Authentication



Depending on the authentication method chosen by your organization, there may be a separate authentication to login or logout of the application via the drop down menu.

Change Order of Login Menu Dropdown

The drop down menu defaults to "local" - if you are using another authentication method, you can use the following to change the default ordering and improve usability.

In the file data/globals.php, add a line:

```
define('DEFAULT_LOGIN_TYPE', 'ldap');
```

Acceptable values instead of 'ldap' are 'local', 'radius' and 'ldap'.

By default, credentials are managed via the local authentication mechanism provided by 6connect. See the following sections for more detail authentication configurations:

- LDAP Authentication
- LDAP Authentication on Windows Server
- RADIUS Authentication

For information on SAML and DUO, see Admin Preferences.

LDAP Authentication

LDAP Authentication

To setup an LDAP server for authentication, you must perform the following three procedures:

- LDAP Authentication
  - Configure the LDAP Server:
    - LDAP Schema - Example
  - Creating a LDAP User:
    - Test the LDAP Server
  - Configure ProVision for LDAP Authentication

Configure the LDAP Server:

Configuring the LDAP server involves ((adding the schema)) and adding LDAP users / groups to the server:

LDAP Schema - Example

```
attributetype (1.3.6.1.4.1.5023215.2.3.21 NAME 'sixConnGroup' SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 )
objectclass ( 1.3.6.1.4.1.5023215.2.4.2 NAME 'sixConnectPermissionsV2' DESC '6Connect Permissions Object v2'
SUP top AUXILIARY MUST ( sixConnGroup ) )
```

Creating a LDAP User:

SSH into your openLDAP server and create a new 'ldif' file. Example:

```
dn: cn=JoeSmith,ou=people,dc=6connect,dc=com
cn: JoeSmith
sn: JoeSmith
objectclass: top
objectclass: person
objectclass: sixConnectPermissionsV2
sixConnGroup: "Global Admins"
sixConnGroup: "IT Engineering"
sixConnGroup: "Sales"
sixConnGroup: "Customer Admin"
userPassword: testpass
```

To create a new user, make a new ldif file and change all instances of "JoeSmith" to whatever username you wish to create and update the password. Keep all of the object class definitions as listed above. Add a sixConnGroup declaration for each ProVision user group a user is in.

After the file is created, run the following command to add the new user to LDAP server:

```
ldapadd -h [SERVER] -x -f [LDIF FILE] -D [ROOTDN] -w [ROOT PW] -v
```

Example:

```
ldapadd -h localhost -x -f 6connect.ldif -D "cn=Manager,dc=6connect,dc=com" -w secret -v
```

The user will now be active in openLDAP and can be used to login to ProVision.

Test the LDAP Server

To query the LDAP server, run the following command on any server which has openLDAP enabled:

```
ldapsearch -b [BASE] -h [IPADDRESS] -D [DOMAIN] -w [PASSWORD] [USER]
```

Note: We have not been able to use a v6 address at with this tool, even though multiple sources say it should work.

At the end of the command where [USER] is specified, user or groups can be used (in LDAP format) to query.


Example:

```
ldapsearch -b "dc=6connect,dc=com" -h 50.240.195.129 -D "cn=Mayor,ou=people,dc=6connect,dc=com" -w testpass
"cn=MajorMiner"
```

Configure ProVision for LDAP Authentication

To configure the use of LDAP authentication with ProVision, follow the steps below.

- Log into 6connect ProVision
- Go to Admin -> General Settings -> Authentication
- Click the LDAP Enable checkbox.
- Fill in the hostname or ip address, authentication port, LDAP Security, Auth DN, and Fetch DN.



Example values in this case would be:

LDAP Enable: (Checked)

LDAP Server Address: 52.240.195.12

LDAP Port: 389 (or SSL/TLS port is 636)

LDAP Security: None

LDAP Auth DN: cn=%LOGIN%,ou=people,dc=6connect,dc=com

LDAP Fetch DN: cn=%LOGIN%

Setting default login authentication options

In the login screen, you would select the authentication method from the dropdown. If you like, you can set the default login option in the following way:

Go to the /data/globals.php and open in vi (or other editor). Add in the following text as the last line of the file (before the closing ?>)

define('DEFAULT_LOGIN_TYPE', 'radius');

Acceptable values are "local", "radius" and "ldap". If this line is not present in globals.php, the default option is "local".

Using SSL encryption

To use SSL encryption with LDAP, the ldap.conf file must be correctly configured on the ProVision server.

Typically, the LDAP configuration file is kept at "/etc/ldap/ldap.conf". Make sure the following line is present:

```
TLS_REQCERT allow
```

and restart the webserver.

LDAP Authentication on Windows Server

LDAP Authentication on Windows Server

Starting in 3.6, ProVision supports LDAP authentication (including Windows Server!). To setup an LDAP server for authentication, you must perform the following procedures:

- LDAP Authentication on Windows Server
  - Configuring the LDAP functions on your Windows Server
    - LDAP Schema - Example
    - LDAP User Example
  - Test the LDAP Server
  - Configure ProVision for LDAP Authentication

Configuring the LDAP functions on your Windows Server

You should confirm these steps with your LDAP admin - the purpose of this walkthrough is to provide some level of detail on how to extend LDAP functionality to support integration with an application like ProVision.

Step 1: Prepare to extend the Schema (http://technet.microsoft.com/en-us/library/cc961754.aspx)

This is not a minor operation and requires interaction with various control modification areas of Windows Server:

- If you have not modified the schema before, you will need to use the Active Directory Schema console on a DC (Domain Controller) to permit write access to the DC schema.
- Since the schema object has dedicated permissions, admins must be a member of the Schema Administrator group (Schema Admins).
- Note that the DC that is holding the Schema Master Role is the only one allowed to write to it.

Step 2: Decide on method for Installing/executing Schema Extensions (http://technet.microsoft.com/en-us/library/cc961742.aspx)

If you have already used other AD integrations, this should be straightforward. We recommend using the LDIF script method

Step 3: Add and Modify a Schema Object (http://technet.microsoft.com/en-us/library/cc961575.aspx)

To add a new attribute to the schema, you first have to create a attribute object. The you will need to complete the following steps:

- Select a name for the attribute (ProVision assumes that the name will be '**sixConnGroup**')
- Get a valid Object Identifier (OID) from an issuing authority (http://msdn.microsoft.com/en-us/library/ms677620.aspx)
  - Generate an Object Identifier

    Microsoft has released a script that can generate an Object Identifier (OID): https://gallery.technet.microsoft.com/scriptcenter/56b78004-40d0-41cf-b95e-6e795b2e8a06
- Document the attribute syntax
- Confirm that the attribute should be single-value
- Confirm the attribute indexing behavior
- Decide if the attribute needs to be distributed to the Global Catalog

LDAP Schema - Example

```
attributetype (1.3.6.1.4.1.5023215.2.3.21 NAME 'sixConnGroup' SYNTAX 1.3.6.1.4.1.1466.115.121.1.15 )
objectclass ( 1.3.6.1.4.1.5023215.2.4.2 NAME 'sixConnectPermissionsV2' DESC '6Connect Permissions Object v2'
SUP top AUXILIARY MUST ( sixConnGroup ) )
```

LDAP User Example

SSH into your openLDAP server and create a new 'ldif' file. Example:

```
dn: cn=JoeSmith,ou=people,dc=6connect,dc=com
cn: JoeSmith
sn: JoeSmith
objectclass: top
objectclass: person
```

```
objectclass: sixConnectPermissionsV2
sixConnGroup: "Global Admins"
sixConnGroup: "IT Engineering"
sixConnGroup: "Sales"
sixConnGroup: "Customer Admin"
userPassword: testpass
```

To create a new user, make a new ldif file and change all instances of "JoeSmith" to whatever username you wish to create and update the password. Keep all of the object class definitions as listed above. Add a sixConnGroup declaration for each ProVision user group a user is in.

After the file is created, run the following command to add the new user to LDAP server:

```
ldapadd -h [SERVER] -x -f [LDIF FILE] -D [ROOTDN] -w [ROOT PW] -v
```

Example:

```
ldapadd -h localhost -x -f 6connect.ldif -D "cn=Manager,dc=6connect,dc=com" -w secret -v
```

The user will now be active in openLDAP and can be used to login to ProVision.

Test the LDAP Server

To query the LDAP server, run the following command on any server which has openLDAP enabled:

```
ldapsearch -b [BASE] -h [IPADDRESS] -D [DOMAIN] -w [PASSWORD] [USER]
```

Note: We have not been able to use a v6 address at with this tool, even though multiple sources say it should work.

At the end of the command where [USER] is specified, user or groups can be used (in LDAP format) to query.


Example:

```
ldapsearch -b "dc=6connect,dc=com" -h 50.240.195.129 -D "cn=Mayor,ou=people,dc=6connect,dc=com" -w testpass
"cn=MajorMiner"
```

Configure ProVision for LDAP Authentication

To configure the use of LDAP authentication with ProVision, follow the steps below.

- Log into 6connect ProVision
- Go to Admin -> General Settings -> Authentication
- Click the LDAP Enable checkbox.
- Fill in the hostname or ip address, authentication port, LDAP Security, Auth DN, and Fetch DN.



Example values in this case would be:

LDAP Enable: (Checked)

LDAP Server Address: 52.240.195.12

LDAP Port: 389 (or SSL/TLS port is 636)

LDAP Security: None

LDAP Auth DN: cn=%LOGIN%,ou=people,dc=6connect,dc=com

LDAP Fetch DN: cn=%LOGIN%

Setting default login authentication options

In the login screen, you would select the authentication method from the dropdown. If you like, you can set the default login option in the following way:

Go to the /data/globals.php and open in vi (or other editor). Add in the following text as the last line of the file (before the closing ?>)

define('DEFAULT_LOGIN_TYPE', 'radius');

Acceptable values are "local", "radius" and "ldap". If this line is not present in globals.php, the default option is "local".

Using SSL encryption

To use SSL encryption with LDAP, the ldap.conf file must be correctly configured on the ProVision server.

Typically, the LDAP configuration file is kept at "/etc/ldap/ldap.conf". Make sure the following line is present:

```
TLS_REQCERT allow
```

and restart the webserver.

RADIUS Authentication

RADIUS Authentication

ProVision supports 6connect vendor-specific attributes (VSAs) for use with RADIUS authentication. To use these attributes, you must perform the following procedures:

- RADIUS Authentication
  - Add the 6connect VSA to the Radius Installation
  - Configure Radius Accounts
  - Test Radius Accounts
  - Configure ProVision for Radius Authentication

Add the 6connect VSA to the Radius Installation

To use the 6connect VSA, the attributes must be defined on the RADIUS server. Add the following RADIUS dictionary file to your RADIUS server and name it dictionary.6connect:

ProVision 4.0 and greater:

```
VENDOR 6connect 36009

BEGIN-VENDOR 6connect

ATTRIBUTE 6connect_user_group 10 string
#A 6connect User Group to which this user belongs.

END-VENDOR 6connect
```

Make sure to add the following to the primary dictionary file: $INCLUDE dictionary.6connect

Configure Radius Accounts

On the Radius server, configure the user accounts that will have access to the ProVision system.

An example of a ProVision account configuration for the user file on a Freeradius system for ProVision 4.0 and greater:

Example: To add a new radius user, edit the 'users' file found at /etc/raddb/users and add a block like:

Setting up a RADIUS account

```
bobber Cleartext-Password := "hello"
6connect_user_group = "Global Admins,Group 2,Group 1,Group Nonexistant"
```

The Radius server must be restarted every time you add, remove, or modify users. To restart the Radius server, use this command:

```
/etc/init.d/radiusd restart
```

Note on RADIUS attributes

There are many Radius attributes, but '6connect_user_group' is the one used by 6connect ProVision. It is a comma-separated list of all the group names that the user belongs to.

Test Radius Accounts

For ProVision 4.0 and higher, test and response should look like the following:

To query a radius server, use the following command format:

```
radtest [USERNAME] [USERPASSWORD] [SERVER] 0 [SECRET]
```

Example:

```
radtest bobber hello 208.39.140.106 0 6connect
```

A successful response will look like this:

```
Sending Access-Request of id 198 to 208.39.140.106 port 1812
User-Name = "bobber"
User-Password = "hello"
NAS-IP-Address = 67.221.240.229
NAS-Port = 0
Message-Authenticator = 0x00000000000000000000000000000000
rad_recv: Access-Accept packet from host 208.39.104.106 port 1812, id=198, length=69
Attr-10 = 0x476c6f62616c2041646d696e732c47726f757020322c47726f757020312c47726f7570204e6f6e6578697374616e74
```


A rejected response may look like this:

```
Sending Access-Request of id 68 to 208.39.140.106 port 1812
User-Name = "bobberbro"
User-Password = "hello"
NAS-IP-Address = 67.221.240.229
NAS-Port = 0
Message-Authenticator = 0x00000000000000000000000000000000
rad_recv: Access-Reject packet from host 208.39.104.106 port 1812, id=68, length=20
```

Configure ProVision for Radius Authentication

To configure the use of Radius authentication with ProVision, follow the steps below.

- Log into 6connect ProVision
- Go to Admin -> Authentication
- Ensure that Radius functions are marked as available. Radius functions are always available on 6connect cloud instances. Radius functions are available on VM Images and Local Installations only if the relevant PHP Pear Radius Libraries have been installed.



- Click the Radius Enable checkbox.
- Fill in the hostname or ip address, authentication ports, accounting port, and shared Radius key as specified.

Setting default login options

⚠

In the login screen, you would select the authentication method from the dropdown. If you like, you can set the default login option in the following way:


Go to the /data/globals.php and open in vi (or other editor). Add in the following text as the last line of the file (before the closing ?>)

define('DEFAULT_LOGIN_TYPE', 'radius');

Acceptable values are "local", "radius" and "ldap". If this line is not present in globals.php, the default option is "local".

IPAM Administration

Overview



IPAM Administration is accessed through the Admin area of ProVision. It includes sections to manage IPAM Lists, the Holding Tank, LIR, and IPAM Configuration.

- Overview
  - IPAM Lists Management
  - Holding Tank Management
  - LIR Management and Use
  - IPAM Configuration
  - Additional Information:

IPAM Lists Management

These links are to the respective IPAM Parameters that are available for customization - tags, regions, subnets, IPAM Rules, Numbering Authority, and IPAM / VLAN Columns.

See the IPAM Parameters page for additional details and examples for updating IPAM Parameters, IPAM / VLAN column customization, and IPAM Rules for additional information on managing IPAM Rules.

Holding Tank Management

When IPv4/IPv6 resources are reclaimed, they are placed into the "Holding Tank". This feature allows for a block to stay out of the available address pools until the administrator approves it.


See the Holding Tank Management page for more details.

LIR Management and Use

ProVision supports multiple LIRs from the UI. This allows users to select from various LIRs when they want to update SWIP/RPSL information for a subnet allocation.

See the LIR Management and Use page for more details.

IPAM Configuration



Holding Tank Days: This is the number of days that a block will be held in "Holding" status before being available to be moved to the Available pool, and thus ready to be assigned. By default this is initially set to 30 days.

IPv4 Block Scanner Enable: This is a beta feature that allows a user to scan a block of IPv4 space and show host counts of responding addresses.

IPv4 Block Scanner Max Block Size: The max size (mask) the IPv4 Block Scanner considers (Command Line tool only).

RIPE Database: Select the desired database - RIPE or TEST.

Show /32 or /128 mask for statics: Enable to show /32 or /128 masks.

Merge after unassign: Select to automatically merge adjacent blocks when they become available after unassign.

Automatic Merge respects Tags & Regions: When "Merge after unassign" is selected, the automatic merge will stop if the two blocks do not have matching tags and regions.

Enable Map View: Select to enable a map view of assigned aggregates on the IPAM tab, determined by assigned region.

Default Tag Selection Mode: Set which radio button will be selected by default when working with tags in the IPAM Gadget

Sparse Allocation Block Size: Sets the size of the blocks generated for IPv6 Sparse Allocation

Sparse Allocation Type: Sets the Sparse Allocation scheme to Leftmost, Rightmost, or Center.

Additional Information:


- IPAM Parameters
- IPAM Rules
- Holding Tank Management
- RIR Integration: SWIP/RPSL
- LIR Management and Use

IPAM Parameters

IPAM Parameters - Overview

IPAM Lists Management is access from the Admin section of ProVision, under the **IPAM Admin** tab.

Through this area, admin users can update IPAM tags, IPAM Regions, IPv4 / IPv6 subnets, IPAM Rules, Numbering Authority, and IPAM / VLAN Columns.




- IPAM Parameters - Overview
  - Add / Edit IPAM Tags
  - Add / Edit Regions
    - Applying a Google Geocoding API Key:
    - Managing Regions
    - Valid / Invalid Regions
  - Add / Edit IPv4 / IPv6 Subnet Dropdowns
  - Edit IPAM Rules
  - Numbering Authority
    - Available Domain Types
    - Working with Numbering Domains
      - Create a Numbering Domain
      - Number Domain Actions
  - Edit IPAM or VLAN Columns
  - Additional Information

Add / Edit IPAM Tags

When you are applying properties to IP blocks, you have the option to edit tags. IPAM Tags are used in a number of areas in ProVision and can be added or edited from this screen.

To add a new IPAM tag, click on "Add Tag" at the top of the Edit IPAM Tags page.



Then, type in the desired name value for the new tag, and hit "Add Tag".



To **edit** a tag, simply type your changes in to the text box with the tag name. Tags with unsaved changes will be highlighted until saved.

To **reorder** the tag list, click and hold on the "list" icon (three lines) to the left of the tag name, then drag to the desired location in the list and release.

To **delete** a tag, click on the red "delete" symbol to the right of the tag name.



When complete, be sure to click on the "Save" button to save your changes.

Add / Edit Regions

Google Geocode API Key Requirement


Due to changes in Google's licensing and Geocoding API, the previous geolocation method used in ProVision is no longer supported. IPAM Regions now requires a Google Geocode API Key in order for IPAM Maps to properly determine a Region's location.

6connect is exploring adding additional map integration options for ProVision.

Any customers who require an alternative geocode option supported apart from Google Geocode API key, please contact us at feedback@6connect.com.

If enabled, Regions can function as a way to further define your network segments (regional tie-downs, etc.). This gives you flexibility for allocations and assignments beyond simply using Tags. Regions are used by the IPAM Gadget, the IPAM Manage UI, and IPAM Map View.

Access IPAM regions from **IPAM Admin** **Edit IPAM Regions**.



The Regions display includes fields for Region Code, Name, and Address.

- 'Region Code' is the shorthand name that will show in the IPAM Gadget and IPAM Manage screens.
- 'Name' is the long form name value that will be written to the database, used for API calls, and is also used for some filter selectors.
- The 'Address' field is used by IPAM map view (via Google Geocode API) to geolocate aggregates with that assigned region. Address may be in the form of a City / State / Country, a full street address, a company name, or other search term that Google API can return a location for. The more accurate your address information, the more accurate map view will be with your aggregate locations. An "address" value that appears invalid to Google Geocode API will display a yellow ⚠ warning symbol.

To use regions, you will need to apply a Google Geocode API Key.

Applying a Google Geocoding API Key:

Step 1: Obtain a Google Geocoding API Key


To get a Google Geocoding API Key, follow the instructions listed here:

How to get a Google Geocoding API Key

Note: In order to obtain a Google Geocoding API Key, a company must have a subscription enabled to Google Cloud Platform Console.


Step 2: Assign the API Key to IPAM Regions

Once assigned a Google Geocoding API Key, paste the API key into the IPAM regions page under "Apply google geocode api key" and click the "Apply" button.




Managing Regions


To **add** a new Region item, click the "Add Item" link at the top of the screen.



In the form that appears, type in a new Region Code, Name, and Address into the empty fields and click "Add Element".



The new Region will be added to the Region list.



To **edit** a region, simply type your changes in to the text box with the region name. Then, click on the "Update" Button.

To **delete** a region, click on the red "delete" symbol to the right of the region name.

To **reorder** the regions list, click on the "Reorder list alphabetically" button.

Valid / Invalid Regions

Valid addresses (according to Google's API) will show a green check mark next to the address field, invalid addresses (unable to be mapped) will show a yellow exclamation mark.



If you are getting unexpected results from the Regions validity checker, copy the address input into to ProVision into Google Search, and check out the top result(s) - sometimes, Google's API may be finding different results than you expected. For best results, be as specific as possible in


Add / Edit IPv4 / IPv6 Subnet Dropdowns

When assigning blocks using the "Smart Assign" function in the IPAM Gadget, the user has an option to assign an IP resource by allocation size. ProVision supports assignments down to a single host level (/32 for IPv4, /128 for IPv6).


Note on Editing the Subnet Dropdown

Keep in mind that this is a global edit. If the values in the dropdown are changed, it will affect ALL users of the ProVision application.


To add a new Subnet item, click on "Add Item" at the top of the Edit List: IPv4 or IPv6 Subnets page.



Then, type in the desired Value and Display value for the Subnet, and hit "Add Item".



After adding a new item, it will show at the bottom of the list highlighted in yellow. Hit "Save" to save your changes.



To **edit** a subnet, simply type your changes in to the text box. Entries with unsaved changes will be highlighted until saved.

To **reorder** the subnet list, click and hold on the "list" icon (three lines) to the left of the subet, then drag to the desired location in the list and release.

After adding or editing a subnet, you may wish to clean up the list order by hitting "Sort List Numerically" at the top of the page to reset the list order including the new entry.


To **delete** a subnet, click on the red "delete" symbol to the right of the subnet entry.

When complete, be sure to click on the "Save" button to save your changes.

Edit IPAM Rules

IPAM Rules allow for certain address positions within an IP Block to be reserved when utilizing Direct Assign and Smart Assign.


These rulesets may be managed in the "Edit IPAM Rules" section of IPAM Admin.



For additional details, see IPAM Rules.

Numbering Authority

Numbering Authority allows Admin users to configure domain sets of values, for use with associated ProVision functions or external number tracking.



With Numbering Authority, you can create new numbering domains, track which values have been handed out, free values no longer in use, generate the next sequence value, and associate keys-value pairs to a number value. Numbering Domains may be used with ProVision's APIv2 to generate numbers for use within ProVision instances or custom applications.

Available Domain Types

Four numbering domain types are available in Numbering Authority: Sequential, Multi-Range, UIUDv4, and IPv6 Sparse Allocation.

Sequential:

Provides a sequential number domain starting with '0' and progressing in numerical order. Potential Applications: Ticketing Queues, Customer Numbers

Multi-Range:

User-defined numbers and number ranges (e.g.: 2-3,4-6, 25, 27-28) to include or exclude as available. Potential Applications: VLANs

UIUD v4:

Generates a Universally Unique Identifier according to v4 (Random) standard. Potential Applications: Unique Identifiers

IPv6 Sparse Allocate:

Determines the next IPv6 block to assign to evenly distribute assignments throughout the provided range. Used with the IPAM IPv6 Aggregate Sparse Allocate function. See: Working with IP Aggregates . Applications: ProVision IPv6 Sparse Allocation


Working with Numbering Domains

See below for additional information on creating Numbering Domains and using domain actions.

Create a Numbering Domain

Go to Admin IPAM Admin, and select the "Numbering Authority" page.

Create a new numbering domain by expanding the "Create New Numbering Domain" section, then typing in a name for the new domain and selecting a domain type.




Enter information for the specific domain type, if necessary, and select whether to allow number reuse. When done, click "Create".

Number Domain Actions

Once a numbering domain is created, you may perform the following actions:


Get Next Value:

Gets the next value in the domain, adds it to the list of used domain values (assigns to the domain), and displays that value to the user.



View Assigned Values:

View values that are assigned to the domain, view used/free status, free assigned blocks, and save key-value metadata to values.



- Sort by Value and Free/Used values by clicking the column names
- To add metadata to a value, enter your information into the "Key" and "Value" fields under Metadata, then click "Save".
- Free a value for reuse, if allowed, by clicking "Free" under the value Actions column.

Delete:

Deletes the numbering domain.

Edit IPAM or VLAN Columns


The Edit IPAM Columns and Edit VLAN Columns pages lets you change the order, column name, and visibility of IPAM / VLAN columns globally for IPAM / VLAN areas, respectively, in ProVision.

Editing IPAM Columns will affect the order, name, and visibility of columns in IPAM Manage and the IPAM Gadget, and the available fields in Edit Block for both VLAN and IPAM.

Editing VLAN columns will affect the order, name, and visibility of columns in VLAN Manage, VLAN Advanced, and the available fields in Edit Domain / Edit VLAN.


Additionally, for both IPAM and VLAN, any disabled fields will not be filterable or accessible in IPAM / VLAN Reports.

Eleven default ProVision fields and ten user-defined "Metadata" fields are available for customization.



Keep in mind that "Edit Columns" is a global edit. If the values for order, header, or visibility are changed, it will affect ALL users of the ProVision application!

To **edit** a column name, simply type your changes in to the text box. and click the "Update" button.




To **reorder** the columns, click and hold on the "list" icon (three lines) to the left of the subet, then drag to the desired location in the list and release.



To **toggle visibility** for a column, click in the checkmark field to the right of the column name to enable / disable visibility.

This shows or hides the column in both IPAM Manage and the IPAM Gadget, and affects all users.



When complete, be sure to click on the "Update" button to save your changes.

Additional Information

Continue on to the following pages for additional information on IPAM Admin tasks in ProVision:

- IPAM Rules
- Holding Tank Management
- LIR Management and Use


For additional information on non-admin IPAM areas, see:

- IPAM Tab


IPAM Rules

IPAM Rules

IPAM Rules are accessed from the Admin section of ProVision, under the **IPAM Admin** tab by clicking on "Edit IPAM Rules".



In the IPAM Admin "Edit IPAM Rules" section, Admin users may view all existing IPAM Rules, the blocks affected by each rule, and delete rules.



- IPAM Rules
  - IPAM Rules Overview
  - IPAM Rules Behavior and Bounds:
  - Edit IPAM Rules Page
  - Add an IPAM Rule:
    - IP Rule Positions
  - Edit an IPAM Rule:
  - View Affected IP Blocks:
  - Delete an IP Rule:
  - Working with IP Rules:
  - Additional Information

IPAM Rules Overview

IPAM Rules allow users to exclude IP addresses from being assigned by Smart Assign or Direct Assign, based on the address position in the block (ie, first address, last address, n^{th} from last).

Reserved addresses are set by their position in the block, starting with position '1' to represent the first address, '2' the second, and so on (1,2,3). The last position in the block is represented as '0', with each step backwards set as the next lowest negative integer (0, -1, -2, 3). Rulesets may reserve one or many positions in a block, so you can choose to reserve only the first address (1), only the last address (0), or combinations as desired - reserving the first three and last three addresses on a block would look like (1,2,3,0,1,-2).


IPAM Rules may be created and applied to blocks under the IPAM Tab -> IPAM Manage screen, in the Action Menu for the desired block. Additional management tasks are available under the IPAM Admin -> "Edit IPAM Rules" page.

IPAM Rules Behavior and Bounds:

- Rules may be applied to IPv4 or IPv6 blocks
- Once a rule has been applied to a block, the addresses at the selected rule positions will by bypassed when Smart Assigning from that block, or return an error when Direct Assigning that position from the IPAM Gadget.
- Only one ruleset may be applied per block - so if a rule already exists for reserving the first address in a block, and a second rule exists for reserving the last address, and you would like to use both, a third, new ruleset must be created that combines reserving both first and last.
- Rules cascade down the IP tree. If a rule is applied to a /24, child blocks under that /24 (/30s, etc) will have the same ruleset applied.
- Changing the positions in a ruleset applies that change to all blocks using that rule - ensure that changes are desired universally when updating a rule.
- If a rule's position(s) is outside of the boundary of the selected block (for example, trying to reserve the 60th address of /30), an error message will notify the user and prompt for a different rule selection.

Edit IPAM Rules Page

In the IPAM Admin "Edit IPAM Rules" section, Admin users may view all existing IPAM Rules, the blocks affected by each rule, create new rules, and delete existing rules.



Add New Rule: Opens the "Manage Ruleset" interface where a new rule may be created. This module is also accessible from the "IP Rules" option on the IPAM Manage Action Menu.

Search: Filter the list of rules by searching for a rule name.

Rule Name: The user-created name of the rule. **Clicking** on the rule name will bring up the Manage Ruleset screen, showing an editable list of rule positions.

Creation Date: Date the rule was created.

Positions: How many positions are reserved by the rule.

View Applied Networks: Shows a list of blocks that have the rule applied.

Delete Rule: Deletes the selected rule.

Add an IPAM Rule:

Adding an IPAM Rule from the Admin area of ProVision functions the same way as if accessed from IPAM Manage.

Click on "Add new Rule", and the Manage Ruleset screen will appear, prompting you to enter a Ruleset name, and select positions to reserve.

IP Rule Positions

Reserved addresses are set by their position in the block. Positions start at '1', for the first address in a block, and step up by one for each subsequent IP address. The last position in a block is '0', representing the last address, and steps down a negative integer for each position from last - so the last three addresses in a block would be represented by (0, -1, -2). When reserving multiple positions, the typed order of the positions does not matter.

Position examples:

(1) - Reserves the first IP

(0) - Reserves the last IP


(1,2,3) - Reserves the first three IPs

(0, -1, -2) - Reserves the last three IPs.

(1,2,3,0,-1,-2) - Reserves the first three and last three IPs


Type in the desired name for the new rule, and one or multiple positions (denoted by integers separated by commas) into the box below the name.

When complete, click the "Save" button, or hit "Cancel" to exit without saving. The Rule preview screen will appear.




Edit an IPAM Rule:

From the Admin IPAM Rules page, click on the Rule entry in the list when highlighted.



This will bring up the "Manage Ruleset" module, showing the rule name and the currently reserved positions for the ruleset.

To change the rule name, simply type the desired changes into the Rule Name text box, and click "Save".




To edit the positions in the rule, either delete a position by clicking on the "x" for the position, or add a new position by typing the position number and then hit enter.

When you are done with your changes, click the "Save" button.

To discard changes, or exit the module, click "Cancel".

Note: When positions are changed, the change applies to all blocks using that rule! Ensure that the change is desired universally for all blocks using that rule prior to updating.

View Affected IP Blocks:




Clicking on "View Affected IP Blocks" in the IP Rules list for a rule will show a list of blocks that currently have the rule applied. It is recommended that you check the affected blocks list before editing or deleting an IP Rule to ensure that the changes are desired for the affected blocks.



Delete an IP Rule:

To delete an IP Rule, click on the "Delete Rule" button for the rule in the IPAM Rules list. This will permanently delete the rule and remove it from any blocks currently affected by the rule.

If you only wish to remove a rule from a block, but retain the rule for future use (or to retain use by other blocks), please see "Remove a rule from a block" detailed at Working with IP Rules.



Working with IP Rules:

For additional information on common IP Rules tasks that do not require Admin access, see Working with IP Rules in the ProVision User Guide.

Detailed walkthroughs of creating a new rule, applying an existing rule to a block, and removing a rule from a block are provided.

Additional Information

See the following pages for additional information on IPAM Admin tasks in ProVision:


- IPAM Parameters
- Holding Tank Management
- LIR Management and Use

For additional information on non-admin IPAM areas, see:

- IPAM Tab

Holding Tank Management

Holding Tank Overview




The Holding Tank, accessible from **IPAM Admin** Process Holding Tank, displays a list of all unassigned IPAM blocks with the "Holding" status. Blocks older than the IPAM Configuration Holding Tank Days setting may be processed to be returned to the "Available" status.

- Holding Tank Overview
  - Holding Tank Views
    - View Blocks over X days (Default View)
    - View Pending Blocks
    - View All Blocks
  - Sort Holding Tank Blocks
  - View Block in IPAM Manage
  - Processing Blocks
    - Process Individual Blocks
    - Process All Blocks
    - Process Completed
  - Holding Tank Permissions
  - Additional Information

Holding Tank Views

Access the holding tank from **IPAM Admin** Process Holding Tank.




Then, at the top of the holding take, select the desired view from the top of the "Process Holding Tank" page in IPAM Admin. You may choose to view Blocks over X days, View Pending Blocks, or View All.

View Blocks over X days (Default View)

The default Holding Tank view is "View Blocks over X days", which only displays blocks over the "Holding Tank Days" setting in IPAM Configuration. To change to this view from a different view, click "View Blocks over X days" from the view list in the top center of the Holding Tank.


In this view, all processable blocks are shown, and you may select either specific blocks or all blocks for processing.



View Pending Blocks

To view only Pending blocks, click "View Pending Blocks " from the view list in the top center of the Holding Tank. "View Pending Blocks over X days" only displays blocks more recent than the "Holding Tank Days setting".


Pending blocks are not selectable or processable, but display the same data as processable blocks. You may view additional details for the block in IPAM Manage by clicking on CIDR link for the desired block.



View All Blocks


To all blocks, click "View All" from the view list in the top center of the Holding Tank. "View All" displays both Pending and processable blocks, but only processable blocks older than the Holding Tank Days may be selected for release.

Pending blocks display in a lighter color text than processable blocks, and do not have a selection box available. Any block may be viewed in IPAM manage by clicking on the CIDR link for the block, and the list may be sorted into ascending/descending order for any field.




Sort Holding Tank Blocks

From any view in the Holding Tank, click on the up/down arrows next to the column name to sort the results by ascending/descending order for that field.



View Block in IPAM Manage

While in the Holding Tank, you may open the IPAM Manage page for a specific block by clicking on the block's CIDR - this allows you to review the block or manually manage it otherwise.



Processing Blocks


The Process Blocks action(s) in the Holding Tank will process all selected blocks with the "Holding" status older than the "Holding Tank Days" setting, and change them to the "Available" status. Processable Blocks will display with selection boxes next to them to mark for processing.

The default time for blocks to be held prior to showing in the holding tank is 30 days, but this number is customizable from the IPAM Configuration page. Regardless of the holding tank days setting, blocks may be manually reset to available at any time.

Two process options are available - "Process Selected", where one or more blocks are manually selected for processing by clicking the checkbox next to the block, and "Process All over X days", which processes all blocks older than the listed days (equal to "Holding Tank Days").

Process Individual Blocks


Select individual blocks to release from holding by clicking the checkbox for the desired block(s), then click "Process Selected".



Process All Blocks


To Process All Blocks meeting the Holding Tank days, click the button "Process All over X days", and all non-pending blocks will be returned to the available block pool.

You may also click the "select all" checkbox at the top left header of the table, ensuring all blocks are selected, then click "Process Selected".



Process Completed

Once the selected block(s) have been processed, a message will display confirming how many IPv4 / IPv6 blocks were successfully returned to the available status.



Pro-Tip!

If you need to do a bulk "empty" of the holding tank, set the "Holding Tank Days" setting to "0" days. This will allow you to process all blocks in holding immediately.

Holding Tank Permissions


For blocks with subassignments, the Holding Tank can utilize ProVision's permissions structure in order to override holding. This allows the subbassigned block to be set as assigned to the parent resource.

Using this feature requires:

1) A block (block 1) assigned to a Resource (Resource A) that allows subassignments.

2) A block (block 2) subassigned to another Resource (Resource B) from the parent (block 1).

3) A User assigned to a Group with permissions to both Resource A and Resource B, and IPAM permissions for the 6connect Holding Resource. See Users and Groups for additional information on setting up Users and Group permissions.



Steps:

1) While logged in as the user with the above permissions, go to the IPAM manage screen for the subassigned block (block 2).

2) Select "Unassign" from the Action Menu. The 'Assigned To' column will change from showing "Resource B" to "Holding"

3) For the same block, select "Override Holding" from the Action Menu. This is the step that setting the 6connect Holding resource permissions allows, that would otherwise be unaccessible.

4) You will then see the 'Assigned To' field change from "Holding" to "Resource A", as the assignment is reverted to match the parent level.

Override Holding through the permissions structure is intended only for blocks that are subassigned. It is not intended for blocks that are not subassigned. Setting holding permissions for non-subassigned blocks simply allows viewing of the block(s) in holding, and permissions do -not- extend to allowing overrides by design.

Additional Information

See the following pages for additional information on IPAM Admin tasks in ProVision:

- IPAM Parameters
- IPAM Rules
- LIR Management and Use

For additional information on non-admin IPAM areas, see:

- IPAM Tab

RIR Integration: SWIP/RPSL

Overview

ProVision supports updating SWIP/RPSL functions for ARIN and RIPE blocks through simple reassigns using the RIR Integration action.

- Overview
  - RIR Integration
    - When do I use RIR Integration and Why?
    - What is Simple Re-assign?
  - Workflow
    - 1) LIR Setup
    - 2) Assign IP blocks to the ARIN or RIPE RIRs
    - 3) RIR Integration
      - ARIN / Update SWIP
      - RIPE / Update RPSL

RIR Integration

When do I use RIR Integration and Why?

From ARIN.net:

Organizations that receive space allocations from ARIN, either directly or as a downstream customer, must provide reassignment information back to ARIN. This information must be sent within seven days of the reassignment so that the WHOIS database may be maintained. ARIN also uses utilization history, projected requirements, and other information in order to make future space allocations.

From RIPE.net:

All RIPE assignments and allocations must be registered in the RIPE Database. This is necessary to ensure uniqueness and to support network operations.
Only allocations and assignments registered in the RIPE Database are considered valid. Registration of objects in the database is the final step in making an allocation or assignment. Registration data (range, contact information, status etc.) must be correct at all times (i.e. they have to be maintained).The RIPE community's policies require LIRs to register an inetnum object in the RIPE Database for their own infrastructure and customers' networks. LIRs must ensure registration information is correct and up to date at all times.

RIPE Integration

⚠ You must be using an MD5 password to update RIPE objects from ProVision! Please refer to RIPE's authentication page for additional details:

https://www.ripe.net/manage-ips-and-asns/db/support/security/protecting-data#solving-authentication-problems

What is Simple Re-assign?

From ARIN.net:

Used to subdelegate IP addresses to a customer that does not need to:

- subdelegate the addresses to their own customers
- maintain their own in-addr.arpa delegation
- display their own point of contact (POC) information.

It can also be used to change the customer name and address information (but not the range) on an existing simple reassignment and to remove simple reassignments. It is submitted by an ARIN Online user account linked to the parent organization's Admin or Tech POC, or the Tech POC for the resource.

Workflow

1) LIR Setup

ProVision supports multiple LIRs (Local Internet Registries) in a single instance. This means that you have the ability to update SWIP/RPSL functions for a given allocation with the LIR information that you wish. LIRs are set up and managed from the IPAM Admin area of ProVision, and thus require Admin level permissions to set up.

While setting up the LIR, the POCs / Contact fields that are filled in will later be used for the RIR Integration.

For detailed step by step instructions, see:

LIR Management and Use

ARIN LIR Setup and Use


RIPE LIR Setup and Use

2) Assign IP blocks to the ARIN or RIPE RIRs

Assign an IP block to a Resource using the IPAM Gadget or the Assign function from the IPAM Manage screen. See Working with IP Blocks for additional detail.

3) RIR Integration

Once LIRs have been configured, and blocks assigned under the applicable RIR, you will be able to use the **RIR integration** feature from the Action Menu on the IPAM Manage screen or IPAM Gadget.




Depending on the RIR associated with the block, either an ARIN or RIPE Integration box will pop up.

ARIN / Update SWIP


Select LIR:

Select the desired LIR, and verify the Net Name / Public Name if desired.



Reassign:

Once the LIR and Handle is selected, you can click either "Simple Reassign", "Detailed Reassign" or "Close" to exit.



For detailed step by step instructions, see:

ARIN LIR Setup and Use

RIPE / Update RPSL

Select LIR:



Select Data Set / Create Inetnum

Identify which LIR data you want to use for the netnum update, and select either "Create Inetnum" or "Close" to exit.



For detailed step by step instructions, see:

RIPE LIR Setup and Use

LIR Management and Use


Overview

ProVision supports multiple LIRs (Local Internet Registries) in a single instance. This means that you have the ability to update SWIP/RPSL functions for a given allocation with the LIR information that you wish.


- Overview
  - LIR Setup and Use
  - Edit a LIR
  - Add a LIR
    - ARIN
    - RIPE
  - RIR Integration

LIR Setup and Use

There is an LIR Manager available from the IPAM Admin page. In the Admin section of ProVision, select the **IPAM Admin** tab, then "LIR Management: Add / Edit / Update LIRs".




You will be taken to the LIR Manager page, showing your current LIRs. You may Add LIRs, edit the existing LIRS by hitting the Action Menu (wrench icon), or delete LIRs through the red delete icon.



Edit a LIR

Edit a LIR by clicking on the Action Menu (wrench icon) next to the entry in the LIR Manager. The Update LIR dialog will open. From here, you can edit RIR, Name, ASN, and Org information, as well as add / delete Orgs.




Add a LIR

After clicking on the **Add LIR** button, you can setup the required data for the specific RIR/LIR combination:

ARIN

Adding a new LIR with ARIN selected for RIR will bring up the following fields.



Enter the Name, ASN, ORG ID, POC information, NET Name Prefix, and API Key. Additional Orgs may be added by selecting the "Add Org" button.

Be sure to click the "Update" button when done to save your changes.

Press UPDATE to SAVE!

Make sure to press the Update button or else the LIR data will not save.


RIPE

Adding a new LIR with RIPE selected for RIR will bring up the following fields.

RIPE Integration

You must be using an MD5 password to update RIPE objects from ProVision! Please refer to RIPE's authentication page for additional details:

https://www.ripe.net/manage-ips-and-asns/db/support/security/protecting-data#solving-authentication-problems



Enter the Name, ASN, Maintainer, Password, and Contact information. Additional Maintainers may be added by selecting the "Add Maintainer" button.


Be sure to click the "Update" button when done to save your changes.

Press UPDATE to SAVE!


Make sure to press the Update button or else the LIR data will not save.

RIR Integration

Once these have been configured, you will be able to use the **RIR integration** feature from the Action Menu on the IPAM Manage screen or IPAM Gadget:



RIR specific options will pop up (see ARIN example below) and give the options for "Simple Reassign", "Detailed Reassign", or "Close" to exit.



For additional detail, continue on to:

- ARIN LIR Setup and Use
- RIPE LIR Setup and Use
- LIR Walkthrough

ARIN LIR Setup and Use

LIR Setup


- LIR Setup
  - Step 1: Setup the LIR information via the LIR Manager
  - Step 2: Assign an IP block to a Resource using the IPAM Gadget or the Assign function from the IPAM Manage screen.
  - Step 3: Update SWIP information
    - Simple Re-assign
    - Detailed Re-assign

Step 1: Setup the LIR information via the LIR Manager

You will be prompted to the select the RIR



Add in the requisite Org and POC information




Multiple Org Support

Note that we support multiple Org Handles per ARIN entry. Simply click on the Add Org link at the bottom of the Add LIR dialog box.


Step 2: Assign an IP block to a Resource using the **IPAM Gadget** or the Assign function from the IPAM Manage screen.

Go into IPAM Manage or the IPAM Gadget, and assign a block. See Working with IP Blocks for additional detail.




Step 3: Update SWIP information

Select "RIR Integration" from the Action Menu in IPAM Manage.




It will bring up an RIR Integration dialog, dependent on the selected RIR (ARIN example shown):



Select the ARIN LIR that has been created in ProVision, and add the Net Name / Registrar Public Name if desired.

Afterwards, you can select the Org Handle and chose "Simple Reassign", "Detailed Reassign", or "Close" to exit.



SWIP Update Functionality Details

In the case when a user already has SWIPped blocks to ARIN, 6connect checks prior to actually performing a SWIP. In the process, if the IP block is already SWIPped, it will check for existing ARIN customer data and update the 6connect data to reflect what ARIN has on file. Once that is complete, the user can then perform a de-SWIP function using ProVision.

Simple Re-assign

From ARIN.net:

Used to subdelegate IP addresses to a customer that does not need to:

- subdelegate the addresses to their own customers
- maintain their own in-addr.arpa delegation
- display their own point of contact (POC) information.

It can also be used to change the customer name and address information (but not the range) on an existing simple reassignment and to remove simple reassignments. It is submitted by an ARIN Online user account linked to the parent organization's Admin or Tech POC, or the Tech POC for the resource.

Detailed Re-assign

From ARIN.net:

Used to subdelegate IP addresses to a downstream organization that does not need to further subdelegate the IP addresses, but does need to maintain its own reverse name servers and/or display separate point of contact (POC) information. It is submitted by an ARIN Online user account linked to the parent organization's Admin or Tech POC, or the Tech POC for the resource.

RIPE LIR Setup and Use

LIR Setup - RIPE

- LIR Setup - RIPE
  - Before you begin:
  - Step 1: Setup the LIR information via the LIR Manager
  - Step 2: Assign an IP block to a Resource using the IPAM Gadget or the Assign function from the IPAM Manage screen.
  - Step 3: Update RPSL information

Before you begin:


RIPE Integration

⚠ You must be using an MD5 password to update RIPE objects from ProVision! Please refer to RIPE's authentication page for additional details:


https://www.ripe.net/manage-ips-and-asns/db/support/security/protecting-data#solving-authentication-problems

Step 1: Setup the LIR information via the LIR Manager

You will be prompted to the select the RIR



Then add in the requisite Maintainer Object related information:




Be sure to hit "Update" when done to save your changes.

Multiple Maintainer Object Support

Note that we support multiple maintainer objects per LIR entry. Simply click on the Add Maintainer link at the bottom of the Add LIR dialog box.


Step 2: Assign an IP block to a Resource using the **IPAM Gadget** or the Assign function from the IPAM Manage screen.

Go into IPAM Manage or the IPAM Gadget, and assign a block under the RIPE RIR. See Working with IP Blocks for additional detail.




Step 3: Update RPSL information

Select "RIR Integration" from the Action Menu in IPAM Manage.



Identify which LIR data you want to use for the netnum update, and select either "Create Inetnum" or "Cancel" to exit.


RIPE Integration 2001:db8::/33 (2001:db8:: - 2001:db8:7fff:ffff:ffff:ffff:ffff:ffff)
6connect TEST
mnt-by
admin-c
tech-c
API Key
MNT-SIXCONNECT-TESTING
LJ1-TEST
LJ1-TEST
MNT-SIXCONNECT-TESTING-SHARED
LJ1-TEST
LJ1-TEST
TEST-DBM-MNT
LJ1-TEST
LJ1-TEST
Create Inetnum
Close

LIR Walkthrough

Create LIRs

Before You Begin


Before you begin, determine who in your organization has access to the RIR API Keys related to the ASNs used by your organization and gather the following data:

For ARIN, you will need to gather data for the ASN, Org ID, Admin/Tech/Abuse POCs, Name Prefix, and API Keys for each ASN.

For all other RIRs, you will need information for the Maintainer, Password, and Admin/Tech Contacts per ASN.


First, go and set up an LIR from Admin **IPAM Admin.**

Click "Add / Edit / Update LIRs"



Complicated or large organizations will likely need many.

Start by Adding a new LIR by clicking "Add LIR" at the bottom of the LIRs List:




At this point, you should have data collected for each RIR/ASN combination used in your organization.

Select the RIR, enter the Name and ASN, and then enter the relevant Org ID / POC / API Key (or Password) for the LIR. Entering the ARIN API Keys for ARIN LIRs is critical for every SWIP action. The API Key contained within an LIR object will be used to authenticate against ARIN's systems when you want to update them.

When you are done, click "Update" to save, and continue to add other LIRs as needed.

An example of how this should look:



We can verify this information by querying the ARIN database, like so:

https://whois.arin.net/rest/org/CONNE-81/pft?s=conne-81 https://whois.arin.net/rest/poc/6CONN-ARIN?s=6conn-arin

Once you have an LIR in ProVision, it is trivial to query the API of its resource from the ProVision database using the resource Id number.

Set up IP Associations

From here, ensure that IP space has been entered into ProVision, along with necessary Contacts and Resources. Associate Contacts with the Resources, and assign IP space to the necessary Resources. See: Resources, Working with Entries, Contact Manager, and Working with IP Blocks.

Ensure that you have followed the following guidelines:

Danger #1: Make sure you own the IP space in question. ARIN knows who is supposed to be administering every bit of IP space under its domain, and you will run into issues if you do not actually own the IP space according to the RIR.

Danger #2: Make sure the IP space is actually assignable with ARIN.

An example of why SWIPs might fail

Lets imagine that 10 years ago some network administrator did a simple assignment with ARIN which noted that a certain /26 was under management by Company A. Since then, that administrator has been fired, the company he worked for has been acquired, that company was then itself acquired, and Company A has gone bankrupt and dissolved.


Today, nobody knows about all this. But ARIN remembers that a certain /26 has been delegated to Company A, and nobody has informed them otherwise. This is a not-uncommon issue.

So today, you come along and you are doing your tests with a /28 which happens to be a sub-block of the /26. You can configure everything correctly and despite that, ARIN will completely refuse to SWIP the /28, because ARIN thinks that the /28 is part of a /26 which is already SWIP'd.

To make matters worse, ARIN won't tell you why it is refusing to SWIP the /28 -- it will just tell you its invalid. The only way to debug this situation is manually probe the ARIN database until you find the already-SWIP'd block, construct this block in ProVision, try to SWIP it (and fail, because it is already SWIP'd), then de-SWIP it, clearing the erroneous state both from ProVision and from ARIN. Due to a lack of access to the ARIN database, ProVision is limited in its methods of handling situations such as these.

SWIP

We've got everything together so let's do some SWIP'ing. Our happy candidate is 67.221.244.160/27, which is a slice of 6connect's very own domain. Screenshot from ARIN:



From here we can see that the /27 is currently undivided as far as ARIN is concerned. ARIN's database is arranged in a hierarchy, so it first looks to see if that /27 exists in its

database (nope), then it looks for blocks it *does* know about it which contains it. Here we see 6connect's /20 as its immediate owner:


https://whois.arin.net/rest/net/NET-67-221-240-0-1

And ARIN's own base allocation as the next-highest owner:


https://whois.arin.net/rest/net/NET-67-0-0-0-0

The story of this block is therefore: "ARIN was given this IP Block by ICANN, then ARIN did a Direct Allocation of a /20 to 6connect." And in a bit here, 6connect will do a detailed re-assign to MedaTeckle, a made-up company whose headquarters is the birthplace of Genghis Khan.

Here is my resource:




And here are the contacts:




Having someone in the 'ARIN-NET' and the 'ARIN-ADMIN' roles is required for a Detailed Reassign. As I mentioned with Joe earlier, it is currently not possible to have a single Contact with both roles, so you'll need two.

Here is the last piece, our IP block:



So I open up the wrench menu for the IP block right here on the Resource page and I get this screen:



I select the LIR in the upper-left (currently selected: 6connect), the Net Name is automatically generated from the LIR + netblock, and we are using the "CONNE-81" organization within the 6connect LIR. This will supply the ARIN API Key to make this all happen. I hit Detailed Reassign and after a few minutes of waiting for ARIN to catch up, here are the results:



Our /27 has been delegated to our new fake company, here:

https://whois.arin.net/rest/net/NET-67-221-244-160-1

A new ARIN entry for the fake company has been automatically made:

https://whois.arin.net/rest/org/MEDAT-1.html

https://whois.arin.net/rest/org/MEDAT-1.html


And the relevant Points of Contact have been generated:

https://whois.arin.net/rest/org/MEDAT-1/pocs

This lets everyone know that if issues arise with that / 27, they know who to contact to resolve the issue.

DNS Administration

DNS Administration



DNS Administration in DNSv3 is primarily handled under the **DNS** tab **DNS Servers** sub-tab, with DNS Administrative settings available under the Admin Preferences page.

The **DNS Servers** tab is only accessible to Admin users, and contains functions for adding, updating, and managing DNS servers as well as scheduling server tasks.

Additional DNS Admin tasks occur in other ProVision areas, and not all management tasks require Admin-level permissions - some only require appropriate resource permissions on the DNS Groups, Zones, and servers involved. See additional sections on this page for more detailed information:

- DNS Administration
  - DNSv3 Overview
    - DNSv3 Permissions
      - Permission Shortcut Button ("Perms")
    - DNS Approvals
    - DNSv3 Administrative Tasks
  - Manage DNS Servers
  - ACLs / Views
  - DNS Zone Transfers (Pushes)
    - Manual DNS Pushes:
    - Scheduled DNS Pushes:
  - DNS Record Types
  - Global DNS Settings (Local Installation Only)
    - DNSSEC Settings:
    - DNS Dynamic Update Settings
    - DNS Backup Settings
    - DNS Import Settings
  - DNS Export Functions
    - Exporting Zones
  - Importing DNS Zones:
  - Additional Information:
    - System Information for Local Installations
    - Additional Sections:

DNSv3 Overview

DNSv3 reorganizes ProVision's DNS system into a more unified and accessible interface, combining both admin and non-admin DNS tasks together under the **DNS** tab.

In DNSv3, zones are gathered under DNS Groups, servers are attached to those Groups, and Nameservers, Default SOA values, and ACLs are managed at a per-Group level.

Users can then view and manage Groups, individual zones, default SOA values, ACLs, attach servers, and perform pushes all on the same page.

DNSv3 Zone Name Response Change

Note: In DNSv3, zone name responses will enforce and return a trailing period (i.e., "example.com" will be converted and returned as "example.com.").

DNSv3 is designed to reflect RFC 1035 standards for valid data formats and will return error messaging for data not meeting those formats.

DNSv3 Permissions

DNSv3 incorporates DNS zones and Groups into ProVision's Resource System. Zones and Groups are Resources just like Customers, Servers, Routers, or Contacts (See The Resource System for a more detailed explanation of Resources in ProVision).

This allows for DNS zones and Group permissions to be managed similarly to other ProVision resources, where users with Resource permissions (Create / Read / Update / Delete) on the parent resource of the DNS Group can create groups and zones, manage those groups and zones, push (if a server is attached), and delete.

A user with full Resource permissions on a DNS Server, as well as the parent resource of a Group, may view and attach that server to a Group.

Users with Admin permissions can access the **DNS Servers** area under the **DNS** tab manage DNS server creation, edits, and deletion.

For more information on setting up permissions groups in ProVision, see Users & Permissions.

Permission Shortcut Button ("Perms")


Throughout DNS, a shortcut permissions button ("Perms") is available on a per-item level, accessible only to Admin users.

This permissions button allows for direct, point-of-use permissions adjustments to DNS Groups, Servers, Zones, and Records. It uses the same CRUD permissions and groups available in the Admin Users tab, but removes the need to remember and search for the DNS item name.

To open the Change Resource Permissions module, click on the "Perms" Button for any DNS item.



Edit the CRUD permissions for any ProVision user group by clicking the checkbox for the desired group and permission type. When done, click "Save Changes". The permission changes will be also be reflected in the Admin **User** tab Group settings.




DNS Approvals

The Approvals module stores and queues DNS actions made by selected User Groups, and sends those actions to a Pending Changes list for administrative review. Later, an administrator (or combination of administrators) can approve or reject these stored actions.

Approvals is primarily set up and managed via the Admin **Approvals** Tab. See the ProVision Admin Guide - Approvals Tab for details on setting up and using Approvals from the Administrative viewpoint.

In the **DNS** Tab, a "Resources Awaiting Approval" module will display near the top of DNS Groups, DNS Zone Lists, and DNS Servers pages, if a change has been submitted on that page that is pending approval.



Users who submitted a change for approval will see the details of their change request in this module.

Admin users with permissions to approve or reject the request will have the option to Approve or Deny the change.

DNSv3 Administrative Tasks

Admin-only tasks in DNSv3 include setting DNS Globals, importing zones, scheduling pushes, managing DNS Servers, and managing DNS Approvals.

These tasks may be accessed in the following areas:

- DNS Global Settings: Admin Preferences page.
- Importing DNS Zones: the **Data Import** tab, see Import DNS Zones.
- Scheduling DNS Pushes:
    - May be set up from the Scheduler Tab or,
    - Set by server from the **DNS Servers** page, or
    - Set by DNS Group from the **DNS Groups** page, or
    - Set by individual zone from the View Zone page
- Managing DNS Servers: The **DNS Servers** page
- Approvals: The Approvals Tab.

Tasks such as working with zones, DNS Groups, adding ACLs, attaching servers to Groups, and manually pushing zones do not require ProVision Admin permissions.

Instead, these tasks simply require that the user be included in a User Group that has appropriate permissions (either direct, or inherited) on the DNS zones, Groups, and servers involved.

Manage DNS Servers

Adding, configuring, and managing DNS Servers occurs in the Admin-only **DNS Servers** page under the **DNS** Tab.

Supported DNSv3 server types include:


- ISC BIND
- Secure 64 (Authority, x86 Authority, KNOT Authority, Cache, Signer)
- PowerDNS (BIND and MySQL)
- InfoBlox
- Knot DNS
- NS ONE
- DynDNS (Beta)
- DNSMadeEasy
- AWS Route53 (Beta)
- Dummy (a fake server entry used for servers outside of ProVision access, in order to manage master / slave configurations)

Some server types may require outside subscriptions or accounts.

For detailed information on adding, editing, and deleting DNS Servers, see Working with DNS Servers.

ACLs / Views

In DNSv3, Views may be created by selecting the "Export Groups as Views" toggle and selecting a DNS Group under the server details sections "DNS Group Settings".



ACLs are managed on a per-DNS Group level, and may be added, edited, or removed by any user with appropriate resource permissions on the DNS Group.



For details on working with ACLs, see Configuring Split Horizon/Views.

DNS Zone Transfers (Pushes)

In DNSv3, zones may be pushed manually or scheduled for a future time, and may be performed for a single zone, all zones in a DNS Group, or all zones on a server.

Scheduling DNS pushes requires administrative access, but manual pushes only require permissions on the DNS Group / DNS Zone, and the server(s) attached.

Manual DNS Pushes:

Manual pushes may be performed from the following locations in ProVision:

- Single Zone: From the DNS Groups Zone list "Push" button. See Working with DNS Zones - Pushing Zones
- Single Zone: From the DNS View Zone page "Push Zone Now" button. See Working with DNS Zones - Pushing Zones
- Group: From the DNS Groups Zone list "Push Group" button. See Working with DNS Groups - Pushing a Group
- Server: From the DNS Servers list "Push" button. See Working with DNS Servers - Pushing a server
- Server: From the DNS Server Settings page "Push Zones" button. See Working with DNS Servers - Pushing a server

Scheduled DNS Pushes:

Scheduled pushes may be performed from the following locations in ProVision:

- May be set up from the Scheduler Tab for single zones, all zones in a Group, or all zones on a server.
- Set by server from the **DNS Servers** page, or
- Set by DNS Group from the **DNS Groups** page, or
- Set by individual zone from the View Zone page

DNS Record Types

DNSv3 Record Types are a static list comprised of:


- A, AAAA, CNAME, DNAME, DNSKEY, DS, MX, NAPTR, NS, PTR, SOA, SRV, SPF, HINFO, TXT.

Any user with appropriate resource permissions on the DNS Zone / DNS Group may add, edit, or delete DNS Records.

See Working with DNS Zones for detailed information on managing DNS Records.

Global DNS Settings (Local Installation Only)

DNS Global Settings is accessible from the Admin Preferences page by users with Admin level permissions.



DNSSEC Settings:


If using DNSSEC, select whether to enabled DNSSEC local signing, or sign zones by dnssec-tools, then enter the following information:

zonesigner path : Enter the zonesigner path that will be used for DNS. Zonesigner is required if dnssec-keygen and dnssec-signzone are not set.

Sign zones by ISC BIND Utilities: Select whether to use ISC BIND utilities to sign zones.


dnssec-dsfromkey path : Enter the dnssec-dsfromkey path that will be used for DNS. Required in all cases.

DNS Dynamic Update Settings




Dynamic Update via nsupdate: Toggle to "On" if you wish to use Dynamic Updates via nsupdate, instead of ProVision's internal implementation.

DNS Backup Settings



Records Limit : The limit for the number of records a zone may have for a zone to process a backup. If the records count exceed this number, zone backups will be omitted at zone push.

DNS Import Settings



Keep Import File: Saves DNS zone import files to the zone's "Zone Backups and Attached Files" area, for later download. Optional.

DNS Export Functions

Exporting Zones

Individual Zones:

DNS zones may be exported individually from the zone's View Zone page "Export Zone" button, by any user with appropriate zone permissions (see: DNS Zones Overview).

Zones in a DNS Group:

All zones under a DNS Group may be exported from the DNS Group "Export Zones" button, by any user with the appropriate group permissions (see: Working with DNS Groups).

Zones directly connected to a server:

Zones directly connected to a server may be exported by Admin users from the DNS Server Details page, under the section "Zones connected directly to the server".

Expand the module by clicking the (>) arrow, and then click the "Export Zones" button.



Importing DNS Zones:

ProVision offers six DNS zone import options, available under the **Data Import** tab in the Admin section. For more information on importing DNS zones, see Importing your Data and Import DNS Zones.

BIND Zone Upload / Import: Imports DNS zones using the named.conf configuration file tied to the zones you are uploading, a .zip or .tar file of the zones themselves, and an optional .csv file mapping zones to customers and DNS Servers. This is the simplest and most commonly used import method. Refer to Import DNS Zones for more information.

PowerDNS Zone Import: This tool is available after configuring a PowerDNS server with a MySQL backend. The PowerDNS Import connects to the selected server and imports all zones.

InfoBlox Zone Import: Imports DNS zones using a provided Host, Username, and Password. The InfoBlox import pulls all zones on the InfoBlox LOCAL grid and adds them to a designated Group. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

NS ONE Zone Import: Imports DNS zones using a NS One API Key. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

Dyn DNS Zone Import: Imports DNS zones using a Dyn DNS Customer Name, Username, and Password. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.


DNSMadeEasy Zone Import: Imports DNS zones using a DNSMadeEasy API Key and API Secret. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

IPPlan Zone Import: Imports DNS zones using IPPlan MySQL database options. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.


Additional DNS import options may be available on a per-zone or per-server level, accessed from the **DNS** Tab:

DNS Zone Import: This tool is available on a zone's "View Zone" page, and allows the user to import additional zone/record information into an existing ProVision zone by uploading a zone file (.zone).

- From the View Zone page, a zone file (.zone) may be imported into a ProVision zone to populate record data. Click "Import Zone".



A Zone Import dialog box will open. Next to **Zone File:**, click "Choose File" and select your .zone file to import. Then, select an import policy to follow.



When done, Click "Import Zone".

Additional Information:

System Information for Local Installations

Zones are stored in the 6connect web root under /zones.

DS keys are stored in the 6connect web root under /keys.

Global DNS Settings may be set from the Admin Preferences page.

Additional Sections:


For more information on DNS and configurations, see the following sections:

- Working with DNS Servers
- Configuring ISC BIND Support
- Configuring PowerDNS Support
- Configuring Secure64 Support
- Configuring Route53 Support
- Configuring Split Horizon/Views
- Configuring DNSSEC

Working with DNS Servers

DNS Servers


ProVision's DNSv3 combines server management, group organization, and zone management under the **DNS** tab.



The **DNS Servers** tab is only accessible to Admin users, and contains functions for adding, updating, and managing DNS servers as well as scheduling server tasks.

- DNS Servers
  - DNS Server List Interface
- Working with DNS Servers
  - Add a Server
    - Server Settings
      - 1) Set Server Common Settings
      - 2) Set Server Specific Settings
      - 3) Set DNS Group Settings for Server
      - 4) Save Changes
  - Edit Servers
  - Review Zones Connected to a Server
    - Zones Directly Connected to the Server
    - Zones Connected via a Group
  - Pushing a Server
    - Manual Push
    - Scheduled Push
  - Delete a Server
- Additional Information

DNS Server List Interface



1) Add Server Button: Opens a dialog for creating a DNS server.

2) Server List:


3) Server Name: Name of the DNS server. Click to open server details.

4) Server Backend: The DNS Service backend type for the server.

5) Server Type: Whether the server is a master or slave type.

6) Server Status: Currently a placeholder column for future display of server error and connection status messages.

7) Actions: The actions that may be performed on each server:



8) Delete: Deletes the server from ProVision.


9) Push: Pushes all zones associated with the selected server.

10) Perms: Opens a shortcut to edit permissions for the selected server.

Working with DNS Servers

Add a Server

To create a new server, start from the **DNS** Tab, select the **DNS Servers** sub menu. Then, click the "Add Server" button next to "DNS Server List".




This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, service type, and desired parent Resource (may be left at the default Top Level Resource).



Display Name: Name you want the server to display.

FQDN or IP: The FQDN or ip address of the DNS server.

Default: Specify if the server should be added to new zones by default or not.

Server Type: Specify if the server is a master or slave. Different configuration files are created master vs. slave on the Bind, PowerDNS /Bind, and Secure64 platforms.

DNS Service: Select the DNS service type (ISC Bind, Secure64, KnotDNS, etc).


Parent Resource: Select the ProVision resource to be the "parent" of the server - typically TLR (Top Level Resource), but may be a lower level resource such as a Customer or Location. The parent resource selection is the basis of access permissions for the server.

2) Set Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DNS Service" type chosen under "Common Settings".

Here, we see the fields for ISC BIND server settings. Enter the server Username, Password, Port, Remote Director, Named Conf. Path, and Pre /Post Command (if desired). Your fields may vary for other server types.

For SSH Public Key Authentication, DNSSEC, and Dynamic Option updates, click on the ON / OFF toggle to select "ON" or "OFF" for each as needed.



SHH Public Key Authentication: If applicable, toggle "On" or "Off"

Username: Login/username for the target DNS server. The specified account needs to be valid, and have write permission to the remote directory and execute permission for any pre/post commands.

Password: Password for the target account. All passwords are stored encrypted in the database.

Port: Port to contact the target server on. This is port used for SSH on Bind and Secure64 server types.

Remote Directory: The target directory to transfer zone files to on the DNS system.

Named Conf Path: The path to other zones on the Bind systems.

Pre Command: Any valid system command on the target DNS system. This command will be run before any files are transferred.

Post Command: Any valid system command on the target DNS system. This command will be run after any files are transferred. For example, on a Bind system you would need to run "rndc reload" to reload the zones.

Enable DNSSEC: If available for the server type, toggle to "On" or "Off". See Configuring DNSSEC for additional information.

Enable Dynamic Updates: Toggle to "On" or "Off", if the server allows dynamic updates.

Some DNS Server types use subscription services or outside accounts, in which case you may instead be prompted to provide account credentials, API keys, API secret, or other vendor-specific fields to connect to the service.

After entering the server-specific settings in this section, you can click the "Test Server" button at the top of the section to test the server connection and authentication.

The "Test Server" button will attempt to login to the target system and write to the target directory.




A window will pop up showing a success or failure response.

If any failures are encountered, an error will be written with some detail. If the test is successful, the word "Success!" will show verifying that files can be transferred. This does not test if the user can execute pre/post commands. This needs to be checked manually.




3) Set DNS Group Settings for Server

In the last section, select whether to enable Multiple Groups Support for exporting Groups as View (click to toggle ON / OFF), and select a default Group, if desired, to be associated with the server. Zones assigned to the selected Group will automatically be attached to the server.



4) Save Changes


Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.




The new server will now be added to the DNS Servers list. These settings may be changed at any time by selecting the server from the server list and editing the information.

Edit Servers


Edit an existing server by clicking once on the server name in the DNS Servers list.



The "Server Settings" page will open.



Click inside the field that you want to change, type your changes, and then click "Save Changes" at the bottom of the page.



Review Zones Connected to a Server

There are two ways that zones may be connected to a DNS server:

1) Directly connected, by attaching the zone to a server from the View Zone page.

or,

2) Connected by a Group that has been set as the default DNS Group for the server, selected under "DNS Group Settings".

Both are able to be viewed on the DNS Server Settings page.

To view either, open the Server Settings page for the server by clicking on the server name in the DNS Servers list.


Edit an existing server by clicking once on the server name in the DNS Servers list.



The "Server Settings" page will open.


Zones Directly Connected to the Server

Scroll to the bottom of the page, and open the module titled "Zones directly connected to the server" by clicking on the expansion arrow.



A zone list will show the zone(s) that have been directly connected to this server.

Here, you may browse through forward and reverse zones by selecting the "Forward Zones" or "Reverse Zones" tabs, sort the list by Zone Name or Last Modified, open the zone's page by clicking on the name, or check the zone's status by clicking the "Check" button.




Zones may be exported by clicking the "Export Zones" button.

Zones Connected via a Group


If a default Group has been selected under "DNS Group Settings" for the server, Zones under that Group will be connected to the server and able to be viewed on the Server Settings page.

Scroll to the bottom of the page, and open the module titled "Zones connected to Group '(Group Name)' " by clicking on the expansion arrow.



A zone list will show the zone(s) that connected to this server via a selected Group.

Here, you may browse through forward and reverse zones in that Group by selecting the "Forward Zones" or "Reverse Zones" tabs, sort the list by Zone Name or Last Modified, open the zone's page by clicking on the name, or check the zone's status by clicking the "Check" button.



Pushing a Server

Manual Push


Manually pushing all zones on a server may be done directly from the DNS Server list. Under the "Actions" section of the Server List, click the "Push" button for the desired server.



Pushing may also be done while in the Server Settings page. While in the Server Settings page, click the "Push Zones" button at the top right of the page.



A "DNS Push Status" box will appear, showing the status of each zone as it is pushed. Once all zones have been pushed successfully, a green status message of "Finished DNS Pushing Request" will appear. At this point, the push is complete and the window may be closed.



Scheduled Push


DNS server pushes may be scheduled from either the Admin Area **Scheduler** Tab, or from within the DNSv3 Server Settings page. Scheduled pushes require Admin access.

For information on scheduling a push from the **Scheduler** Tab, see Scheduler Tab documentation.

To schedule a push from a server's Settings page, open the Server Settings page for the desired server, and click on the "Schedule Push" button.




The Push Scheduler dialog will open. Click on the calendar on the left to select a date for the push, set the desired push time on the right, enter a notification email address, and then click "Save Changes".




Once a schedule push has been created, a "Scheduled Tasks" module will appear at the top of the Server Settings page.

Click on the expansion arrow for the module to open and view the tasks.



Scheduled pushes for the server will be listed in the "Scheduled Tasks" module, and may be viewed or deleted (by clicking the "Delete" button under "Actions").



If necessary, the Scheduled Push may be edited from the **Scheduler** Tab in the Admin area of ProVision. See the Scheduler Tab for information on editing scheduled tasks.

Delete a Server

Delete a server by clicking the "Delete" button under the "Actions" section of the Server List for the desired server.



Additional Information

For additional information on working in DNS, see the following sections:

- Configuring ISC BIND Support
- Configuring PowerDNS Support
- Configuring Secure64 Support
- Configuring Split Horizon/Views
- Configuring DNSSEC
- Import DNS Zones
- DNS Tab

Configuring ISC BIND Support

Configuring ISC BIND Support

- Configuring ISC BIND Support
  - Getting Started
  - Adding a BIND Server to ProVision
    - Server Settings
      - 1) Set Server Common Settings
      - 2) Set Server Specific Settings
      - 3) Set DNS Group Settings for Server
      - 4) Save Changes
- Additional Information

Getting Started

BIND Version Compatibility

BIND 9 Support is officially supported. Please note that as of May 24, 2018, ISC implemented a different release numbering scheme. From the ISC BIND 9.13 release notes (https://kb.isc.org/article/AA-01612):

Previously new feature development releases were tagged as "alpha" and "beta", leading up to the first stable release for a given development branch, which always ended in ".0".

Now, however, BIND has adopted the "odd-unstable/even-stable" release numbering convention. There will be no "alpha" or "beta" releases in the 9.13 branch, only increasing version numbers. So, for example, what would previously have been called 9.13.0a1, 9.13.0a2, 9.13.0b1, and so on, will instead be called 9.13.0, 9.13.1, 9.13.2, etc.

The first stable release from this development branch will be renamed as 9.14.0. Thereafter, maintenance releases will continue on the 9.14 branch, while unstable feature development proceeds in 9.15.

You will need a user who can log in to the DNS server and make changes to the directory in which the zones are being stored. Additionally, it is often useful for this user to have the ability to restart the DNS server. The login and password for this user will be required to configure this server on the DNS Admin page.

6connect Zone files are written out in the following format:

/path/to/zone/directory/viewName/zoneFirstLetter/zonefile.zone

If no views are configured, or if views are expressly disabled, then the default viewName "6connectGeneric" is used. The zoneFirstLetter is the first letter of the zone name, so the subdirectory 'microsoft.com.zone' is placed in would be /m/.

All 6connect-managed Zones are managed by a dedicated 6connect configuration file named 6connect_named.conf. This file is created to act a supplementary conf file to work in concert with any existing named.conf which might exist. To include the 6connect configuration file, edit named.conf and append the following line:


include "/path/to/conf/directory/6connect_named.conf";

You must remember to include the 6connect configuration file or none of the changes managed by 6connect ProVision will take effect!

It is also important to note that if your existing named.conf file contains zones within Split Horizon views, then the 6connect-managed zones must also be view-enabled. Likewise, if existing zones are not grouped into views, then views must be disabled on ProVision.

Adding a BIND Server to ProVision

To create a new server, start from the **DNS** Tab, select the **DNS Servers** sub menu. Then, click the "Add Server" button next to "DNS Server List".




This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, service type, and desired parent Resource (may be left at the default Top Level Resource).




2) Set Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DNS Service" type chosen under "Common Settings".

Here, we see the fields for ISC BIND server settings. Enter the server Username, Password, Port, Remote Director, Named Conf. Path, and Pre /Post Command (if desired). Your fields may vary for other server types.

For SSH Public Key Authentication, DNSSEC, and Dynamic Option updates, click on the ON / OFF toggle to select "ON" or "OFF" for each as needed.



After entering the server-specific settings in this section, you can click the "Test Server" button at the top of the section to test the server connection and authentication.




A window will pop up showing a success or failure response.




3) Set DNS Group Settings for Server

In the last section, select whether to enable Multiple Groups Support for exporting DNS Groups as Views (click to toggle ON / OFF), and select a default Group, if desired, to be associated with the server. Zones assigned to the selected Group will automatically be attached to the server.



4) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.



The new server will now be added to the DNS Servers list. These settings may be changed at any time by selecting the server from the server list and editing the information.

Additional Information

For additional information on working in DNS, see the following sections:

- Working with DNS Servers
- Configuring PowerDNS Support
- Configuring Secure64 Support
- Configuring Split Horizon/Views
- Configuring DNSSEC
- Import DNS Zones
- DNS Tab

Configuring PowerDNS Support

Configuring PowerDNS Support


- Configuring PowerDNS Support
  - Environments supported
  - Step 1: Add a PowerDNS Server
    - Server Settings
      - 1) Set Server Common Settings
      - 2) Set Server Specific Settings
      - 3) Set DNS Group Settings for Server
      - 4) Save Changes
  - Step 2: Import PowerDNS Zones
  - Step 3: Push zones to PowerDNS
  - BIND Backend
  - MySQL Backend
- Additional Information

Environments supported

- PowerDNS version 3.0 or above on the target server(s)
- BIND or MySQL backend

Step 1: Add a PowerDNS Server

To create a new server, start from the **DNS** Tab, select the **DNS Servers** sub menu. Then, click the "Add Server" button next to "DNS Server List".




This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, DNS service type, and desired parent Resource (may be left at the default Top Level Resource). For PowerDNS servers, ensure that either "PowerDNS BIND" or "PowerDNS MySQL" is selected under DSN server type.




2) Set Server Specific Settings


The next section is entering server service-type specific settings. The options visible in this section will depend on the "DNS Service" type chosen under "Common Settings".

Here, we see the fields for PowerDNS BIND server settings. Enter the server Username, Password, Port, Remote Director, Named Conf. Path, and Pre/Post Command (if desired). Your fields may vary for other server types.

For SSH Public Key Authentication, DNSSEC, and Dynamic Option updates, click on the ON / OFF toggle to select "ON" or "OFF" for each as needed.



After entering the server-specific settings in this section, you can click the "Test Server" button at the top of the section to test the server connection and authentication.




A window will pop up showing a success or failure response.




3) Set DNS Group Settings for Server

In the last section, select a default Group to be associated with the server. Zones assigned to the selected Group will automatically be attached to the server.



4) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.




The new server will now be added to the DNS Servers list. These settings may be changed at any time by selecting the server from the server list and editing the information.

Step 2: Import PowerDNS Zones

While in the **Admin** section, navigate to the **Data Import** Tab. Select the "Power DNS Zone Import" link.

To import your data, simply choose your PowerDNS server and click "Import".



Step 3: Push zones to PowerDNS

Navigate back to the **DNS** tab, and select the "**DNS Servers**" tab.

Locate the PowerDNS server in the DNS Servers list, and then click the "Push" button under "Actions" at the end of the row.



BIND Backend

Note on SSH

The integration does not require a remote database connection, but it does require an SSH account and a writable directory. The SSH account must have access to the server. This account will also be used for DNSSEC functionality within PowerDNS.

MySQL Backend

Note on SSH

The integration requires a remote database connection, so will need a mysql user with permissions for remote administration. We highly recommend using ACLs to ensure that configuration only occurs from intended sources.

For DNSSEC functionality, you will need a standard SSH user account withing your PowerDNS user group

Please note that Views are not supported with the MySQL backend
Only BIND and MySQL backends are supported.

Additional Information

For additional information on working in DNS, see the following sections:

- Working with DNS Servers
- Configuring ISC BIND Support
- Configuring Secure64 Support
- Configuring Split Horizon/Views
- Configuring DNSSEC
- Import DNS Zones
- DNS Tab

Configuring Secure64 Support

Configuring Secure64 Support

- Configuring Secure64 Support
  - Step 1: Create an nsd.conf file under the root directory / of your S64 Auth server
  - Step 2: Make a directory for 6connect ProVision to push zone files to on the Secure64 DNS Server
  - Step 3: Setup and Configure 6connect ProVision for your Secure64 DNS Server
    - Server Settings
      - 1) Set Server Common Settings
      - 2) Set Server Specific Settings
      - 3) Set DNS Group Settings for Server
      - 4) Save Changes
  - Step 4: Associate zones to your Secure64 DNS Server(s)
  - Step 5: Push Zones to Secure64 Server(s)
  - Step 6: Verify DNS Zone push on Secure64 Server(s)
  - Step 7: Validate Zone data in Your Infrastructure
- Additional Information

A note on Ports



ProVision uses port 22 to communicate with and configure Secure64 infrastructure - please ensure that this is addressed in any ACLs/firewalls

ProVision also uses port 53 to do zone checks if the DNS Module is enabled and in use. Please ensure that your Secure64 infrastructure is configured to accept DNS lookups from the ProVision server

The initial setup of the Secure64 Authoritative server is as follows:

Step 1: Create an nsd.conf file under the root directory / of your S64 Auth server

DO THIS



Make sure to add the line include: 6connect_nsd.conf to the nsd.conf file

Output/Input

```
[authdnsadmin@Secure64DNS]# cat nsd.conf
server:
ip-address: 50.198.192.141

axfr-logfile: /axfr_log/axfr.log
axfr-logfile-flush-count: 1
axfr-logfile-max-size: 100000
axfr-logfile-max-size: 10

request-logfile: /request_log/request.log
request-logfile-flush-count: 10
request-logfile-max-size: 1000000
request-logfile-max-files: 10


include: 6connect_nsd.conf
```

Step 2: Make a directory for 6connect ProVision to push zone files to on the Secure64 DNS Server

```
[authdnsadmin@Secure64DNS]# mkdir test12
[authdnsadmin@Secure64DNS]# ls
/:
322 2013-08-19 06:07:42 nsd.conf
<DIR> 1024 2013-08-16 17:30:12 test12
```

Step 3: Setup and Configure 6connect ProVision for your Secure64 DNS Server

To create a new server, start from the **DNS** Tab, select the **DNS Servers** sub menu. Then, click the "Add Server" button next to "DNS Server List".




This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, DNS service type, and desired parent Resource (may be left at the default Top Level Resource). For Secure64 servers, ensure that DNS Service is set to "Secure64 Authority", "Secure64 x86 Authority", "Secure64 KNOT Authority", or "Secure64 Cache".




2) Set Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DNS Service" type chosen under "Common Settings".


Here, we see the fields for Secure64 server settings.

Enter the server Username, Password, Port, Remote Directory, Named Conf. Path, and whether to enabled SNMP.

For SSH Public Key Authentication and Dynamic Option updates, click on the ON / OFF toggle to select "ON" or "OFF" for each as needed.



After entering the server-specific settings in this section, you can click the "Test Server" button at the top of the section to test the server connection and authentication.




A window will pop up showing a success or failure response.




3) Set DNS Group Settings for Server

In the last section, select whether to enable support for exporting DNS Groups as Views (click to toggle ON / OFF), and select a default Group, if desired, to be associated with the server. Zones assigned to the selected Group will automatically be attached to the server.



4) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.




Step 4: Associate zones to your Secure64 DNS Server(s)

If a default Group was selected while setting up the S64 server, then any zones in that Group will automatically be associated with the server.

Zones may be manually added, moved, or imported into the Group - see Working with DNS Zones and Working with DNS Groups for details on associating zones with Groups.

If zones are to be imported, a DNS Group may be selected during the import process to associate with the zones.



Select the group specified as the default S64 server Group, then import the zones as described in the Import DNS Zones documentation.

Step 5: Push Zones to Secure64 Server(s)

Navigate back to the **DNS** tab, and select the "**DNS Servers**" tab.

Locate the Secure64 server in the DNS Servers list, and then click the "Push" button under "Actions" at the end of the row.



Step 6: Verify DNS Zone push on Secure64 Server(s)

The result of the Push can be checked/verified by checking the Secure64 server as follows:

Verifying Zone pushes

ssh to 50.198.192.141
Login using the designated login account and password
Enable cachednsadmin
ls

Now, verify that the "788 2013-08-21 12:35:04" 6connect_nsd.conf file now exists.

```
[authdnsadmin@eval138.secure64.com]# ls
/:
6728 2013-08-13 00:15:30 nsd.conf
8416071 2013-08-21 12:35:07 nsd.db
788 2013-08-21 12:35:04 6connect_nsd.conf
<DIR> 1024 2013-08-21 12:34:50 test12
```

You can verify the Push contents by doing a cat of the 6connect_nsd.conf

[authdnsadmin@Secure64DNS]# cat 6connect_nsd.conf

AutoGenerated by 6connect ProVision. Do not manually edit.

zone:

name: atestzone.com

zonefile: /test12/6connectGeneric/m/atestzone.com.zone

zone:

name: Testzone2.com

zonefile: /test12/6connectGeneric/m/Testzone2.com.zone

In the example above, two Zones have transferred.

To look at the contents of each zone you can cd to the proper directory /test12/6connectGeneric and find the zone files in an alphabetical directory structure as follows:

```
[authdnsadmin@Secure64DNS]# cd 6connectGeneric
[authdnsadmin@Secure64DNS]# cd test12

changed to test12
[authdnsadmin@Secure64DNS]# ls
/test12/:
<DIR> 1024 2013-08-16 19:43:21 6connectGeneric
[authdnsadmin@Secure64DNS]# cd 6connectGeneric
changed to 6connectGeneric
[authdnsadmin@Secure64DNS]# ls
/test12/6connectGeneric/:
<DIR> 1024 2013-08-16 17:30:13 e
<DIR> 1024 2013-08-16 17:30:16 m
<DIR> 1024 2013-08-16 18:49:21 d
<DIR> 1024 2013-08-16 19:43:23 s
[authdnsadmin@Secure64DNS]# cd m
changed to m
[authdnsadmin@Secure64DNS]# ls
/test12/6connectGeneric/m/:
[authdnsadmin@eval138.secure64.com]# ls
5192 2013-08-21 15:35:01 atestzone.com.zone
6758 2013-08-21 15:35:02 Testzone2.com.zone
[authdnsadmin@Secure64DNS]#
```

Step 7: Validate Zone data in Your Infrastructure

Finally, do a **dig** of the zones to verify the DNS configuration has been successfully deployed.

Using dig to validate your Secure64 Server installation

```
[authdnsadmin@eval138.secure64.com]# dig @50.198.192.141 atestzone.com
; <<>> DiG SourceT 3.x <<>> @50.198.192.141 atestzone.com
;; Got answer:
;; ~~>>HEADER<<~~ opcode: QUERY, status: NOERROR, id: 59591
;; flags: qr aa rd; QUERY: 1, ANSWER: 0, AUTHORITY: 1, ADDITIONAL: 0
;; QUESTION SECTION:
;atestzone.com. IN A
;; AUTHORITY SECTION:
atestzone.com. 3600 IN SOA ns1.dns.6connect.net. hostmaster.6connect.net. (2013082102 10800 3600 604800 38400 )
[authdnsadmin@eval138.secure64.com]#
```

For any questions regarding the integration of Secure64 products into 6connect ProVision, please email 6connect at support@6connect.com, or Secure64 at support@secure64.com

Changing Secure64 Server IP addresses

When you setup ProVision to communicate via SSH to a Secure64 server, a ley/fingerprint is saved to the local hosts file. If you modify the IP address, but do not clear out the hosts file, then ProVision will think this is an attack and prevent communication with the Secure64 server.

To rectify this issue, you may need to reset the host file so that a new SSH host key can be added for the IP address. To do this manually, please follow the following steps:

1) The admin needs to login to the ProVision server via SSH/CLI
2) Open the file “known” in the /tmp folder in your preferred editor (vi, etc.)
3) Delete the line in the file with the server IP/fingerprint
4) Save the changes and exit the editor

To verify the functionality - attempt to connect to the DNS Server(s) using the “Test Server” button from the ProVision GUI

If you have any issues, please contact 6connect support per your Support Agreement/Plan.

Additional Information

For additional information on working in DNS, see the following sections:

- Working with DNS Servers
- Configuring ISC BIND Support
- Configuring PowerDNS Support
- Configuring Split Horizon/Views
- Configuring DNSSEC
- Import DNS Zones
- DNS Tab

Configuring Route53 Support

Configuring Route53 Support

- Configuring Route53 Support
  - Getting Started
  - Adding a Route53 Server to ProVision
    - Server Settings
      - 1) Set Server Common Settings
      - 2) Set Route53 Server Specific Settings
      - 3) Set DNS Group Settings for Server
      - 4) Save Changes
- Additional Information


Getting Started

To use the Route53 connector, you must have Route53/AWS account set up and be able to provide the API Key, API Secret, and API Region provided to your Route53 account. For information on setting up a Route53 account, learning resources, or FAQ, see https://aws.amazon.com/route53/ .

To add a new DNS Server in ProVision, you must be logged in as an Admin-level user.

Adding a Route53 Server to ProVision

To create a new server, start from the **DNS** Tab, select the **DNS Servers** sub menu. Then, click the "Add Server" button next to "DNS Server List".



This will open the "Server Settings" page.


Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter a Display Name for the new Route53 server, *skip FQDN / IP* , and select Server Type.

Under "DNS Service", select the "AWS Route53 (Beta) connector. The FQDN field will automatically be disabled, and AWS/Route53 specific settings will be enabled in the next section.


If desired, adjust the other available settings in this section, then scroll down.



2) Set Route53 Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DNS Service" type chosen under "Common Settings".


Under the section for **AWS Route53 (Beta) Settings**, enter the API Key, API Secret, and API region provided to you for the AWS/Route53 account.



Enter additional Dynamic Updates, NS Records, and Group settings if desired, then click "Save Changes".

For information on working in the rest of ProVision's DNS system, see DNS Tab, DNS Administration, andWorking with DNS Servers.

After entering the server-specific settings in this section, you can click the "Test Server" button at the top of the section to test the server connection and authentication.




A window will pop up showing a success or failure response.




3) Set DNS Group Settings for Server

In the last section, select a default Group to be associated with the server (optional). Zones assigned to the selected Group will automatically be attached to the server.



4) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.



Additional Information

For additional information on working in DNS, see the following sections:

- Working with DNS Servers
- Configuring PowerDNS Support
- Configuring Secure64 Support
- Configuring Split Horizon/Views

- Configuring DNSSEC
- Import DNS Zones
- DNS Tab

Configuring Split Horizon/Views

Configuring ACL Views

ProVision's ACL module applies the specified network lists to the in the named.conf for zones inside the group and the servers that belongs to the group, when exporting the group or zone.

- Configuring ACL Views
  - Create an ACL View
  - Edit an ACL
  - Delete an ACL
  - Add an existing ACL to another Group
- Additional Information


WARNING

If you see a view named "_6connectDefault" - DO NOT DELETE IT.

Create an ACL View

ACL views may be created under each DNS Group, accessed from the **DNS** tab **DNS Groups** sub-tab.

Expand the Group that you want the view applied to, and then expand the section "Applied ACLs" by clicking on the expansion arrow to the right of the section name.




If ACLs already exist, they will be shown under this section.

To add a new list, click the "Add or Edit ACL" button.




If no ACLs currently exist, the dialog will only show inputs for ACL Name and ACL Networks - enter a Name and Network and click "Save Changes".



If previous ACLs exist, a selector will be be available for "Existing ACL:".

Since we are creating a new ACL, just keep this at the default value ("Choose Existing ACL or create a new one"), and enter in the Name and Network(s) for the new ACL. Separating multiple CIDRs with a comma (,).




When done, save the ACL by clicking "Save changes". The new ACL will be added to the Group's Applied ACL list.



Edit an ACL

ACLs may be edited similarly to how they are created. Click the "Add or Edit ACL" button under the "Applied ACLs" module for the DNS Group.

Select the ACL you wish to edit from the "Existing ACL" Selector. Then, edit the Name or Network fields as desired.



When done, click "Save Changes".

Detach an ACL from a Group

Detaching an ACL removes it from the Group, but the ACL will still exist in ProVision for re-use in other Groups.

To detach an ACL, expand the "Applied ACLs" section under the desired Group, and click on the "Detach" button under the "Actions" column.




The ACL will be removed from under the Group, but will remain in other Groups it exists under, as well as be selectable from the "Add ACL" window.

Delete an ACL

ACLs may be deleted through the "Edit ACL" interface. Click the "Add or Edit ACL" button under the "Applied ACLs" module for the DNS Group.

Select the ACL you wish to delete from the "Existing ACL" Selector. Then, click the red "Delete" button under the Networks field.




The ACL will be permanently deleted, and will no longer show under any Groups to which it has been attached, nor show in the "Existing ACLs" list.

Add an existing ACL to another Group

Existing ACLs may be added to as many Groups as desired. If ACLs already exist in ProVision, clicking the "Add ACL" button will give an additional option to "Create New".

To select a previously created ACL, turn the "Create New" toggle to the "OFF" position.



An "Existing ACL" list appears. Select the desired existing ACL from the list, and then click "Save changes" when done.

Additional Information

For additional information on working in DNS, see the following sections:

- Working with DNS Servers
- Configuring ISC BIND Support
- Configuring PowerDNS Support

- Configuring Secure64 Support
- Configuring DNSSEC
- Import DNS Zones
- DNS Tab

Configuring DNSSEC

Configuring DNSSEC

- Configuring DNSSEC
  - Enable DNSSEC for a Server (ProVision GUI)
  - Enable DNSSEC for a Zone (ProVision GUI)
    - Enabling DNSSEC (for a single zone)
    - Update Registrar and Confirm
  - For BIND server(s)
  - For Secure64 and PowerDNS
- Additional Information

Enable DNSSEC for a Server (ProVision GUI)

DNSSEC may be enabled on a per-server basis in the ProVision DNS Server Settings.

Navigate to the **DNS** Tab, and select the **DNS Servers** section.

Find the desired server in the DNS Server List, and then click on the server name to open the settings for that server.



In the server settings page, scroll to the bottom of the second section, containing server-specfic settings.

Near the bottom of the section is a toggle to "Enable DNSSEC" for the server; click the toggle to the "ON" position.



Enable DNSSEC for a Zone (ProVision GUI)

DNSSEC may be enabled on a per-zone basis in the ProVision Zone Advanced Settings.


Before you enable DNSSEC for a zone, make sure that do the following:

- Make sure DNSSEC is enabled on the DNS server(s) you will be pushing zones to (see "Enable DNSSEC for a Server", above)
- run **configTest.php** to make sure that your directories/permissions are correct
- Set external server for Authenticated Data verification
- Create/Edit a zone - see Working with DNS Zones for additional information.
- Ensure that the zone is associated with a DNS server(s)


Enabling DNSSEC (for a single zone)

Navigate to the **DNS** Tab, and select the **DNS Groups** section.

Find the desired Group and Zone in the Groups List, and then click on the zone name to open the details for that zone.




The view zone details page will open. Expand the zone details section "Advanced Settings" by clicking on the expansion arrow.



At the top of the "Advanced Settings" section will be a toggle to "Enable DNSSEC". Click the toggle to enable to the ON position.




Once enabled, the toggle will show as "ON", and a "Show DS Records" button will appear. At this point, no records exists, so clicking "Show DS Records" will result in a message telling you so.



In order for DS Records to be created, the zone must be successfully pushed. Push the zone, Group, or Server containing the zone successfully and DS records will be created (see Working with DNS Zones and Working with DNS Groups for details on how to schedule and push zones).


To quickly push just a single zone, go back to the DNS Groups section, and click on the "Push" button for the zone.




If successfully pushed, a green "Finished DNS Pushing Request" message will appear.



At this point, you will now have DS records available in the view zone details - Advanced Settings section. Open Advanced Settings for the zone and click on the "Show DS Records" button.



The DS records will be shown in a pop-up. Note these values for Registrar confirmation.



Update Registrar and Confirm

Once DS records have been created in ProVision, you will need to update and confirm the Zone Registrar:

- Upload these values to your Zone Registrar, obtained from the "Show DS Records" button
    - DS Record #, Key Tag, Algorithm, Digest Type, Digest
- Confirm values are saved at the Zone Registrar
- External sites
    - http://dnssec-debugger.verisignlabs.com/
    - http://dnsviz.net/

For BIND server(s)

To enable DNSSEC on BIND9 you need to modify **named.conf.options** with following parameters in the **options { }** section:

```
dnssec-enable yes:
dnssec-validation yes:
dnssec-lookaside auto;
```

These parameters may already be enabled in some Linux distributions by default, so please confirm before making changes.

Your DNSSEC implementation may need other options for your environment - please contact support@6connect.com if you have ny

Please note that you will need to restart the BIND service after these changes.

For Secure64 and PowerDNS

DNSSEC Signatures

In this scenario, 6connect ProVision uses the DNSSEC signing functions of the respective environment we write the zones to. We are evaluating how to properly integrate DNSSEC functions to ProVision for these platforms. Please contact support@6connect.com if you have feedback or specific questions.


Additional Information

For additional information on working in DNS, see the following sections:

- Working with DNS Servers
- Configuring ISC BIND Support
- Configuring PowerDNS Support
- Configuring Secure64 Support
- Configuring Split Horizon/Views
- Import DNS Zones
- DNS Tab

DHCP Administration

DHCP Administration



DHCP Administration is primarily handled under the **DHCP** tab **DHCP Servers** sub-tab.

The **DHCP Servers** tab is only accessible to Admin users, and contains functions for adding, updating, and managing DHCP servers as well as scheduling server tasks.

Additional DHCP Admin tasks occur in other ProVision areas, and not all management tasks require Admin-level permissions - some only require appropriate resource permissions on the DHCP Groups, Zones, and servers involved. See additional sections on this page for more detailed information:

- DHCP Administration
  - DHCP Overview
    - DHCP Permissions
    - DHCP Administrative Tasks
  - Manage DHCP Servers
  - DHCP Pool Pushes
    - Manual DHCP Pushes:
    - Scheduled DHCP Pushes:
  - Additional Information:

DHCP Overview

The **DHCP** Tab organizes ProVision's DHCP system into a more unified and accessible interface, combining both admin and non-admin DHCP tasks together under the **DHCP** tab.

DHCP pools are gathered under DHCP Groups and servers are attached to those Groups. Pools, attached servers, and failovers are managed at a per-Group level.

Users can then view and manage Groups, individual pools, failover values, attach servers, and perform pushes all on the same page.

DHCP Permissions

DHCPv2 (ProVision 7.0.0 and later) more effectively utilizes ProVisions resource permissions system to allow fine-grain permissions in DHCP.

In order for a user to work with DHCP Groups, Pools, and servers, they must have User Group permissions for:

- One or more Parent Resources under which the DHCP Group and DHCP Pools will be associated (it can be a specific resource, or the all-encompassing "TLR")
- IPAM permissions sufficient to access and manage the desired blocks from which to assign DHCP Pools

- Permissions on the specific DHCP Server(s) in order to attach, detach, and push.

Creation and management of DHCP servers, as well as scheduled DHCP pushes, are Admin-only tasks.

DHCP Administrative Tasks

Admin-only tasks in DHCP include scheduling pushes, and creating / managing DHCP servers.

These tasks may be accessed in the following areas:

- Scheduling DHCP Pushes:
  - May be set up from the Scheduler Tab or,
  - Set by server from the **DHCP Servers** page, or
  - Set by DHCP Group from the **DHCP Groups** page, or
  - Set by individual pool from the Pool Details page
- Managing DNS Servers: The **DHCP Servers** page

Tasks such as working with pool, DHCP Groups, editing Group Settings, attaching servers to Groups, and manually pushing pools do not require ProVision Admin permissions.

Instead, these tasks simply require that the user be included in a User Group that has appropriate permissions (either direct, or inherited) on the Parent Resources, DHCP Groups, and servers involved.

Manage DHCP Servers

Adding, configuring, and managing DHCP Servers occurs in the Admin-only **DHCP Servers** page under the **DHCP** Tab.

Supported DHCP server service types include:

- ISC DHCP
- Cisco Prime Network Registrar

For detailed information on adding, editing, and deleting DHCP Servers, see Working with DHCP Servers.

DHCP Pool Pushes

In DHCPv2, pools may be pushed manually or scheduled for a future time, and may be performed for a single pool, all pools in a DHCP Group, or a full DHCP server.

Scheduling DHCP pushes requires administrative access, but manual pushes only require permissions on the DHCP Group / Parent Resource, and the server(s) attached.

Manual DHCP Pushes:

Manual DHCP pushes may be performed from the following locations in ProVision:

- Single Pool: From the DHCP Groups pool list "Push" button. See Working with DHCP Pools - Pushing DHCP Pools
- Single Pool: From the DHCP Pool Details page "Push Now" button. See See Working with DHCP Pools - Pushing DHCP Pools
- Group: From the DHCP Groups list "Push Group" button. See Working with DHCP Groups - Pushing a DHCP Group
- Server: From the DHCP Servers list "Push" button. See Working with DHCP Servers - Pushing a server
- Server: From the DHCP Server Settings page "Push Pools" button. See Working with DHCP Servers - Pushing a server

Scheduled DHCP Pushes:

Scheduled pushes may be performed from the following locations in ProVision:

- May be set up from the Scheduler Tab for a DHCP Group or server
- Set by server from the **DHCP Servers** page, or
- Set by DHCP Group from the **DHCP Groups** page, or
- Set by individual pool from the Pool Details page

Additional Information:

For more information on DHCP Adminsitrative tasks, see the following sections:

- Working with DHCP Servers


For non-admin level tasks, see:

- DHCP Tab
- Working with DHCP Groups
- Working with DHCP Pools
- Working with DHCP Gadgets

Working with DHCP Servers

DHCP Servers


ProVision's DHCPv2 combines server management, group organization, and pool management under the **DHCP** tab.



The **DHCP Servers** tab is only accessible to Admin users, and contains functions for adding, updating, and managing DHCP servers as well as scheduling server tasks.

- DHCP Servers
  - DHCP Server List Interface
- Working with DHCP Servers
  - Add a Server
    - Server Settings
      - 1) Set Server Common Settings
      - 2) Set Server Specific Settings
      - 3) Set Advanced Server Settings
      - 4) Set DHCP Group Settings for Server
      - 5) Save Changes
  - Edit Servers
  - Review Pools Connected to a Server
    - Pools Directly Connected to the Server
    - Zones Connected via a Group
  - Pushing a Server
    - Manual Push
    - Scheduled Push
  - Review Pushed / Unpushed Configurations
  - Scan a Server
  - Delete a Server
- Additional Information

DHCP Server List Interface



1) Add Server Button: Opens a dialog for creating a DHCP server.

2) Server List:


3) Server Name: Name of the DHCP server. Click to open server details.

4) Server Backend: The DHCP Service backend type for the server. Available types are ISC and CPNR.

5) Server Host: The server host.

6) Parent Resource: The ProVision resource set as the Parent for the server.

7) Actions: The actions that may be performed on each server:




8) Delete: Deletes the server from ProVision.

9 Push: Pushes all pools associated with the selected server.

Working with DHCP Servers

Add a Server

To create a new server, start from the **DHCP** Tab, select the **DHCP Servers** sub menu. Then, click the "Add Server" button next to "DHCP Server List".




This will open the "Server Settings" page.

Server Settings

1) Set Server Common Settings

In the "Common Settings" section of Server Settings, enter the new server's Display Name (the name that will appear on the ProVision interface), the FQDN / IP, server type, service type, and desired parent Resource (may be left at the default Top Level Resource).



Display Name: Name you want the server to display.

Server IP: The IP or Hostname of the DHCP server.

DHCP Service: Select the DHCP service type - ISC DHCP, or Cisco Prime Network Registrar (CPNR).

Parent Resource: Select the ProVision resource to be the "parent" of the server - typically TLR (Top Level Resource), but may be a lower level resource such as a Customer or Location. The parent resource selection is the basis of access permissions for the server.


2) Set Server Specific Settings

The next section is entering server service-type specific settings. The options visible in this section will depend on the "DHCP Service" type chosen under "Common Settings".

Here, we see the fields for ISC DHCP server settings. Enter the server Username, Password, Port, Leases Directory, Server Start / Stop Commands, Server Test Command and Freelines (if desired).

Your fields may vary for other server types.

For SSH Public Key Authentication, click on the ON / OFF toggle to select "ON" or "OFF" as needed.




3) Set Advanced Server Settings

If desired, Advanced Settings for the DHCP Server may be entered. Toggle "Authorative Server" to "On" or "Off", and fill in the fields for Routers, Domain Name Servers, Domain Name, Default Lease Time, Max Lease Time, Local Port, or Log Facility.



4) Set DHCP Group Settings for Server

In the last section, select whether to attach the server to an existing DHCP Group. Pools assigned to the selected Group will automatically be attached to the server.



5) Save Changes

Save your changes when done! Just click the "Save Changes" button at the bottom right of the page.



The new server will now be added to the DHCP Servers list. These settings may be changed at any time by selecting the server from the server list and editing the information.

Edit Servers

Edit an existing server by clicking once on the server name in the DHCP Servers list.



The "Server Settings" page will open.

Click inside the field that you want to change, type your changes, and then click "Save Changes" at the bottom of the page.



Review Pools Connected to a Server

There are two ways that pools may be connected to a DHCP server:

1) Directly connected, by attaching the pool to a server from the Pool Details page.

or,

2) Connected by a Group that has been set as the default DHCP Group for the server, selected under "DHCP Group Settings".

Both are able to be viewed on the DHCP Server Settings page.

To view either, open the Server Settings page for the server by clicking on the server name in the DHCP Servers list.

Edit an existing server by clicking once on the server name in the DHCP Servers list.



The "Server Settings" page will open.

Pools Directly Connected to the Server

Scroll to the bottom of the page, and open the module titled "Pools directly connected to the server" by clicking on the expansion arrow.




A pool list will show the pool(s) that have been directly connected to this server.

Here, you may browse through subnet and host pools by selecting the appropriate tabs, sort the list by Pool Name or Last Modified, or open the Pool Details page by clicking on the name.

Zones Connected via a Group

If a default Group has been selected under "DHCP Group Settings" for the server, pools under that Group will be connected to the server and able to be viewed on the Server Settings page.

Scroll to the bottom of the page, and open the module titled "Pools connected to Group '(Group Name)' " by clicking on the expansion arrow.



A pool list will show the pool(s) that have been directly connected to this server.

Here, you may browse through subnet and host pools by selecting the appropriate tabs, sort the list by Pool Name or Last Modified, or open the Pool Details page by clicking on the name.


Pushing a Server

Manual Push

Manually pushing all pools on a server may be done directly from the DHCP Server list. Under the "Actions" section of the Server List, click the "Push" button for the desired server.



Pushing may also be done while in the Server Settings page. While in the Server Settings page, click the "Push Pool" button at the top right of the page.




A "DHCP Push Status" box will appear, showing the status as the server is pushed. Once all pools have been pushed successfully, a green status message of "Finished DHCP Pushing Request" will appear. At this point, the push is complete and the window may be closed.

Scheduled Push


DHCP server pushes may be scheduled from either the Admin Area **Scheduler** Tab, or from within the DHCP Server Settings page. Scheduled pushes require Admin access.

For information on scheduling a push from the **Scheduler** Tab, see Scheduler Tab documentation.

To schedule a push from a server's Settings page, open the Server Settings page for the desired server, and click on the "Schedule Push" button.



The Push Scheduler dialog will open. Click on the calendar on the left to select a date for the push, set the desired push time on the right, enter a notification email address, and then click "Save Changes".



Once a schedule push has been created, a "Scheduled Tasks" module will appear at the top of the Server Settings page.

Click on the expansion arrow for the module to open and view the tasks. Scheduled tasks may be deleted by clicking the "Delete" button under "Actions".




If necessary, the Scheduled Push may be edited from the **Scheduler** Tab in the Admin area of ProVision. See the Scheduler Tab for information on editing scheduled tasks.

Review Pushed / Unpushed Configurations

After a server has been created, unpushed edits may be viewed under the "Unpushed Configurations" module in Server Settings.

After a push, the most recent pushed configuration may be viewed under the "Current Pushed Configuration" module in Server Settings.

To open either, click the expansion arrow for the module on the top right of the header.



The Unpushed Configuration module will show the edits made to the configuration since the last successful push, and the user, time, and date of the change.




In Current Pushed Configuration, you may search for a specific line by entering a term in the search bar and hitting the "Enter" key - the config will jump to the appropriate line for review.




Scan a Server

Scan a DHCP Server by clicking the "Scan Server" button at the top of the Server Settings page.



When complete, a "Server Statistics" module will appear. Expand the module, and if the server permissions allow, the scanned statistics will show in the module.

If permissions or directory location fails during the scan, an error message will show instead.



Delete a Server

Delete a server by clicking the "Delete" button under the "Actions" section of the Server List for the desired server.



Additional Information

For more information on working with DHCP in ProVision, see the following areas:

- DHCP Tab
- Working with DHCP Groups
- Working with DHCP Pools
- Working with DHCP Gadgets

Importing Your Data

Preparing for Data Import

Before importing your data into ProVision, there are a few steps we recommend in order to make the import process as smooth as possible:

- Preparing for Data Import
  - Step 1: Normalize your Data
  - Step 2: Prep your Data
  - Step 3: Import your Data
- Data Import Overview: Which Import Tool Should I Use?
  - Resource Import
  - Peering Import
  - IP Import
  - DNS Import
  - Import Templates
  - Additional Information

Step 1: Normalize your Data

Prior to importing your data, there is a key step of Data Normalization to ensure that information is accurate. If you need assistance with parsing your data prior to importing, 6connect can help with our Data Analyst service. Email us at support@6connect.com for more information.
You can also use off the shelf tools like Microsoft Excel, MySQL, or Google Refine if you intend to take on the task of data cleanup in house.

Common normalization steps required for ProVision imports include:

- Remove any empty rows in the data range
- Remove any empty columns in the data range
- Remove stray data from inside and outside the data range, such as:
  - notes, comments, and placeholder text as field values, when not set as their own data column
  - nested secondary information located in additional rows under a primary record
- Ensure proper data formatting
  - Check for data formatting errors - a common issue is leading zeros being dropped from a ZIP field when a file is opened. Re-specify format as needed.
  - Ensure each field has consistent formatting for values
- Ensure unique values for primary identifiers, such as Resource Name and ID Fields

  Data Encoding Format


  

  To ensure correct importing of any special characters, make sure to use UTF-8 encoding for your CSV file!

Step 2: Prep your Data

You can download data import templates from the **Dashboard Tab** or **Data Import Tab**. We recommend that you open the CSV import templates and get familiar with the data fields that you can import into the platform.

- **For Company information** you can import relevant data including mailing/billing address information as well as ARIN specific SWIP fields, and specific DNS servers.
- **For Contact information** you can import contact records assigned to a given **Company**. We support typical fields for this data including Name, multiple email fields, phone numbers as well as Timezone and Role (Roles can be customized from the **IPAM Admin Tab)**.
- **For IP Block information** you can import the following fields:




Allow Subassignments option

When importing the field "Allow Subassignments" - the parameters accepted are "TRUE", "1", "Y", "yes"

Step 3: Import your Data

Get to the **Data Import Tab** from the **Admin button** to import your data. For larger data import runs, feel free to contact 6connect at any time for assistance at support@6connect.com.




Data Import Overview: Which Import Tool Should I Use?

Resource Import

Simple Upload / Import from CSV: Use this tool if you have a simple .csv file of customer / contact information, such as Name, Address, Billing Address, Phone numbers, POC, etc. See Resource Import from CSV for more details.

This tool supports the following fields:



For Resource Import from .csv, the following fields are REQUIRED:

- Name (Unique Resource / Customer Name)
- Customer ID (Unique non-name identifier)

All other fields are optional.

Resource Import Tool: The Resource Import tool is designed for importing .csv files for any Resource type (company, physical devices, contacts, customers, etc), and allows for customized headers through integrating ProVision's Section fields. It also allows for data editing within the tool. Use the Resource Import Tool if you have resource data that does not fit under the Simple Upload / Import from CSV field options, and can equate that data to an existing or newly created Section.

Additional Information


A tutorial / walkthrough for this tool is available at the Resource Import Tool page.

Peering Import

Import BGP Sessions: This section imports peering sessions from a selected exchange and router. Routers must be created prior to using this importer. See Peering Routers and Importing Sessions for additional information.

IP Import

Upload / Import from CSV: Use this tool if you have a .csv file of IP block information, such as CIDR, Mask, ASN, RIR, etc.
This tool supports the following fields:



For IP Import from .csv, the following fields are REQUIRED:

- CIDR String OR both IP and Mask
- RIR OR a selected default RIR

All other fields are optional.

Import from RIR: This tool automatically lookups your ARIN or RIPE information based on the IP address you are connected to. Once it identifies the blocks assigned to your company, you can import both 1918 aggregates as well as public IP space from ARIN and RIPE. See Import Aggregate Blocks for more detail on this tool.

DNS Import

The following DNS Import options are available from the **Data Import** tab:

BIND Zone Upload / Import: Imports DNS zones using the named.conf configuration file tied to the zones you are uploading, a .zip or .tar file of the zones themselves, and an optional .csv file mapping zones to customers and DNS Servers. This is the simplest and most commonly used import method. Refer to Import DNS Zones for more information.

PowerDNS Zone Import: This tool is available after configuring a PowerDNS server with a MySQL backend. The PowerDNS Import connects to the selected server and imports all zones.

InfoBlox Zone Import: Imports DNS zones using a provided Host, Username, and Password. The InfoBlox import pulls all zones on the InfoBlox LOCAL grid and adds them to a designated Group. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

NS ONE Zone Import: Imports DNS zones using a NS One API Key. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

Dyn DNS Zone Import: Imports DNS zones using a Dyn DNS Customer Name, Username, and Password. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.


DNSMadeEasy Zone Import: Imports DNS zones using a DNSMadeEasy API Key and API Secret. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

IPPlan Zone Import: Imports DNS zones using IPPlan MySQL database options. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.


Additional DNS import options may be available on a per-zone or per-server level, accessed from the **DNS** Tab:

DNS Zone Import: This tool is available on a zone's "View Zone" page, and allows the user to import additional zone/record information into an existing ProVision zone by uploading a zone file (.zone).

- From the View Zone page, a zone file (.zone) may be imported into a ProVision zone to populate record data. Click "Import Zone".



A Zone Import dialog box will open. Next to **Zone File:**, click "Choose File" and select your .zone file to import. Then, select an import policy to follow.



When done, Click "Import Zone".

Import Templates

Import template sample files are available for selected ProVision import tools. A link is provided for a download page, both here and on the **Data Import** Tab.

These may be viewed as an example of .csv setup for their respective importers, or used for tutorials.

They are:

All Import Samples - Links to the CSV import templates page of the documentation, showing all available import template .csv files.

IP Import Sample File - Download the IP-import-sample_v1.csv file, used in the IP Import: Upload / Import from CSV Tool.

Customer Sample Import - Download the customer-import-sample.csv file, used in the Resource Import: Simple Upload / Import from CSV Tool.

Additional Information


For more details, see:

- Resource Import from CSV
- Resource Import Tool
- Import Peering Sessions
- IP Import from CSV
- Import Aggregate Blocks
- Import DNS Zones

Resource Import from CSV

Simple Upload / Import from CSV

The Simple Upload / Import from CSV tool is used if you have a simple .csv file with customer / contact information, such as Name, Address, Billing Address, Phone numbers, POC, etc. It is accessed from the **Data Import Tab** from the **Admin** section of ProVision.



To import your customer / contact information, follow the following steps:

- Before you Begin: Prepare your Data for Import
- Step 1: Create a new Resource / Customer Import Job
- Step 2: Define Columns
- Step 3: Reviewing Data
- Additional Information

Before you Begin: Prepare your Data for Import

The Simple Upload / Import from CSV tool requires only a .csv file for importing.

Be sure to review "Preparing Data for Import" on the Importing your Data page before you begin. Verify that your .csv is correctly parsed and cleanly formatted with your customer/contact information (using your choice of the available field list shown below), and is UTF-8 encoded for best results.


Be sure to check that your data is cleaned up with the following steps:

- Remove any empty rows in the data range
- Remove any empty columns in the data range
- Remove stray data from inside and outside the data range, such as:
  - notes, comments, and placeholder text as field values, when not set as their own data column
  - nested secondary information located in additional rows under a primary record
- Ensure proper data formatting
  - Check for data formatting errors - a common issue is leading zeros being dropped from a ZIP field when a file is opened. Re-specify format as needed.
  - Ensure each field has consistent formatting for values
- Ensure unique values for primary identifiers, such as Resource Name and ID Fields

  Data Encoding Format

  ⚠ To ensure correct importing of any special characters, make sure to use UTF-8 encoding for your CSV file!

This Resource Import from .csv tool supports the following fields:




Note: the following fields are REQUIRED:

- Name (Unique Resource / Customer Name)
- Customer ID (Unique non-name identifier)

All other fields are optional.


Step 1: Create a new Resource / Customer Import Job

Navigate to the **Data Import** Tab from the **Admin** button. Select "Simple Upload / Import from CSV" under "Resource Import".



Create a Job Name and Description for the import. This is especially useful to keep track of progress in cases the data arrives from multiple sources, or will require multiple stages of manual review.

Select the .csv file that you prepared above by selecting the "Choose File" button, and browsing to the correct file location. Then hit "Start Import".




Working with Large or Multiple Data Sets

Although you cannot add new files to an existing job, for jobs with multiple sources for data (which may have different formatting), you can simply create separate jobs and descriptions for each source - no need to manually combine the data into one file before importing. The Import tool's mapping and editing functions will allow for the data to be reconciled in ProVision.

For large data sets where multiple stages of manual review might be needed, you can create a new job using the same set of data files in order to work in parallel on a different portion of the data.

After importing, the new job will appear under the "Existing Jobs" section.

To continue working with this job, select it from the list (by clicking on the link) and the next step ("Define Columns") will appear at the bottom of the page.



Step 2: Define Columns


Using the dropdown menu above each data field, select the appropriate definition for each of the imported columns. **Phone** and **Fax** may have multiple columns associated with the data. Other columns which do not apply under the available definitions should be left as blank, and will be skipped during the upload process.

Note: the following fields are REQUIRED:

- Name (Unique Resource / Customer Name)
- Customer ID (Unique non-name identifier)

Make sure that you have defined all desired fields by using the scroll bar below your data to view additional columns.

When completed, hit "Next".



Step 3: Reviewing Data


After supplying the file and defining columns, a review step is provided. Records with errors will show as color coded, and can be filtered to be viewed by All, Valid, Warnings, Invalid, or Ignored.

From here, the records can be edited or ignored. Select "Ignore" for records that you do not wish to import at this time. Records that are Ignored or Invalid will automatically be skipped.


Header Rows

If your .csv has a header row as the first line, that row will be shown as the first record in review data as well. Simply click "Ignore" on the first record to disregard the row.

For rows with an "Invalid" or "Warning" status, you may wish to edit the record to change information to a valid option.




Hitting the "Edit" button for the record provides options to change or add information for available fields.



In this example, as "Name" was the invalid field, it has been updated to a unique value. The "Custom Field" value has been added as well.

After making the desired edits, hit "Save".


The data record will be re-checked for validity, and will have a white background if it is now valid for import.



After data has been reviewed for accuracy, you may execute the import.


Step 4: Execute Import

When the review step is completed, hit the "Execute Import" button.



A progress bar will appear to and display the records as they are imported.

When the bar reaches 100%, and displays "Current Step: Finished!" the import is complete, and you may leave the page.



Additional Information

For more import options, see:

- Resource Import Tool
- Import Peering Sessions
- IP Import from CSV
- Import Aggregate Blocks
- Import DNS Zones

Resource Import Tool

Importing Resources

- Importing Resources
  - The Resource Import Tool
  - Before You Begin
  - Opening the Resource Import Tool
    - The Resource Import Tool UI
  - Resource Importer Walkthrough

The Resource Import Tool

The Resource Import Tool (in beta) allows you to import resource data from a .csv file into ProVision. In the Resource Import Tool, you can open one or more user-created .csv spreadsheets, perform basic editing functions if needed, associate the data to a specific Section, and correlate the data columns to specific Section Fields.

In ProVision, since Resources can be any desired entity, and Sections can be anything from "customers" to "firewalls" to "racks", you have total flexibility in what type of data to import with the Resource Importer to meet your specific company needs. Check out Working With Resources, Customizing Sections, and Customizing Fields for more details on how to fit these elements to your business.

Before You Begin

There are a few items that you will need have set up prior to using the Resource Importer Tool. Ensure that you have:


- The .csv document you wish to import saved with UTF-8 encoding. Windows, Mac, and Linux type .csv files are supported.
- A header row for the data in the .csv.
- The .csv file should be "clean", that is, only contain the data to be imported and a header row for that data.
- A Section created in ProVision with fields that correlate to the import data. For example, if you wish to import a list of contact information, there will need to be a Section in ProVision created for "Contacts", with fields such as "First Name", "Last Name", "email address", "Phone number", and so on. To create a new Section, or edit an existing Section, refer to Working With Resources, Customizing Sections, and Customizing Fields.

  If the above preconditions are not met, the Resource Importer Tool may not be able to correctly read the .csv file or complete the import. Verify UTF-8 .csv encoding, a clean dataset with a header row, and that an appropriate Section exists in ProVision prior to import.
  Best Practice

  To ensure a fast and straightforward resource import, best practice is to verify ahead of time that your .csv data is correct and contains all the necessary column information for the Section. This includes a top-level Name and Unique ID, as well as a column per Section field. Data edits and column adjustments can be performed inside the Resource Importer Tool if necessary, but will require additional time and steps.


Opening the Resource Import Tool

To open the Resource Import Tool, navigate to the **Data Import Tab** from the **Admin button** to import your aggregate blocks. Select "Resource Import Tool" under "Resource Import".



The Resource Import Tool UI

When you first open the Resource Importer, you will be given the option to view a short on-screen guide to using the tool. After stepping through the guide and/or exiting out of it, the tool will look like this:



On the top are standard menu options of "File", "Insert", and Data" and "Help". Under those menus, you may see greyed-out functions listed. Those functions are items under development, or not available to use at the current Importer step.

On the left side of the screen is a listing of currently opened files:

Sections Grids lists grids currently open that were created from a ProVision Section

Open Files lists the current user created .csv spreadsheets that are open

Local Grids lists any grids that were created in the tool itself, instead of opened from an external file

Completed Imports show imports which have been completed and imported into ProVision

If, at any time, you need to leave the Resource Importer Tool, select the "Exit Import Tool" in the top right corner of the screen, and you will be taken back to the ProVision Dashboard.

Exiting the Resource Importer Tool prior to completing the import process will result in the current open grids being discarded.

Resource Importer Walkthrough

For a step by step walkthrough of the Resource importer, continue on to the Resource Importer Walkthrough , which shows how to import a sample contact list and perform minor editing tasks.

Resource Importer Walkthrough - Step 1 Upload your .csv data file

Resource Importer Walkthrough - Step 2 Open a Template Grid from an existing Section

Resource Importer Walkthrough - Step 3 Reorder .csv columns to match the Section Grid column order

Resource Importer Walkthrough - Step 4 Edit Data as Needed

Resource Importer Walkthrough - Step 5 Drag rows from the .csv Grid to the Section Grid

Resource Importer Walkthrough - Step 6 Import into ProVision

Resource Importer Walkthrough - Step 1

Importing Resources

Before You Begin

Ensure that you are familiar with the overview and "Before you Begin" requirements listed on the Resource Import Tool page.


For this tutorial, we will be using the Contact Import Sample .csv available on the Import Templates page as an example, and associating it to an existing Section called "Contact" having the fields: First Name, Last Name, Email, 2nd Email, Phone, 2nd Phone, Mobile Phone, Role, and Time Zone. To create this Section, or edit an existing Section, refer to Working With Resources, Customizing Sections, and Customizing Fields.

In order to illustrate the abilities of the Resource Importer to edit data and adjust for formatting issues, the Contact Import Sample .csv is used intentionally leaving a few less-than-ideal conditions (much like you may encounter in real life) such as leaving typos, having an extra data column, and missing a needed column. If you follow the "Before you Begin" requirements and "Best Practice" notes, however, you may be able to skip any editing or column adjustment steps.

When you are ready to begin, open the Resource Importer and proceed to Step 1.


Step 1: Upload your .csv data file

Under the "File" Menu, select "Open .csv". Browse to and select your UTF-8 encoded data file.





After hitting "OK", your file should be visible in the workspace, as well as listed under "Open Files" like this:




After opening your .csv grid, proceed to Step 2 - Open a template grid from an existing Section

Resource Importer Walkthrough - Step 2


Importing Resources

Step 2: Open a Template Grid from an existing Section

Under the "Data" menu, select "Create Sheet from Section".




The Resource Browser will pop up, showing the list of Sections currently available in Provision. Clicking on the "Details" button will show the fields for that Section.




Verify that the Section and available fields match the type of data you are trying to import. In this case, the Section "Contact" has the fields that correlate to our spreadsheet data.

Select "Create Grid" to create a grid based off this Section.



When the Section Grid has been created, required fields will show in blue font with (required) after the header, in this case, "Name" is a required field. The "Custom ID" field is metadata allowing for a unique ID to be associated with each entry, but is not necessary for a successful import. The remainder of the headers directly match the Section's fields.



After you have opened your Section Grid, proceed to Step 3: Reorder .csv columns to match the Section Grid


Resource Importer Walkthrough - Step 3

Importing Resources

Step 3: Reorder .csv columns to match the Section Grid column order

One of the most important steps is to reorder the columns from the .csv data to match the order of the Section Grid headers - think of the importer as copying and pasting the csv data into the "Contact" Section grid- we want to ensure that the data is under the correct headers!

Click on the column header to Drag and Drop to the desired location:



#	Unique ID	Last Name	First Name
0	6c-004	Hughes	Aaron
1	6c-004	Parker	John
2	6c-004	Taylor	Tom
3	6c-007	Smith	Bob

Click back and forth between the tabs to verify the column order, then click on a header and drag and drop into the desired order. This moves not only the header, but also the data below it.

Common Column Editing Questions

What if just my column headers are in the wrong place?

What if I have too many / too few columns in my .csv to match the Section Grid?

If you see any of these issues, proceed to Step 4 - Edit data as needed.

Otherwise, if your columns match up perfectly and none of the data needs editing, skip to Step 5 - Drag rows to the Section Grid

Resource Importer Walkthrough - Step 4

Importing Resources

Step 4: Edit data as needed


As you may have noticed in Step 3, with this example we have a couple of columns that don't quite match up to the Section Grid. The "Title" column in the .csv data is an additional column we are not tracking in our Section. Also, although we have a "First Name" and "Last Name", we are missing a data column for the top-level "Name" required in the Section Grid.

Common Editing Questions:

- What if I have too many / too few columns in my .csv to match the Section Grid?
- What if I see a typo in the .csv data?
- What if just my column headers are in the wrong place?


To hide extraneous column information:

Right click on a header and deselect the check box for the column you wish to hide. In this case, we want to hide "Title".



To Edit Data in the Resource Importer

Data in the grids can be edited directly by clicking on the cell(s). In our example, we can see that "Amanda Kingson" should really be "Amanda Kingston". Let's fix that! Click in the cell, type in the edit you wish to make, and then click outside of the cell to exit edit mode. To edit a full row of data, you can right click on the row, select "Edit" row, and make multiple changes in the form box.




#		Unique ID	First Name	Last Name	email	email2	Phone
0	☐	6c-004	Aaron	Hughes	aaron@6connect....	support@6conne...	1-408-555-1212
1	☐	6c-004	John	Parker	john@gmail.com		234.634.1234
2	☐	6c-004	Tom	Taylor	ttaylor@toms.com		503-555-1256
3	☐	6c-007	Bob	Smith	bsmith@apple.com		888-call-now
4	☐	6c-008	Maurice	Carmichael	mc@mail.com		866-555-1134
5	☐	6c-009	Vince	Bunch	vbunch@happypa...	ops@happyplace....	703-555-1111
6	☐	6c-010	Mark	Tompson	tompson@tt.net		888-nice-wor
7	☐	6c-011	Herold	Waters	hwaters@is.co.uk		234-555-6678
8	☐	6c-012	Michael	Sanders	pm@mybusiness....		354-555-1235
9	☐	6c-013	Jll	Keller	jill.keller@another...		17 145 125124
10	☐	6c-014	Sarah	Campbell	sa.camp@intel.net		234-234 1234
11	☑	6c-015	Amanda	Kingston	akingston@sellin...		44 123 555 12

If a column header is over the wrong data:

If just the header is in the wrong spot (doesn't match the data below it), you can move just the column header in the Resource Importer, without moving the data below it.

1) Right click on a row of the grid to edit and select "Set Columns":



2) In the "Change Column Header" dialog box, drag and drop the column header(s) into the desired order. Remember, this only moves the headers, not the data below them! Then, hit "OK".



If your .csv data is missing a data column needed for the Section grid:


In our case, the .csv data is missing the required "Name" column for the Section grid. Think of the "Name" as the information you would want to search for in Provision. We wouldn't want to search just for "Bob" or "Smith" when looking down a list of names, so under the "Name" column, we need to see the full first and last names, like "Bob Smith".

Currently, our options to fix this are:

1) Edit the .csv directly in your spreadsheet program: (Recommended) Simply revise the .csv to include another column for "Name", and re-open the .csv in the importer. The benefit to this method is your .csv file will be set up as a template for future imports.

Or:

2) In the Resource Importer, temporarily hide the extra column in the Section Grid: Make the columns between the .csv and the Section Grid match exactly by temporarily hiding the column (in this case, "Name") in the Section Grid, proceed to move the data into the Section grid (see Step 5), then unhide the "Name" column and manually add the data as needed prior to completing the import.



#	Name (required)	Custom ID	First Name	Last Name	Email	2nd Email	Phone	
0	Aaron Hughes	6c-004	Aaron	Hughes	aaron@6c...	support@...	1-408-555...	1-
1	Amanda Kingston	6c-015	Amanda	Kingston	akingston...		44 123 55...	
2	Bob Smith	6c-007	Bob	Smith	bsmith@a...		888-call-now	
3	Herold Waters	6c-011	Herold	Waters	hwaters@i...		234-555-6...	
4	Jill Keller	6c-013	Jll	Keller	jill.keller@...		17 145 12...	
5	John Parker	6c-004	John	Parker	john@gm...		234.634.1...	
6	Mark Tompson	6c-010	Mark	Tompson	tompson...		888-nice-...	
7		6c-008	Maurice	Carmichael	mc@mail....		866-555-1...	
8		6c-012	Michael	Sanders	pm@myb...		354-555-1...	
9		6c-014	Sarah	Campbell	sa.camp...		234-234 1...	
10		6c-004	Tom	Taylor	ttaylor@to...		503-555-1...	
11		6c-009	Vince	Bunch	vbunch@...	ops@hap...	703-555-1...	

When edits and adjustments are complete, move to Step 5 - Drag rows to the Section Grid


Resource Importer Walkthrough - Step 5

Importing Resources

Step 5: Drag rows from the .csv Grid to the Section Grid


Once you have set the columns to match exactly between the .csv Grid and the Section grid, it's time to pull in the data from one to the other.

Simply click the checkboxes for the rows you wish to import (or use the "Select all" checkbox at the top), click anywhere on the row, and drag & drop onto the Section Grid tab ("Contact"). The tool will tell you how many rows you are moving as you drag them.



Click on the "Contact" tab when you are done, and you will now see your data in there, instead of the original .csv.

If you had to hide columns in the Section Grid prior to moving the .csv data, verify that all columns are visible and the required data filled in. In this case, we filled in the "Name" Column that was missing in the original .csv.




After moving your data into the Section grid, proceed to Step 6 - Importing into ProVision.

Resource Importer Walkthrough - Step 6


Importing Resources

Step 6: Import into ProVision

When all of the data is under the Section Grid tab, and any required field data filled in, you can import the data into Provision! From the Data menu, select "Import active Sheet into ProVision".




You may also click directly on the grid menu and select "Import".




Select Parent Resource

After initiating the import, a dialog box will ask if you would like to assign TLR as the parent resource for the imported items - if so, click "OK".

If you would like to specific a different resource to use as the parent, click "Cancel".



A "Resource Search" form opens, allowing you to search for a resource. To select the parent resource, click on the ID number (blue link) of the desired resource. You may also cancel the import, if needed.



You will see an import progress bar. Once complete, you data will be in provision, filled into the Section fields for your chosen Resource.



From here, you may review or edit the imported resources from the Resources Tab or Resource Entry page.

Additional Information


For more information on working with resources or importing, see:

- Resources
- Working with Entries

- Resource Import from CSV
- Resource Import Tool

Import Sessions

Importing BGP Sessions



Importing peering sessions requires Admin-level permissions, and is accessible only from the Admin section of ProVision.

From the Admin section of ProVision, navigate to the **Data Import Tab.** Under Peering Import, select **Import BGP Sessions.** This will take you to the Peering Import section of ProVision.

- Importing BGP Sessions
  - Standard BGP Session Import
    - Before You Begin
    - Load Router Sessions
    - Edit Sessions (Optional)
    - Select Groups and Sessions
  - Importing with Router File Connectors
    - Step 1
    - Step 2
    - Step 3
    - Via APIv2
  - Additional Information


Standard BGP Session Import

Before You Begin

Before attempting a session import, ensure that the applicable exchange and router have been added into ProVision. See Peering Exchanges and Peering Routers for details.

Load Router Sessions

First, select the desired exchange and router. Routers with Logical Systems information will show up as the router name with the Logical System info in parenthesis (e.g. "Juniper (test)"). Then click "Load Sessions".



Peer Group and Sessions will then display below your selections.

Edit Sessions (Optional)

The available peer Groups and Sessions will display below your selected exchange and router.

If edits need to be made to the session prior to import, click on the wrench icon to open field edits.




Make the changes to desired field(s), then click "Done" to save your changes and proceed to importing.



Select Groups and Sessions

Lastly, select the check box next to each Session to import (or the check box at the top to select all sessions) and click "Import Selected Sessions".

Successful imports will then display with a green check mark at the beginning of the row.



Once imported, you can manage and configure your sessions from the Peering Tab.

Importing with Router File Connectors

Note: These connector types are only used for this direct data import process - do not select these for standard ProVision router/session creation, as peering management functions (config pushes, session states, etc) do not obtain a router connection while using File Connectors.

File Connectors should only be used in rare circumstances where direct router access is unavailable.

Step 1

Generate a router response data text file (it should be named “cisco_router_data.txt”, “juniper_router_data.txt” or “arista_router_data.txt”) and place it in ProVision's /data directory.


To generate the router response, run the following commands:

Cisco	Juniper	Arista

terminal length 0 show bgp ipv4 unicast sum show bgp ipv4 unicast neighbor show bgp ipv6 unicast neighbor	show bgp neighbor | display xml | no-more show bgp group | display xml | no-more	terminal length 0 show ip bgp summary show ip bgp neighbors

Step 2

Create a new 'Router' in ProVision, selecting the appropriate file connector as the Router Make type - CiscoFile, JuniperFile, or AristaFile.




Step 3

Navigate to Admin Data Import Peering BGP Import.

Select the appropriate exchange, then the File Connector Router that you created.



Click "Load Sessions", and the sessions contained within the router data file will be available to review, select, and/or import into ProVision.



Via APIv2

The same import process may also be performed via APIv2, using the following information:

1) "router id" contained within the URL for an already-created File Connector Router

2) "ix_id" (the ID of the exchange) in the body

3) "router_response" (the output from the router) in the body

The APIv2 details can be view from ProVision swagger documentation at ['instance']/dev/swagger/spec.php?family=peering#/default/single_parse_bgp_info

Additional Information


See the following areas for more information on working with Peering tasks:

- Peering
- Peering Exchanges
- Peering Routers
- Peering Sessions

IP Import from CSV

Simple Upload / Import from CSV

The Upload / Import from CSV tool is used if you have a simple .csv file with IP block information, such as CIDR, Mask, ASN, RIR, etc. It is accessed from the **Data Import Tab** from the **Admin** section of ProVision.



To import your IP block information, follow the following steps:

- Simple Upload / Import from CSV
  - Methodology
  - Before you Begin: Prepare your Data for Import
  - Import Your Data
    - Step 1: Create a new IP Import Job
    - Step 2: Define Columns
    - Step 2.5: Missing References
    - Step 3: Reviewing Data
    - Step 4: Execute Import
    - Post Import Followup
  - Additional Information

Methodology

The Import from CSV tool will create Top-Level Aggregates and place blocks under those aggregates based on the following method:

First, the importer will parse through the provided data, order all blocks from largest to smallest, then attempt to split the largest block out of an existing block matching the IP space and RIR. If that fails (no larger block exists), then that block is added in the system as its own Top-Level-Aggregate. Subsequent blocks will undergo the same process.

This method ensures that your list of IP blocks does not need to be organized in any particular order.

If your import includes a large number of small blocks (/30s, /32s), be sure you've included at least one large block which encompasses them (/24, /22). This will ensure that the smaller blocks are neatly organized under the larger block, rather than imported as their own Top-Level Aggregates.

Before you Begin: Prepare your Data for Import

The Upload / Import from CSV tool requires only a .csv file for importing.

Be sure to review "Preparing Data for Import" on the Importing your Data page before you begin. Verify that your .csv is correctly parsed and cleanly formatted with your IP block information (using your choice of the available field list shown below), and is UTF-8 encoded for best results.

Common normalization steps required for ProVision IP imports include:


- Remove any empty rows in the data range

- Remove any empty columns in the data range
- Remove stray data from inside and outside the data range, such as:
    - notes, comments, and placeholder text as field values, when not set as their own data column
    - nested secondary information located in additional rows under a primary record
- Ensure proper data formatting
    - Check for data formatting errors - a common issue is leading zeros being dropped from a ZIP field when a file is opened. Re-specify format as needed.
    - Ensure each field has consistent formatting for values

Data Encoding Format

⚠ To ensure correct importing of any special characters, make sure to use UTF-8 encoding for your CSV file!

This tool supports the following fields:



Required Fields

⚠ For IP Import from .csv, the following fields are REQUIRED:


- CIDR String OR both IP and Mask
- RIR OR a selected default RIR

All other fields are optional.

Import Your Data


Step 1: Create a new IP Import Job

Navigate to the **Data Import** Tab from the **Admin** button. Select "Upload / Import from CSV" under "IP Import".



Create a Job Name and Description for the import. This is especially useful to keep track of progress in cases the data arrives from multiple sources, or will require multiple stages of manual review.

Select the .csv file that you prepared above by selecting the "Choose File" button, and browsing to the correct file location. Then hit "Start Import".




Working with Large or Multiple Data Sets

Although you cannot add new files to an existing job, for jobs with multiple sources for data (which may have different formatting), you can simply create separate jobs and descriptions for each source - no need to manually combine the data into one file before importing. The Import tool's mapping and editing functions will allow for the data to be reconciled in ProVision.

For large data sets where multiple stages of manual review might be needed, you can create a new job using the same set of data files in order to work in parallel on a different portion of the data.

After importing, the new job will appear under the "Existing Jobs" section. To continue working with this job, select it from the list (by clicking on the link) and the next step will appear on the page.




Step 2: Define Columns


Using the dropdown menu above each data field, select the appropriate definition for each of the imported columns.

- **CIDR** or **IP/Mask** fields must be provided
- **Notes, Tags,** and **Regions** may have multiple columns associated with the data.
- If you do not have a defined **RIR** column, you must select a default RIR to associated the blocks to.

Other columns which do not apply under the available definitions should be left as blank, and will be skipped during the upload process.



Make sure that you have defined all desired fields by using the scroll bar below your data to view additional columns.



When completed, hit "Next".


Step 2.5: Missing References

If references exist in your data that do not currently exist in ProVision (such as new tags or resources) the import tool will alert you to the missing references, and give you the option to create those references in ProVision. If you wish to add these elements, select the checkboxes next to the element and click the "Add (Element name)" button below.

Header Rows

If your .csv has a header row as the first line, that row may give information that produces a missing reference notice - such as "Tag", "Region", "Block", and so forth.

If this is the case, simply uncheck that item and add only the desired references.



In this example, we get a notification that we are missing a tag named "Tags". However, we know by looking at our data that is simply an item that was part of the header line in the .csv, so we want to bypass this step.

Step 3: Reviewing Data


After supplying the file and defining columns, a review step is provided. Records with errors will show as color coded, and can be filtered to be viewed by All, Valid, Warnings, Invalid, or Ignored.

From here, the records can be edited or ignored. Select "Ignore" for records that you do not wish to import at this time. Records that are Ignored or Invalid will automatically be skipped.


Header Rows

If your .csv has a header row as the first line, that row will be shown as the first record in review data as well. Simply click "Ignore" on the first record to disregard the row.

If warnings or invalid entries are found, you may edit the data by clicking the "Edit" button.




Here you can edit the invalid field, or add /change information for any other available field.




After editing, hit "Save". If the edits are valid, the background color for the data row will be white.

Continue reviewing and editing data as desired. When done, proceed to Step 4.




Step 4: Execute Import

When the review step is completed, hit the "Execute Import" button. A progress bar will appear to show progress and note errors if they occur.



When the bar reaches 100%, the import is complete. The Data Review section will show which data rows were successfully imported.




Post Import Followup

After the Import is complete, there are a few followup options for working with the import job or imported blocks. We recommend:

- Reviewing the imported blocks in the IPAM Tab, adding additional IPAM data, custom metadata, rules, or subassignments. See Working with IP Blocks and Working with IP Rules.
- If the IP Import was only partially successful or requires additional review, you may keep the import job in the "Existing Jobs" list and revise the failed / invalid blocks at a later time. Re-running the import from the same job will allow you to re-attempt import on only the previously unsuccessful / ignored / edited blocks - successfully imported and unchanged blocks will not be affected.

If the IP Import was fully successful, and you do not wish to retain the job data, the Import Job may be deleted from the "Existing Jobs" list by clicking the delete icon next to the job name.



Deleting an import job is permanent and non-recoverable!

When working with large or sensitive import jobs, consider performing a backup of your instance before and after the import job as a safeguard.

Additional Information


See the following areas for information on working with IPAM / IP Blocks post-import:

- IPAM Tab
- Working with IP Blocks
- Working with IP Rules
- IPAM Administration

Import Aggregate Blocks

Import Aggregates


Importing blocks from your RIR Source IP is available from the **Data Import Tab** in the Admin area of ProVision. This feature uses the RIR Org ID to identify a Source IP and determine blocks assigned to your organization that are available for import.



- Import Aggregates
  - Import from RIR
    - Step 1: Lookup from Source IP
    - Step 2: Import your aggregate blocks
    - Step 3: Customizing Block Data
  - Additional Information


Import from RIR

From the **Data Import Tab,** select "Import from RIR" under "IP Import".



Step 1: Lookup from Source IP

We automatically lookup your ARIN or RIPE information based on the IP address you are connected to:




If you have another source IP that you would like to use for the lookup function, you can edit the IP and click on the "Inquire Again" button.
If the organization name and ORGID are correct, then click on the "Confirm" button to go to the next screen.

Step 2: Import your aggregate blocks

Once we have identified the blocks assigned to your company, you can import the aggregates by pressing the "Add Aggregate" buttons.

This page allows you to add both 1918 aggregates as well as public IP space from ARIN and RIPE.



When done adding aggregates, hit the "Continue to ProVision" button at the bottom of the page.



You will be redirected to the **IPAM** tab to manage the aggregates as desired.

Step 3: Customizing Block Data

With your aggregates added, you are now ready to customize the tool and import additional data! From here, you can manage your aggregates under the **IPAM** tab, edit administration functions under **IPAM Admin**, or import resources using the Resource Import Tool.

Additional Information


See the following areas for information on working with IPAM / IP Blocks post-import:

- IPAM Tab
- Working with IP Blocks
- Working with IP Rules
- IPAM Administration

Import DNS Zones

Importing DNS Zones

ProVision offers multiple DNS zone import options, available under the Data Import tab in the the Admin section of ProVision. Additional Import options may be available on zone or server pages.



DNS Global Import Options

ProVision offers various DNS zone import options available under the **Data Import** tab in the the Admin section of ProVision:

BIND Zone Import

- Imports using the named.conf configuration file tied to the zones you are uploading, a .zip or .tar file of the zones themselves, and an optional .csv file mapping zones to customers.

PowerDNS Zone Import

- Option is available after configuring a PowerDNS server with a MySQL backend. Connects to the selected server and imports all zones.

InfoBlox Zone Import

- Imports DNS zones using a provided Host, Username, and Password. The InfoBlox import pulls all zones on the InfoBlox LOCAL grid and adds them to a designated Group. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

NS One Zone Import

- Imports DNS zones using a NS One API Key. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

Dyn DNS Zone Import

- Imports DNS zones using a Dyn DNS Customer Name, Username, and Password. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

DNSMadeEasy Zone Import

- Imports DNS zones using a DNSMadeEasy API Key and API Secret. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

IPPlan Zone Import

- Imports DNS zones using IPPlan MySQL database options. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

Additional DNS import options may be available on a per-zone or per-server level, accessed from the **DNS** Tab:

DNS Zone Import Options (Individual)

DNS Zone / Record Import:

- This tool is available on a zone's "View Zone" page, and allows the user to import additional zone/record information into an existing ProVision zone by uploading a zone file (.zone).


Import Zone / Import Records

A zone file (.zone) may be imported into a ProVision zone to populate record data. Note: To import the record data, the zone must already exist in ProVision - although it may be an empty placeholder zone if necessary.

Enable Saving Import Files (Admin Setting - Optional)

Before you import a zone file, you may (optionally) select to save the import file to the zone. Saving the file allows you to later re-download it directly from ProVision.

To enable saving import files, go to Admin Preferences DNS Settings sub-tab. From there, select "Import Settings" in the DNS Global Settings module.




Toggle "Keep Import File" into the ON position, then select "Save Changes".


Import Zone File

To import a zone file to populate record data in ProVision, go to the View Zone page for the zone. The zone must already exist in ProVision, although it may be empty

Click "Import Zone" on the View Zone page.




A Zone Import dialog box will open. Next to **Zone File:**, click "Choose File" and select your .zone file to import. Then, select an import policy to follow.




When done, Click "Import Zone".

Importing Zone file with Comments

DNS Zone Import will also import comments contained in the .zone file, such as an internal change log (as seen in the image below).



During import, these comments are added to ProVision's zone comments field:



Additional Information

Continue to the following sections for details on performing each import method:

- BIND DNS Zone Upload / Import

- PowerDNS Zone Import
- InfoBlox Zone Import
- NS One Zone Import
- Dyn DNS Zone Import
- DNSMadeEasy Zone Import
- IPPlan Zone Import

BIND DNS Zone Upload / Import

BIND DNS Zone Import

The BIND DNS Zone Upload / Import tool uses the named.conf configuration file tied to the zones you are uploading, a .zip or .tar file of the zones themselves, and an optional .csv file mapping zones to customers. The following steps are used when importing BIND DNS zones:

- BIND DNS Zone Import
  - Preparing your DNS Zones for Import
  - Importing your DNS Zones (BIND)
    - Video Walkthrough
    - Step 1: Create a new DNS Import Job
    - Step 2: Map Data Columns (Optional)
    - Step 3: Reviewing Data
    - Step 4: Execute Import

Preparing your DNS Zones for Import

If your zone data is currently in BIND format - this is very straightforward.

There are three components for the upload process:

1) The named.conf configuration file tied to the zones you are uploading (required)

This tells the importer the Zone Name and where the zone file is written. It could be as simple as a multi-line file:

Simple DNS Config File

```
zone "my-zone.com" { type master; file "my-zone.com.zone"; };
zone "my-other-zone.com" { type master; file "my-other-zone.com.zone"; };
zone "my-third-zone.com" { type master; file "my-third-zone.com.zone"; };
```

or could be more complex like this file structure directory:

Complex DNS Config File

```
zone "my-zone.com" { type master; file "/usr/local/zones/my-zone.com.zone"; };
zone "my-other-zone.com" { type master; file "/usr/local/zones/more/my-other-zone.com.zone"; };
zone "my-third-zone.com" { type master; file "/usr/local/zones/more/even more/my-third-zone.com.zone"; };
```

This configuration file can be taken directly from the DNS server, and can be in either ISC BIND or NSD format. The system auto-detects which one is being supplied.

For a sample Simple Config: conf.conf

2) A ZIP or TAR file of the DNS zones themselves (required)

This is as it sounds - a file archive where we can find the zones and it should match the configuration file uploaded in Step 1.

Zone Order

⚠

These zone files can be in any order, or in sub-directories, so long as the configuration file (Step 1) correctly points to them

For a sample simple ZIP: zones.zip

3) Match CSV for assigning DNS Zones to Resources (optional)

This file allows the administrator to "assign" zone files to a given Resource. If you have Imported a group of Resources, they have Resource IDs associated with them. You can then import DNS zones and assign them to those Resource IDs. When complete, you will be able to pull up the Resource Record and see the DNS Zones associated to that Resource ID.

Sample CSV File

```
my-zone.com,test-01,fun stuff, 174.23.14.4, 174.23.14.9
my-otherzone.com,test-02,great stuff, dns1.dns.net, dns2.dns.net
even-reverse-zones.arpa,test-03,amazing stuff
```

Note the columns are the "Zone Name", the "Resource ID", "Notes", "Master Server", "Slave Server"

Importing DNS Server Linkages

When importing zones, you can use the "Master Server" and "Slave Server" columns to assign zones to specified DNS Servers. Please note that the IP address or FQDN of the DNS Server is supported in this field.
To successfully map to a DNS server, that server must already exist within Provision.

For a sample CSV: config.csv


Importing your DNS Zones (BIND)

Video Walkthrough

Note: Video walkthrough is from ProVision version 5.1.x - however, import steps and descriptions still apply to current version. Updated videos are in progress!


Step 1: Create a new DNS Import Job

Navigate to the **Data Import** Tab from the **Admin** button to import your data. Select "BIND Zone Upload/Import" under "DNS Import".



Under the "New Import" section, select the DNS Group under which you want the zones to be imported, then create a Job Name and Description for the import. This is especially useful to keep track of progress in cases the data arrives from multiple sources, or will require multiple stages of manual review.

Select the appropriate **Configuration File** (required if the .zip is not a flat archive file), **Archive File** (required), and **CSV File** (optional) that you prepared above by selecting the "Choose File" button(s) under each section, and browsing to the correct file location. Then hit "Start Import".




Working with Large or Multiple Data Sets

Although you cannot add new files to an existing job, for jobs with multiple sources for data (which may have different formatting), you can simply create separate jobs and descriptions for each source - no need to manually combine the data into one file before importing. The Import tool's mapping and editing functions will allow for the data to be reconciled in ProVision.

For large data sets where multiple stages of manual review might be needed, you can create a new job using the same set of data files in order to work in parallel on a different portion of the data.

After importing, the new job will appear under the "Existing Jobs" section. To continue working with this job, select it from the list and the next step will appear on the page.



Step 2: Map Data Columns (Optional)


If you chose to load an optional match CSV file to assign DNS Zones to Resource, a mapping step will be available. Otherwise, proceed to Step 3: Reviewing Data.

For DNS imports, two column definitions are available: **Zone** and **Resource Holder ID**. Using the dropdown menu, select the appropriate column for the zone name and Resource Holder (customer) associated with zone. The Resource Holder ID field will be used to set the Parent Resource of the individual zone once imported.

Server associations will not be imported. Instead, the associated server will be the server attached to the selected DNS Group.


Other columns which do not apply under the available definitions should be left as blank, and will be skipped during the upload process.

When completed, hit "Next".




Step 3: Reviewing Data

After supplying the file set and defining columns (if applicable), a review step is provided. The configuration file is broken into individual jobs, scanned for errors, and shown by row (in batches of 100) to be reviewed. Zones with errors will show as color coded. and can be filtered to be viewed by All, Valid, Warnings, Invalid, or Ignored. From here, the zone can be edited or ignored.




To edit the zone name or select a different Resource Holder, hit "Edit" on the zone record.

After editing, hit "Save", and continue reviewing / editing data as desired.




Step 4: Execute Import

When the review step is completed, hit the "Execute Import" button. A progress bar will appear to show progress and note errors if they occur.



When the bar reaches 100%, the import is complete.



PowerDNS Zone Import


PowerDNS Zone Import

The PowerDNS Zone Import Option is available after configuring a PowerDNS server with a MySQL backend. It connects to the selected server and imports all zones.

- PowerDNS Zone Import
  - Step 1: Verify PowerDNS server setup
  - Step 2: Import your PowerDNS zones


Step 1: Verify PowerDNS server setup

To import PowerDNS zones, first ensure the PowerDNS server has been set up under the **DNS** Tab, DNS Servers section (see: Working with DNS Servers and configuring a PowerDNS server).




Step 2: Import your PowerDNS zones

Once server setup has been verified, navigate to the **Data Import** Tab in the Admin section. Select the "Power DNS Zone Import" link.



Then, to import your data simply choose your PowerDNS server and click "Import".



InfoBlox Zone Import

InfoBlox Zone Import

The ProVision Data Import InfoBlox option imports InfoBlox DNS zones using a provided Host, Username, and Password. It pulls all zones on the InfoBlox LOCAL grid and adds them to a designated DNS Group. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

- InfoBlox Zone Import
  - Step 1: Verify DNS Group setup
  - Step 2: Verify InfoBlox server setup
  - Step 3: Import your InfoBlox zones

Step 1: Verify DNS Group setup


It is recommended to have a DNS Group created in advance with the proper default parameters and records to be inherited by the imported InfoBlox zones and records.

Review the existing DNS Groups in the **DNS** tab, and create a new DNS Group if necessary. See Working with DNS Groups for details on editing or creating DNS Groups.


Step 2: Verify InfoBlox server setup

Although it is not strictly necessary to have the InfoBlox server created in ProVision prior to import, creating or verifying the server at this point gives you an opportunity to test the connection and attach the InfoBlox server to the DNS Group selected in step 1.


Go to the **DNS** Tab, DNS Servers section, and either verify that the desired server is shown in the server list, or click the "Add Server" button to create a new InfoBlox server.



If creating a new server, ensure that "InfoBlox" is selected for the DNS Service.




Under the "DNS Group Settings" section of the server detail page, ensure that the DNS Group from step 1 is selected as the server's Attach to Group setting, and click "Save".




Step 3: Import your InfoBlox zones

Once server setup has been verified, navigate to the **Data Import** Tab in the Admin section. Select the "InfoBlox Zone Import" link.



Then, enter the InfloBlox server Host, Username, and Password. Select Forward or Reverse zone type, the InfoBlox view, and the ProVision DNS Group to add the zones to.

Once all information has been entered, click the "Import" button.



The import may take a couple of minutes. If errors occur, they will show under the Pull in Progress message.

When completed, a successful import will show a green Complete! status message.

Verify the zones by exiting the Admin area of ProVision, clicking on the **DNS** tab, and reviewing the zones under the Group previously selected for the import.

NS One Zone Import

NS One Zone Import

The ProVision "NS One Data Import" option imports NS One DNS zones using a provided NS One API key. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

- NS One Zone Import
  - Step 1: Verify DNS Group setup
  - Step 2: Verify NS One server setup
  - Step 3: Import your zones

Step 1: Verify DNS Group setup


It is recommended to have a DNS Group created in advance with the proper default parameters and records to be inherited by the imported NS One zones and records.

Review the existing DNS Groups in the **DNS** tab, and create a new DNS Group if necessary. See Working with DNS Groups for details on editing or creating DNS Groups.


Step 2: Verify NS One server setup

Although it is not strictly necessary to have the NS One server created in ProVision prior to import, creating or verifying the server at this point gives you an opportunity to test the connection and attach the NS One server to the DNS Group selected in step 1.


Go to the **DNS** Tab, DNS Servers section, and either verify that the desired server is shown in the server list, or click the "Add Server" button to create a new NS One server.



If creating a new server, ensure that "NS One" is selected for the DNS Service.




Under the "DNS Group Settings" section of the server detail page, ensure that the DNS Group from step 1 is selected as the server's Attach to Group setting, and click "Save".




Step 3: Import your zones

Once server setup has been verified, navigate to the **Data Import** Tab in the Admin section. Select the "NS One Zone Import" link.



Then, enter the NS One API key and the ProVision DNS Group to add the zones to.

Once all information has been entered, click the "Import" button.



The import may take a couple of minutes. If errors occur, they will show under the Pull in Progress message.

When completed, a successful import will show a green Complete! status message.

Verify the zones by exiting the Admin area of ProVision, clicking on the **DNS** tab, and reviewing the zones under the Group previously selected for the import.

Dyn DNS Zone Import

Dyn DNS Zone Import

The ProVision "Dyn DNS Zone Import" option imports Dyn DNS zones using a provided Customer Name, Username, and Password. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

- Dyn DNS Zone Import
  - Step 1: Verify DNS Group setup
  - Step 2: Verify server setup
  - Step 3: Import your DynDNS zones

Step 1: Verify DNS Group setup


It is recommended to have a DNS Group created in advance with the proper default parameters and records to be inherited by the imported Dyn DNS zones and records.

Review the existing DNS Groups in the **DNS** tab, and create a new DNS Group if necessary. See Working with DNS Groups for details on editing or creating DNS Groups.


Step 2: Verify server setup

Although it is not strictly necessary to have the Dyn DNS server created in ProVision prior to import, creating or verifying the server at this point gives you an opportunity to test the connection and attach the Dyn DNS server to the DNS Group selected in step 1.


Go to the **DNS** Tab, DNS Servers section, and either verify that the desired server is shown in the server list, or click the "Add Server" button to create a new Dyn DNS server.



If creating a new server, ensure that "Dyn DNS" is selected for the DNS Service.




Under the "DNS Group Settings" section of the server detail page, ensure that the DNS Group from step 1 is selected as the server's Attach to Group setting, and click "Save".




Step 3: Import your DynDNS zones

Once server setup has been verified, navigate to the **Data Import** Tab in the Admin section. Select the "Dyn DNS Zone Import" link.



Then, enter the Dyn DNS Customer Name, Username, and Password. Then, select the ProVision DNS Group to add the zones to.

Once all information has been entered, click the "Import" button.



The import may take a couple of minutes. If errors occur, they will show under the Pull in Progress message.

When completed, a successful import will show a green Complete! status message.

Verify the zones by exiting the Admin area of ProVision, clicking on the **DNS** tab, and reviewing the zones under the Group previously selected for the import.

DNSMadeEasy Zone Import

DNSMadeEasy Zone Import

The ProVision "DNSMadeEasy Zone Import" option imports DNSMadeEasy zones using a provided API Key and API Secret. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

- DNSMadeEasy Zone Import
  - Step 1: Verify DNS Group setup
  - Step 2: Verify server setup
  - Step 3: Import your DNSMadeEasy zones

Step 1: Verify DNS Group setup


It is recommended to have a DNS Group created in advance with the proper default parameters and records to be inherited by the imported zones and records.

Review the existing DNS Groups in the **DNS** tab, and create a new DNS Group if necessary. See Working with DNS Groups for details on editing or creating DNS Groups.


Step 2: Verify server setup

Although it is not strictly necessary to have the DNSMadeEasy server created in ProVision prior to import, creating or verifying the server at this point gives you an opportunity to test the connection and attach the DNSMadeEasy server to the DNS Group selected in step 1.


Go to the **DNS** Tab, DNS Servers section, and either verify that the desired server is shown in the server list, or click the "Add Server" button to create a new DNSMadeEasy server.



If creating a new server, ensure that "DNSMadeEasy" is selected for the DNS Service.




Under the "DNS Group Settings" section of the server detail page, ensure that the DNS Group from step 1 is selected as the server's Attach to Group setting, and click "Save".




Step 3: Import your DNSMadeEasy zones

Once server setup has been verified, navigate to the **Data Import** Tab in the Admin section. Select the "DNSMadeEasy Zone Import" link.



Then, enter the DNSMadeEasy API Key, Secret Key, and the ProVision DNS Group to add the zones to.

Once all information has been entered, click the "Import" button.



The import may take a couple of minutes. If errors occur, they will show under the Pull in Progress message.

When completed, a successful import will show a green Complete! status message.

Verify the zones by exiting the Admin area of ProVision, clicking on the **DNS** tab, and reviewing the zones under the Group previously selected for the import.

IPPLAN Zone Import

IPPlan Zone Import

The ProVision "IPPlan Import" option imports IPPlan zones using provided MySQL database credentials. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.

- IPPlan Zone Import
  - Step 1: Verify DNS Group setup
  - Step 2: Import your IPPlan zones


Step 1: Verify DNS Group setup

It is recommended to have a DNS Group created in advance with the proper default parameters and records to be inherited by the imported zones and records.


Review the existing DNS Groups in the **DNS** tab, and create a new DNS Group if necessary. See Working with DNS Groups for details on editing or creating DNS Groups.

Step 2: Import your IPPlan zones

Once DNS Group setup has been verified, navigate to the **Data Import** Tab in the Admin section. Select the "IPPlan Zone Import" link.



From there, enter the IPPLAN DB Options - Host, Database Name, MySQL Username, and MySQL Password, then select the desired DNS Group to add the zones under.




The import may take a couple of minutes. If errors occur, they will show under the Pull in Progress message.

When completed, a successful import will show a green Complete! status message.

Verify the zones by exiting the Admin area of ProVision, clicking on the **DNS** tab, and reviewing the zones under the Group previously selected for the import.

Users & Permissions

Users




Users & Permissions is accessed from the Admin screen under the **Users** tab. Here, you will find tools for adding and managing permissions groups, users, and running queries for verifying a user's specific permissions.

- Users
  - The Permissions Structure
  - Video Overview
  - Permission Levels
    - Global Permissions
    - Resource Permissions
    - Table of contents:

The Permissions Structure

The Permissions structure in ProVision is designed to give you as much flexibility as you need to accommodate most use cases. When mapping out the permissions structure for your organization, keep in mind who you want to access to application:

- Internal Users and Roles (Admins, Read Only, etc.)
- Partners related to multiple specific Resources/Accounts
- Customers/Departments with limited view to only their respective Resources/Accounts



In this diagram, we have created groups for each of those scenarios – we have internal groups, Partner Groups, and Customer groups. Each of these groups has access to different resources, permission levels, and users assigned to them.

The components of the Permissions System include:

> **Users:** A User is a single login account that accesses ProVision. Users are assigned to Groups.
>
> **Groups:** A Group is a set of permission conditions that apply to selected Users. Allowed Resources and access levels (C/R/U/D permissions) are set inside the Group.
>
> **Resources & Access:** Inside a Group, Resource access may be set to Global (applies to all Resources), or to the Resource level (applies to only the selected Resources). For each Resource selected, access permissions can be set with C/R/U/D permissions under each ProVision functional area (IPAM, DNS, Resource, Peering).

As a whole, this makes up the ProVision permissions system. The Permissions system allows you to fine-tune access to resource data to be as detailed as you need.

Video Overview

Video overview applicable to ProVision version 5.3.3 and earlier.

Permission Levels

Global Permissions

When you see a reference to a "TLR" - that is a "Top Level Resource". This Is the primary Resource under which all other resources fall under. ProVision currently only allows a single level of administrator permissions: Global Administrator.

Users with "Admin" access can assign/modify permissions for other users.

See Global Permissions for more details on configuring these elements.

Resource Permissions

An administrator can also set respective permissions for a given Resource (single or multiple). These permissions fall under Groups. So a Group is configured for the given group of Resource permissions, and then the User account is added.

See Working With Users and Groups to learn how Resource Permissions are assigned.

See Resource Permissions for more details on configuring these elements.

Table of contents:

- Global Permissions
- Resource Permissions
- Working With Users and Groups
- Verifying Permissions

Global Permissions

Global Permissions

Global Permissions apply to the "TLR" or "Top Level Resource" within ProVision. By default, ProVision includes two groups with Global Permissions access - Global Admins and Global Read-Only. Initial Users are typically placed in the "Global Admins" group, and have administrative access to the entire platform. Global Read-Only users have full access to the platform, but with only read permissions.

Administration of these permissions require Administrative privileges. As an Admin, the user can then assign global permissions to groups and users. Depending on the requirement, the user can also have Resource specific permissions depending on how their group is configured.

Global Permission Details

Global groups are visible under the "Groups" section of the **Users** tab. In addition to the two default Global groups, new Global groups may be created through the "Add Group" button.


Under the resource selector, chose the "TLR" Resource ("Top Level Resource"), and then check permissions as desired.



Global groups may also be edited just like standard groups, through selecting the Action Menu (Wrench Icon) to bring up the group information details. Groups may be deleted by selecting the red circle icon.



Group details are the same for Global groups as for non-global groups, excepting that the resource selected is TLR (Top Level Resource). You may choose to edit the name, enable/disable the group, show or hide C/R/U/D permission details, and view users assigned to that group. Be sure to save any changes after editing.



Details on each global permission option is as follows:

Global Permission	Description
Create	Ability to create records of a certain type
Read	Ability to read records of a certain type
Update	Ability to update existing records of a certain type
Delete	Ability to delete records of a certain type

Functional Area	Description
IPAM	IP Address Management functionality - this covers the IPAM Tab in addition to the IPAM "Gadget" that can be present in Resources.
Peer	Peering functionality - covers the Peering Tab, both the Communication Manager and the Session Manager.
Resource	Resource functionality - this controls access for Resources depending on either the TLR or the individual Resource(s) selected. DNS zones, records, and servers are included as "Resources".
User	User/Group management - this controls access for User and Group functions within the administrative area for ProVision.
SWIP*	This affects the SWIP/RPSL integration for ARIN/RIPE. This way a user can either be enabled to have this capability or not.
Admin*	This controls whether a user is an administrator for the global ProVision application. Note: This does not confer any additional permissions on a per-resource level.

*
SWIP and Admin functions are only visible when Show Details is selected

Additional Information

For more information on Users and Groups, see the following areas:

Users & Permissions

Resource Permissions

Working With Users and Groups

Verifying Permissions

Resource Permissions

Resource Permissions

Resource Permissions apply to designated Resources within ProVision. Rather than allowing a user full access to the ProVision platform, you can choose to limit a user's access to only certain resources or functional areas.

Administration of these permissions require Administrative privileges. As an Admin, the user can then assign resource permissions to groups and users.

Resource Permission Details

Resource Permission groups are visible under the "Groups" section of the **Users** tab. New groups may be created through the "Add Group" button.

Under the resource selector, chose one or more resources for which you want to define permissions, and then check permissions as desired.

Additional Resources may be added to the list by clicking on "Add more Group Permissions".

Keep in mind when working with individual Resource permissions that tasks which require moving entities (zones, IPAM blocks, attaching servers, etc) from one resource to another, require the user to have permissions on both the originating Resource and the destination Resource.

Thus, moving IP blocks from "6connect Labz" to "7connect Labs" requires the user to have IPAM and Resource permissions on both Lab resources.

Similarly, attaching a DNS server to a DNS Group requires Resource permissions on both the DNS Group and the intended DNS server to attach.

Here, we show making a group called "Some Lab Group", whose users we want to be able to access two resources: 6connect Labz and 7connect Labs.


These users will be working extensively in IPAM and Resources, so we give them full access to those areas of ProVision.



However, we also want them to view other information in Peering and Users, but not edit it.

Click on "Show Details" to fine-tune the permissions, and then check the "R" column under Peer and User.

Lastly, hit "Save" to save our changes.



Details on each resource permission option is as follows:

Resource Permission	Description
Create	Ability to create records of a certain type
Read	Ability to read records of a certain type
Update	Ability to update existing records of a certain type
Delete	Ability to delete records of a certain type

Functional Area	Description
IPAM	IP Address Management functionality - this covers the IPAM Tab in addition to the IPAM "Gadget" that can be present in Resources.
Peer	Peering functionality - covers the Peering Tab, both the Communication Manager and the Session Manager.
Resource	Resource functionality - this controls access for Resources depending on either the TLR or the individual Resource(s) selected. DNS zones, records, and servers are included as "Resources".
User	User/Group management - this controls access for User and Group functions within the administrative area for ProVision.
SWIP*	This affects the SWIP/RPSL integration for ARIN/RIPE. This way a user can either be enabled to have this capability or not.
Admin*	This controls whether a user is a administrator for the global ProVision application.

*
SWIP and Admin functions are only visible when Show Details is selected

Additional Information

For more information on Users and Groups, see the following areas:

Users & Permissions


Global Permissions

Working With Users and Groups

Verifying Permissions

Users and Groups

Managing Users and Groups




Users and Groups are managed from the Admin area of ProVision, under the **Users** tab. Both Global and Resource level groups are shown.

- Managing Users and Groups
  - Users Overview
    - Creating/Editing User Accounts
    - Setting/Resetting User Passwords
    - Removing a User
  - Groups
    - Default Groups
    - Add or Edit a Group
    - Removing a Group
  - Additional Information


Users Overview

A User is defined as a single login account that accesses ProVision. In the Users section, users may be added, edited, assigned to groups, have password information reset, or be removed.



Creating/Editing User Accounts

Add Users by click on the "Add User" button at the bottom of the "Users" section of the page. The Edit User dialog will pop up.




You can also bring up the same dialog to edit a user's information by clicking on the Action Menu (wrench icon) at the end of the row for the user.



When creating or editing User accounts, you will be presented with the following options.

You may enter or edit the Username, First Name, Last Name, whether to enable help bubbles, and select one or more permissions groups to which to assign the user.



When assigning users to multiple permissions groups, be sure to review the group permission details to ensure that they do not conflict with eachother!


Setting/Resetting User Passwords

When you click on the padlock icon, you will be presented with options to set a new password and/or send a password reset email to the intended user account.



From here, you can choose a new password, or use the automatically generated random password.

If you select the checkbox next to "Send email?", email fields will appear that may be edited as desired. When complete, hit "Send".



Removing a User

To remove a user from the Users list, click on the red circle "delete" icon next to that user.



Groups

ProVision administrators can also create permission groups to assign users to. This allows more control over user roles.


A Group has four elements associated with it:

Users: The Users that are assigned to the group, and will be limited by the selected permissions.

Resources: Resources access may be set to Global TLR (applies to all resources), or to the level of individually selected resources.

Functional Area: The ProVision functional area (IPAM, Resources, Peering, etc) for the selected resource(s) that permissions are set under.

Permission Level: Create, Read, Update, and Delete (C/R/U/D) permissions may be set under each functional area for each resource selected.



In the example above, the group “MyGroup” allows the users Bob Smith and Jane Doe to only read IPAM and DNS data for the Resource “Awesome Co”.

Through the use of these four elements, Groups can create permissions structures that are as flexible as you need.

Default Groups

Two default groups are available initially in ProVision:

- Global Admin (May not be edited or deleted)
- Global Read-Only

These Global groups allow for access to the entire ProVision platform. You may add additional Global groups by creating a new group using the TLR (Top Level Resource). You may also add detailed resource level group permissions by selected individual resources.

For more detail on top-level and resource permissions, see Global Permissions and Resource Permissions.

Overlapping group and user permissions

Permissions are inherited based on the hierarchy of the objects, unless you specify a different permission!

Add or Edit a Group

New Groups can be created by ProVision administrators by pressing the green "Add Group" button. To edit a group, you may click on the Action Menu (wrench icon) for the group.



After hitting the "Add Group" button or wrench icon, the Group Information screen will pop up.




Add in the name of the new group, and set the permissions for that group by defining the resource(s) in the dropdown menu, checking the functional areas that you want accessible.

Click "Show Details" to fine tune the functional areas into Create/Read/Update/Delete level permissions.

To add permissions for additional Resources, click "Add More Group Permissions", select the Resource, and check the desired permissions.

To delete a Resource from the permissions list, simply click the red icon.


In the example below, we make a group called "Some Lab Group", whose users we want to be able to access two resources: 6connect Labz and 7connect Labs. These users will be working extensively in IPAM and Resources, so we give them full access to those areas of ProVision. However, we also want them to view other information, but not edit it. We click on "Show Details" to fine-tune the permissions, and then check the "R" column under Peer and User.



Click "Save" when complete. After adding the group, you can add users to the group by selecting the group when editing a user account.

Removing a Group

To remove a user from the Users list, click on the red circle "delete" icon next to that user.



Note: Users cannot edit or delete permissions for the Group to which they currently belong, unless they are also a member of the default Global Admin Group.

Additional Information

For more information on Users and Groups, see the following areas:

Users & Permissions

Global Permissions

Resource Permissions

Verifying Permissions

Verifying Permissions

Verifying Permissions


- Verifying Permissions
  - Check User Permissions
  - User Permissions Chart
  - Additional Information

Check User Permissions

Users & Permissions is accessed from the Admin screen under the **Users** tab. Here, you will find tools for adding and managing permissions groups, users, and running queries for verifying a user's specific permissions.


To verify the permissions of a certain user, simply select their user account from the dropdown menu, the resource you are checking against, and click on the green "Query" button.

The resulting output will display the detailed permissions for that user and resource combination, as well as list groups effecting the user.




User Permissions Chart

The User Permissions Chart is accessed from the bottom of the **Users** tab page. Click "Go to Chart" and the chart page will open.




You can graphically view the permissions level of a user by selecting their user name and group from the dropdowns at the top of the chart. The resulting chart will be color coded depending on permissions level.



Single clicking on a filled circle resource node will expand and collapse the node.

Double clicking on a resource will open up the Edit Permissions box, where CRUD permissions may be updated for allowed Resources. Check / Uncheck the desired permissions level, and click save.



Additional Information

For more information on Users and Groups, see the following areas:

Users & Permissions


Global Permissions

Resource Permissions

Working With Users and Groups

API Tab

API Tab



The **API** tab provides links to APIv1 / APIv2 documentation and beta Reverse API management. It also allows you to create and manage APIv1 keys for users.

APIv2

APIv2 documentation is available at ProVision Developer Tools and APIv2.

Detailed endpoint descriptions are available at APIv2 Swagger Documentation, or from the instance-specific link provided on the API Tab page / Navigation dropdown.

APIv1

An APIv1 area is provided for legacy users, containing a link to APIv1 Documentation and a tool to create / revoke APIv1 access keys.


Create / Revoke a Key

To create a key, simply select the user, and click on "Generate Keys".



The Name, Username, API Key, Secret Key, and Created date information will be added to the list below.

To revoke a user's key, click "Revoke" at the end of their entry.



For detailed information on working with API features, please refer to ProVision Developer Tools, API v1, and APIv2 Swagger specifications linked in your instance on the API page.

Table of Contents:

- Reverse API UI


Reverse API 1

Reverse API User Interface


- Reverse API User Interface
  - Add a New Endpoint
  - Delete an Endpoint
  - Edit an Endpoint
  - Displaying the Endpoint

This is a beta feature

The Reverse API endpoint builder is accessed from the Admin section of ProVision, under the **API** tab.



Clicking on the link from the dropdown menu, or from under the "Reverse API" section (circled above) will take you to the Reverse API Endpoint Builder interface.



Add a New Endpoint

To add a new endpoint


1) Select "Add a New Endpoint" next to "Endpoint".



2) Type in the desired endpoint name and call




3) Review / Edit the presentation Javascript as desired for your output



4) Save your new endpoint



5) Test the call on a selected Resource by selecting a Resource from the dropdown, then hitting the "Test" button.



Note: The selected Resource must have a Reverse API gadget enabled section! See Customizing Sections and Gadgets for information on enabling gadgets for a section.

Delete an Endpoint

1) Select the endpoint name next to "Endpoint".



2) At the bottom of the screen, click "Delete Endpoint"




Edit an Endpoint

1) Select the endpoint name next to "Endpoint".



4) Save the endpoint



Displaying the Endpoint


The created Reverse API endpoint may be added to the Reverse API Console Gadget, and shown on a Resource's Entry Page.

To add the Reverse API Gadget to a Section, see Customizing Sections.

For information on working in the Gadget, see Gadgets.

Scheduler

Scheduler



The Scheduler tab allows you to manage and schedule repeating tasks in ProVision.

- Scheduler
  - Available Task Types
    - Enter Task Details
    - Add Repeat Settings
    - Verify Repeat Settings and Save
  - Managing Tasks
    - Activate / Deactivate Tasks
    - Edit a Task
    - View Task Log
    - Delete a Task

Available Task Types

Many predefined task types are available through the scheduler:

- **Approvals - Delete events older than 1 month:**

  The "Approvals - Delete events older than 1 month" task deletes any Approvals history events older than 30 days. It is recommended to run this task monthly to clear out obsolete approvals items and reduce approvals page load time. For information on working with Approvals, see DNS Tab and Approvals.

- **Approvals - Process Subscription Events:**

  The "Approvals - Process Subscription" task processes approval request events and handles the sending of notification emails to subscribed Approvals Groups. If Approvals are in use with notifications, it is recommended to create this task with a run time of "every 5 minutes" and no end date. For information on working with Approvals, see DNS Tab and Approvals.

- **Backup - Backup the database**

  Performs a data backup to the 6connect cloud servers, or to a selected resource server existing in ProVision.

- **Backup - Delete old archived data and logs:**

The "Delete old archived data" task removes data older than 30 days from archived resources, logs, systems logs, and statistics from your ProVision instance. Be sure to use care with running this task to prevent accidental deletion of log data that may still be necessary for reference. It is typically recommended to run this task once every 1-3 months to reduce log data volumes.

- **DHCP Leases Monitor:**

Updates lease monitoring and checks for lease expiration for the DHCP module. See DHCP Tab for additional information on setting up DHCP Servers and Push options.

- **DHCP Server Push:**

Pushes configuration updates to the selected DHCP server(s). Select push to a single server, or all DHCP servers. See DHCP Tab for additional information on setting up DHCP Servers and Push options.

- **DNS Error Monitor:**

Checks the DNS records in theError state to determine if they have been fixed. Default setup is once a day, and you can set it to run more often if necessary. This task may replace or supplement the manual DNS Zone / Record "Check" button, depending on set frequency.

- **DNS Resource Monitor:**

Checks Records/Zones periodically to monitor DNS server response.

- **DNS Zone Transfer:**

Pushes zone updates to the DNS servers. Select pushes to apply to all zones in a DNS Group, all zones on one server, or one particular zone. Requires the intended Group / Server / Zone to already exist in ProVision. See DNS Tab for additional information on setting up DNS Servers, Groups, Zones, and Push options.

- **DNS Zones Backup Removal:**

Removes DNS Zone backups that are older than the "Days to preserve" setting in the Scheduler Task. See DNS Tab for additional information on setting up DNS Servers, Groups, Zones, and Push options.

- **GEO IP Exporter:**

The Geo IP Exporter searches the ProVision instance for resources which have IP addresses and an address provided in the Contact Info Gadget, then saves the resulting .csv to the ProVision root directory.

- **IPAM Alerts:**

Set a time / frequency for IPAM aggregate alert emails to be sent to alert recipients. Alert recipient email and available space threshold percentage is set through the action menu for individual aggregates under the IPAM Tab. For information on setting up an alert for an aggregate, see Working with IP Aggregates. This task is created/enabled by default.

- **IPAM - Process Holding Tank:**

Removes IP Blocks from the Holding Tank and returns them to the available pool. See Holding Tank Management.

- **IPAM - Rotate Dynamic IPs:**

The Scheduler task "Rotate Dynamic IPs" reassigns single IPv4 NAT addresses (/32s) after 'x' days post-config to an available address denoted by the Dynamic_Available tags.

Prior to using this task, two blocks (one public, one private) must be NAT'ed in IPAM, the NAT Config pushed to a router, and appropriate blocks tagged with "Dynamic_Base" and "Dynamic_Available". For information on working with NAT'ed Blocks, see Working with IP Blocks .

- **Rotate Logs:**


Removed Log items older than the "Delete Logs older than X days" setting in Admin Preferences.

- **Test Task**:

Tests the scheduler and notification system - it simply sends a notification email to the provided address at the specified run time.

Add Task

To add a new scheduled task, hit the "Add Task" button below the Scheduler task list. You will then see the Task Detail Settings area.



Enter Task Details

Under "Task Detail", fill in the following fields:

Name: Create a name for your task

Task: Select a pre-created task from the dropdown menu.

Process Holding Tank Settings: When selecting the Process Holding Tank task, you will have the following setting options:

> **Email From / Email To**: Enter an email address to send task notifications from, and the desired recipient. This is an optional setting.

DNS Zone Transfer Settings: When selecting the DNS Zone Transfer task, you will have the following setting options:


> **Select Action Type / Select Server:** When selecting the DNS zone transfer task, you can choose the action type to a) push all zones to all servers b) push all zones on a single server (then select server) or c) push one zone (then select zone).

Backup the Database Settings: When selecting the Backup task, you will have the following setting options:

> **Email From / Email To**: Enter an email address to send task notifications from, and the desired recipient. This is an optional setting.
>
> **Location:** Choose "Cloud" to save the backup to the 6connect cloud, or "Server" to save to a specified server resource already defined in ProVision. If "Server" is selected, choose the server resource from the dropdown list.


Start: The start date you wish the task to begin repeatedly occurring. By default, the current day is entered.

End: The date you wish repeat settings to end. For one-time tasks, enter the next calendar day after the start (run) date. To have a task run indefinitely, leave the end date blank



Add Repeat Settings

Add repeat settings for your tasks. First, select your repeat type - hourly, daily, weekly, monthly, or none (one time). The type that you select will prompt different additional setting options.



Repeat Type options and details:

Hourly: Selecting the hourly repeat type will then prompt for the number of repeat times per hour - every 5,10, 15, 20, 30, or 60 minutes. All minute selections start from the top of the hour. For example, if every 20 minutes is selected, the task will run at :00, :20, :40 during each hour.

Daily: Selecting the daily repeat type will prompt for the specific time to repeat the task, and which days you wish the task to occur. The Repeat Time is based on a 24 hour clock set at UTC time. To assist in any time zone conversions, the current UTC time is shown at the top of the scheduler page.

Weekly: Selecting the weekly repeat type prompts for the specific time to repeat the task as well as frequency by week. Weekly tasks occur on the day selected as the start date. Using the weekly option, you may choose from a range of weekly (every 1 week) to once every two months (every 8 weeks).

Monthly: Selecting the monthly repeat type prompts for a repeat time and a day. For the day option, you can either choose a specific day (ie, the 15th of each month) or a relative day (the 1st Friday of each month).

For Monthly repeat settings, verify that the calendar day you select the task to occur exists! For example, if you select the 5th Saturday of each month, the task will repeat only in months which have 5 Saturdays and skip all other months.


None (one-time): Select the time and day that you wish the single occurrence task to run. (Ensure that "End Date" in task details is set to the day after the desired run date).

After you have selected your Repeat Setting options, click the "Add Repeat Setting" button.

Verify Repeat Settings and Save

When you add repeat settings, they will appear under the "Repeat Settings For This Task" area. Verify your settings, and if desired, you may delete individual repeat settings by hitting the "Delete" button.


When complete, hit the "Save Task" button to finalize your changes and add your new task to the task list.



Managing Tasks

After tasks have been added, they will show in the task list along with their basic settings. The list may be filtered to show all tasks or active tasks only by selecting the radio buttons next to "Show:". Further filtering may be done by typing a Name or Repeat Info keyword into the "Filter Tasks" input box above the task list.

From the task list itself, you can enable/disable tasks, view details, view history, run tasks, and delete tasks.



Filters:

Show: Select "Active" to show only active tasks (checkbox enabled under "Active" for the task), or "All" to show all tasks

Filter Tasks (Text box): To further filter the task list, type a Name or Repeat Info keyword (ie, "Backup" or "Every day") into the Filter Tasks text box.

Task List:

Name: The task name assigned during the "Add Task" creation process.

Repeat Start: The date selected for the repeat settings to start

Repeat Info: The repeat settings chosen for the task.

Last Run: The date and time the task was last run, if applicable.

Active: To activate tasks, simply click the check box under "Active" in the task list. To deactivate a task, uncheck it. By default, tasks are checked as active once created.

Details: This link will bring up the task details and repeat settings, which then may be edited and re-saved if needed.


View History: This link will show the log for task actions.

Run Now: The "Run Now" button will run the scheduled task when pressed, regardless of the scheduled repeat settings.

Delete: Deletes the task.


Activate / Deactivate Tasks

Click on the check box under "Active" for the task




Edit a Task

Click on the "Details" link for the task, then edit the Task Detail and Repeat Settings that appear below as needed.




Hit "Save Task" when finished to save your changes, or select "Cancel" to close the view without saving.



View Task Log

Click on the "History" link for the task.




The log details for the task will be shown below. When done, click on the "Close" button to exit the view.



Delete a Task

To delete a task, hit the "Delete" button at the end of the row in the Task List. You will be presented with message asking if you are sure you wish to delete the task. Click on the "Delete" button next to the message to verify the deletion, or hit "Cancel" to exit without deleting.




Enabling the Scheduler

To enable the scheduler in a local instance, add the following to cron:
* * * * * /path/to/php /path/to/ProVision/scheduler/task-runner.php

Log

Log



The 6connect ProVision log provides detailed information on actions performed in ProVision. The Log is only available to Admin users.


To access the Log, either navigate to the Admin area of ProVision, then click the **Log** Tab, or follow an area-specific Log link.

Log Features

Filters and search options:

Filter the log list by selecting (or typing) the desired filter value at the top of the Log page, then click on the "Search" button.


Additional options are made visible by clicking on the "More Filters" link below "Results per page".




The following filters and options are available:

Primary Filters:


Level: Under the "Level" dropdown box, select "All Levels", "Emergency", "Alert", "Critical", "Error", "Warning", "Notice", "Info", or "Debug".




Category: Under the "Category" dropdown box, select "All Categories", "System", "API" , "Assistant", "Device", "DHCP", "DNS", "IPAM", "NTP", "Peering", "Reporting", "Resource Linkage", "Resource Holder", Resource", "User", or "VLAN".



Results per page: In the "Results per page" text box, type the desired number of log entries to see per page. By default, this value is set to 100.



Search: Type a search string, then click the "Search" button. Search terms may be usernames, resource names, task names, resource or task id numbers, IP's, and so on.



More Options:

Additional detailed filter and search options are available under the "More Filters" link.

- **Log ID:** Retrieve a specific log entry from its log_id parameter.
- **IP:** Search by IP of the machine that created the event in the log.
- **Username:** Filter logs by ProVision username, or by "Unknown" user.
- **Time:** Filter log entries by exact time created. Must be in datetime format (2016-08-14 16:41:18).
- **Time Minimum:** The earliest day and time of log entries to show in results. Must be in datetime format (2016-08-14 16:41:18).
- **Time Maximum:** The latest day and time of log entries to show in results. Must be in datetime format (2016-08-14 16:41:18).


Tip

Use "Time Minimum" and "Time Maximum" together to specify a specific date / time range, such as one 24 hour period:

Log Details:

Clicking on the blue arrow on the left side of each log entry expands the entry to show additional details pertaining to that entry.

Not all fields may be populated, and not all log types may have applicable details.




Detail fields may include:

- **id:** The id of the log detail record.
- **log_id:** The id of the parent log entry (the entry that was clicked to reveal details).
- **type:** Log category value.
- **string_value:** String details.
- **number_value:** For resource type log entries, the number_value is the associated resource id.
- **text_value:** API details for API type log entries.
- **date_value:** Day of the log entry.
- **address_value:** For IPAM type log entries, address_value is the starting integer value of the IP Block.
- **address_end_value:** For IPAM type log entries, address_value is the ending integer value of the IP Block.

Log Chart View


To view the graphical chart version of Logs, click the "chart" toggle on the bottom right of the search fields.

Each log event will be displayed as a color-coded box. You may view log details by hovering the mouse arrow over an event box.




Export Logs

Export the current log search results by clicking the "Export to CSV" button after performing your search.


IPAM Admin
Data Import
Users
API
Scheduler
Log
Approvals
Constraints
Exit Admin
Search or type help
Logs
Results 13974
Level
All Levels
Category
IPAM
Results Per Page
100
More filters
Search
Clear
Export to CSV
Search...
Time
User
IP
Level
Category
Message
2020-06-08 07:53:09
ops@6connect.com
96.35.59.123
Info
IPAM
(API) 1.1.8.64/30 aggregated into 1.1.8.64/29
2020-06-08 07:53:06
ops@6connect.com
96.35.59.123
Info
IPAM
(API) 1.1.8.56/29 aggregated into 1.1.8.48/28
2020-06-08 07:53:03
ops@6connect.com
96.35.59.123
Info
IPAM
(API) 1.1.8.48/30 aggregated into 1.1.8.48/29

Approvals

Approvals




The Approvals module stores and queues DNS actions made by selected User Groups, and sends those actions to a Pending Changes list for administrative review. Later, an administrator (or combination of administrators) can approve or reject these stored actions.

The admin **Approvals** Tab contains two sub-tabs: **Pending Approvals** and **Permission Groups**, which are the primary areas to manage Approvals items.

Currently, **Approvals** is available only for **DNS** related actions, while we gather feedback and use cases to inform possible future updates. If you are interested in providing feedback, a use case, or requests for future additions to the Approvals system, please contact feedback@6connect.com.

- Approvals
- Approvals Tab - Overview
  - Approvals Fundamentals (Before you Begin)
    - Policies
    - Family-Action Types
    - User Groups
  - Sample Group Scenarios
    - Scenario 1: One Approver Group, with Restricted Actions
    - Scenario 2: Multiple Approver Groups/Specific user, with Restricted Families
- Approval Workflows
  - Initial Setup
    - Step 1 - Review Existing User Groups and Process Needs
    - Step 2 - Add or Edit ProVision User Groups
    - Step 3 - Assign Approval Action Settings to Groups
    - Step 4 - Enable Notifications (Optional)
    - Step 6 - Add Scheduler Task: "Approvals - Delete events older than 1 month"
  - Daily Use
- Additional Information

Approvals Tab - Overview



The ProVision Approvals system gives administrators an additional layer of flexibility and oversight to manage which changes are allowed to DNS items by users.

With Approvals, administrators can set group permission rules requiring that certain types of DNS changes made by a user are either 1) automatically denied or 2) approved by an administrator. In the latter case, one or more admin group(s) must be assigned to approve those action types.

Viewing requested changes and managing the group permission rules are both managed from the admin **Approvals** tab, under the **Pending Approvals** and **Permission Groups** sub tabs**.**

Approvals Fundamentals (Before you Begin)

The approvals system revolves around three primary concepts: Policies, Family-Action Types, and User Groups. An understanding of all three is necessary before setting up Approvals, and additional steps may need to be taken to ensure proper use of Approvals - such as creating additional User Groups.

Policies

When setting up Approvals Permission Groups, a policy will need to be selected to apply to the User Group / Family-Action Type combination selected. The set policy determines how the Approvals system handles an attempted change by a member of the associated User Group.

There are three available policies:

- **Deny:** The type of change is immediately denied when a member of the User Group attempts to perform that action.
- **Action to be Approved:** The type of change made by any user in the associated User Group will require an administrative user to approve the change (The approver must be included under a "Must Approve" group for the same action).
- **Must Approve:** A user from the group must approve the action for it to be removed from the "Pending" list, and sucessfully execute. If more than one group is assigned with the "Must Approve" policy for an action, all groups must have a user from that group approve the action for it to execute. If the change has only been partially approved, its status will be "Pending, awaiting approval from others" and no action will be executed until all groups have provided a response to the action.

Ensure that for any group/action set with an "Action to be Approved" policy, another group is set with "Must Approve" for the same family-action type. Failure to provide groups for both submitter and approver may result in changes not being processed, due to not having a user assigned to approve the request.

Family-Action Types

In Approvals, the "Action" listed in the Pending Approval information or when setting Approval Permission Groups will be one of the following change types:

- **Add:** Creating a new Group, Zone, Record, or Server
- **Delete:** Deleting a Group, Zone, Record, or Server
- **Update:** Any change to an item that isn't Add, Delete, or Push - such as a settings change, renaming, or entering a value in a field.
- **Push / BackgroundPush:** DNS Server Pushes - manual or scheduled

It is important to note that Action types in Approvals is related-to-but-different than CRUD permissions as set in User groups - although the "Add" Action type and "Create" CRUD permission seem the same, the action type "Add" only applies to *a specific event* occurring, rather than a holistic overarching system-level permission. In order to perform a certain Approval Action Type, a user must already have the CRUD permissions to attempt it.The CRUD permissions determine whether the user can even view an area or attempt an action to begin with, Approvals Policies on Action Types determine what is done with the Action *after* the attempted change.

Further fine-tuning of the action types for permissions is done by selecting the combination of "Family" (type of DNS item) with the Action Type. DNS Families include DNS Servers, DNS Groups, DNS Zones, and DNS Records. Each type of action can be performed on each family, so when setting up Approval Permission Groups you may choose to set the policy for the entire Family (ex:"All DNS Group actions"), Action (ex:"Add actions for all DNS Families"), or just a specific combination (ex: "Only DNS group Delete").

User Groups

Approvals uses ProVision User Groups to determine which users must have a change approved, denied, or can approve others' actions. Therefore, User Groups must be set up with the appropriate users and basic permissions under each group before using Approvals. For information on setting up User Groups and how the basic permissions structure works in ProVision, see Users & Permissions, Global Permissions , and Working With Users and Groups.

Before using Approvals, a review of your user and User Groups is highly recommended to ensure the following:

- That administrators who will be approving change requests are included in a Global Admin (TLR level + Admin) group, in order to access the "Approvals" tab and perform Approve/Reject responses.
- That users included under the same User Groups are similar in terms of what types of tasks they perform and what level of Approval oversight is needed.
    - Example: If "Group A" consists of seven users - four who will need all Add and Delete actions approved, two who do not, and their manager (who will approve their actions)- you may need to move those users under three groups: 1) A group for those requiring action approvals, 3) a group for the users not requiring approvals, and 3) the manager associated with a Global Admin group in order to access Approvals.
- That any user that will be performing DNS Actions with Approvals are in a User Group with appropriate 'resource' CRUD permissions to perform the actions subject to approval.
    - Example: If a user needs zone creations approved, ensure that they have (at the very least) "Create" and "Read" resource permissions so that they can view DNS information and create a zone!
- Consider limiting groups associated with Approvals to *only* those users relevant to the Approvals system, especially if using Approval Notifications. Approval Change Notifications are emailed to all users of the associated User Group - not just the submitter / approver. Be conscientious of colleagues' email boxes and consider which users may not appreciate being included with notifications.

Sample Group Scenarios

Below are a couple of sample scenarios to illustrate common Approval situations, with example notes on Approval Settings.

Scenario 1: One Approver Group, with Restricted Actions

One Admin group and two DNS worker groups with different levels (high - low) of oversight needed, with restrictions set for particular Action types.


Group 1A (Admin)	Group 1B	Group 1C
• Global Admins (Full TLR User Group Perms + Admin) • All Admins in this group can approve any change requests • It doesn't matter which Admin user approves a request **Approval Group Settings:** • Set to policy "Must Approve" for all DNS Family / Action types • Tip: Click the quick select checkbox next to each DNS Family name to select all actions under that family	• Users with minimal oversight • Can work fully in all DNS family areas • Only needs admin approval for DNS Pushes **Approval Group Settings:** • Set to policy "Action to be Approved" for "Push" and "Background Push" actions only, under each DNS Family in Group Assignment	• Users with high oversight • Not allowed to Add or Delete any DNS item • Needs admin approval for all DNS Push and Updates **Approval Group Settings:** • Set to policy "Deny" for "Add" and "Delete" actions under each DNS Family; save • Open again, select "Update" and "Push / Background Push" actions under each DNS family, and set the policy to "Action to be Approved"; save.

Expand the following link to view example images of setting the assignments for all three groups:


These examples use the "Assign" button for the Group under the **Approvals** **Permission Groups** sub-tab, Groups page.

Scenario 1


Group A:




Group B:



Group C, Deny Policy:



Group C, Action to be Approved Policy:



These settings may also be set by Action Type instead of Group, from the **Approvals** **Permission Groups** sub-tab, Actions page.

Scenario 2: Multiple Approver Groups/Specific user, with Restricted Families

Two Admin approval groups exist: One general Approver group that can approve any action type, and a second Group containing one person, Bob, who must sign off on any action taken under DNS Groups.

Group 2A (Admin Approvers)	Group 2B (Admin Approver Bob)	Group 2C
• Global Admins (Full TLR User Group Perms + Admin) • All Admins in this group can approve any change requests • It doesn't matter which Admin user approves a request • DNS Group changes require multiple levels of oversight- from both this group and Bob **Approval Group Settings:** • Set to policy "Must Approve" for all DNS Family / Action types • Tip: Click the quick select checkbox next to each DNS Family name to select all actions under that family	• Global Admins (Full TLR User Group Perms + Admin) • Only contains one user - Bob, who specifically must approve of any change to DNS Groups **Approval Group Settings:** • Set to policy "Action to be Approved" for "Push" and "Background Push" actions only, under each DNS Family in Group Assignment	• Full Access throughout DNS • Not allowed to work with DNS Servers, even if they might have admin level access otherwise • Changes to DNS Groups and DNS Records require approval **Approval Group Settings:** • Set to policy "Deny" after quick-selecting the DNS Servers Family; save • Open again, quick-select the "DNS Groups" and "DNS Records" families, then set the policy to "Action to be Approved"; save.

Approval Workflows

Initial Setup

The high level process to use when first setting up approvals is as follows:

1. Review User Groups and Approval Process Needs

Step 1 - Review Existing User Groups and Process Needs

When setting up Approvals for the first time, review the information in the previous section under "Approvals Fundamentals" to ensure a basic understanding of how Policies, Actions, and User Groups relate together in Approvals.

Then, take a few minutes to think about the following questions to get a better sense of how to use Approvals with your specific organization:

Who are the users that perform DNS tasks, and at what level?

Affects which users should be included in what User Groups

What ProVision User Group(s) are they in?

Approvals settings are applied to the User Group, not individuals - ensure users with similar oversight needs are grouped together

What actions made by a certain user group should be automatically denied, if any?

Assign the "Deny" policy to that Action/User Group combination

What actions made by a certain user group should require oversight (admin approval / rejection)?

Assign "Action to be approved" to that Action/User Group combination

Who is the admin / User Group that will make the final approval on a change?

Ensure the approver(s) is in a User Group with the "Must Approve" policy assigned for the actions requiring approval

Should any changes require multiple admins / User Groups to approve it in order to execute?

A single user from every group assigned with "Must Approve" for the action must approve the action for it to succeed

If two admins are required to both separately agree on a change, they should be under two separate User Groups assigned "Must Approve"

What User Groups would need to receive email Approval Status notifications, and on what type of actions?

Affects whether to enable notifications and set up the scheduler task to send the notifications, and to what User Groups. When enabled, all users of the relevant group(s) will receive the email(s)

Once your User Groups are optimized for use with Approvals, you may want to write down a quick note on which Action Types and policies are planned for each group.

2. Edit User Groups / Create Approvals-Specific User Groups, if needed

Step 2 - Add or Edit ProVision User Groups

From here, depending on the answers to the questions in step 1, you may need to do one or more of the following from the **Users** tab:


a. Edit existing User Groups to add or remove users, in order to combine users who will need similar action types approved.
b. Verify the User Groups have appropriate CRUD permissions set to perform the action(s) to be approved (e.g, you may have previously removed "Create" permissions for a group, but if the intent is now for those users to have "Add" actions approved by an Admin, the submitter will need User Group resource "Create" permissions back!)
c. Create new User Groups specifically for use with Approvals (recommended)
d. Associate users with different, or additional User Groups (remember - users can be associated with multiple groups!)

For more information on adding and editing ProVision User Groups, see Users & Permissions, Global Permissions, and Working With Users and Groups.


3. Assign Action and Policy Settings to User Groups

Step 3 - Assign Approval Action Settings to Groups


From the **Approvals** Tab, navigate to the **Permission Groups** sub-tab.



Then, under the **Groups** page tab, find the ProVision User Group you wish to want to assign a policy to and click "Assign".



Clicking the "Assign" button for a group brings up a checklist to select what policy to apply to the group for what Family and Actions (i.e. DNS Zone 'Add' or DNS Group 'Update'). You can "quick-select" all actions for a DNS Family (Severs, Groups, Zones, Records) by clicking the checkbox next to the family name, or only select individual action types for each Family.




Once you've selected the applicable Family/Action combinations to apply a policy for, select either "Deny", "Action to be Approved", or "Must Approve Action" under Policy.

When done, Click "Assign", and repeat as needed for other Policy types or User Groups.


4. If using Approvals notifications, enable notifications for the appropriate Permissions Group(s)

Step 4 - Enable Notifications (Optional)

From the **Approvals** Tab, navigate to the **Permission Groups** sub-tab **Groups** page tab.



Click on the group name for which you want to set notifications - the Group Permissions Detail page will provide additional information on the group's settings.



For any Family/Action that you want to enable notifications, click the checkbox under "Enable Notifications". All users of that group will get email notifications when a change of the selected type(s) are made.

5. If using Approvals notifications, set up a Scheduler task for "Approvals - Process Subscription"

Step 5 - Add Scheduler Task: "Approvals - Process Subscription"

The "Approvals - Process Subscription" task processes approval request events and handles the sending of notification emails to subscribed Approvals Groups - this task must be created and running on a regular interval in order for Approval Notification emails to be sent.

In order to receive the most up to date information in the Approval Notifications, is recommended to create this task with a run time of "every 5 minutes" and no end date.

For information on setting up Scheduler Tasks, see Scheduler Tab.

6. Set up a Scheduler Task for "Approvals - Delete events older than 1 month", to occasionally clear out old and obsolete Approval request events

Step 6 - Add Scheduler Task: "Approvals - Delete events older than 1 month"

The "Approvals - Delete events older than 1 month" task deletes any Approvals history events older than 30 days.

It is recommended to set this task to run monthly with no end date, to clear out obsolete approvals items, reduce data storage space needs, and reduce approvals page load time.

For information on setting up Scheduler Tasks, see Scheduler Tab.

Daily Use


On a day-to-day basis after initial setup, an Approvals Workflow will be similar to the following (with "Submitter" as the user whose actions require approval, and "Approver" as the admin with the ability to approve/reject the change):

1. Submitter makes an action (either by action type or DNS Family) that requires approval
2. Submitter is notified that their action is pending approval




3. The requested change is sent to the **Approvals** Tab **Pending Approvals** list, and also to the **DNS** **Resources Awaiting Approval** module (the submitter may see their own submitted action under "Resources awaiting approval", but only Approvers can take approve /reject actions)


The **Pending Approvals** list is under the **Approvals** Tab. It shows Approvals events (change requests) for which the user has the ability to Approve or Deny - it does not show approval requests for all of ProVision or those for other users.



A "Resources Awaiting Approval" module will display in selected DNSv3 pages to Users with Admin / Approval permissions, if a change has been submitted on that page that is pending approval by the User's Approval Group.




4. The Approver reviews the change in either their **Approvals** Tab **Pending Approvals** list, or the **DNS****Resources Awaiting Approval** module, and chooses to Approve or Reject the change:



   a. If Approved, and no other groups need to approve it, then the change executes and is saved. A status change notification email is sent, if enabled.
   b. If Approved, and is waiting approval from an additional User Group, the change continues to be held as Pending, until the other group responds (Both groups must "Approve" for the change to execute). A status change notification email is sent, if enabled, stating that the change is awaiting another Group.
   c. If Rejected, the change is not executed. A status change notification email is sent, if enabled.

Example Notification Email:




Additional Information

See the following areas for more information on Approvals and using Approvals with DNS:

- DNS Tab
- Pending Approvals
- Permission Groups
- Scheduler Tab

Pending Approvals

Pending Approvals



The Approvals module stores and queues DNS actions made by selected User Groups, and sends those actions to a Pending Changes list for administrative review. Later, an administrator (or combination of administrators) can approve or reject these stored actions.

The admin **Approvals** Tab contains two sub-tabs: **Pending Approvals** and **Permission Groups**, which are the primary areas to manage Approvals items.


Currently, **Approvals** is available only for **DNS** related actions, while we gather feedback and use cases to inform possible future updates. If you are interested in providing feedback, a use case, or requests for future additions to the Approvals system, please contact feedback@6connect.com.

- Pending Approvals
- Pending Approvals - Overview
- Working with Pending Approvals
    - View / Sort Pending Approvals
    - View / Sort Approval History
    - Viewing Requests Pending by Other Groups
    - Viewing details on a change request
    - Approve / Reject a single change request
    - Bulk Approve / Reject
    - Resources Awaiting Approval Module (DNS Tab)
    - View / Send Request Status Change Notifications
    - Delete Old Approval Events (Scheduler)
- Additional Information

Pending Approvals - Overview

The **Pending Approvals** sub-tab lists Pending approval requests (also referred to as change requests, approval events, or approval items) for which the current admin user has permission to "Approve" or "Reject".

The Pending Approvals list may be sorted by Name, Family, Action Type, Updated time, or by submitted user and searched by resource name.



Approving and Rejecting change requests may be done individually, or in bulk by selecting multiple item checkboxes / clicking the "select all" checkbox. Once selected, an option to Approve/Reject all selected items will appear. If notifications are enabled for the Group or Action, an email will be sent notifying the request submitter of the status change.


At the bottom of the page, historical approval items for the user are shown. The user may filter their previous approval items by Executed, Approved, Rejected, or Pending by Others (for items requiring multiple Groups to approve).

Working with Pending Approvals


View / Sort Pending Approvals

The Pending Approvals list may be sorted for any column with the sort arrow icon ( ).


Click on the column name to toggle between ascending / descending order for that field.



Filter the Pending Approvals list to only view a certain Family/Action type by selecting an option from the "Filter by Action" dropdown.



Search the list for a specific item name by typing all or part of the name in the search box, then clicking the search icon.




View / Sort Approval History

Previous Approval events applicable to the current admin user are displayed under the Approvals Historical Data section, until they are deleted or removed by an archive process, such as the "Approvals - Delete events older than 1 month" scheduler task process.


Similar to the Pending Approvals list, it may be sorted ascending / descending by field, filtered by status, filtered by action, or searched by name.

Click on the column name to toggle between ascending / descending order for that field.




Filter the History to only view a certain status by selecting an option from the "Status" dropdown. The available options include:


- **All Executed** - Shows historical approval events that were approved and executed.
- **Approved** - Approval change requests approved by you, the currently logged in user.
- **Rejected** - Approval change requests rejected by you, the currently logged in user.
- **Pending by others** - Approval change requests that you have already responded to with an approval or rejection, but that are awaiting responses from one or more other groups.



Filter the History to only view a certain Family/Action type by selecting an option from the "Filter by Action" dropdown.




Search the list for a specific item name by typing all or part of the name in the search box, then clicking the search icon.




Viewing Requests Pending by Other Groups

Approval requests that you have approved/rejected, but which are still awaiting a response from another group, may be viewed under Historical Approvals Data by setting the "status" filter to view "Pending by Others".



Viewing details on a change request


To view details on any Approvals change request, click the name for the desired item. An information box will appear with details on the change, including status, id, creation date, family, field values, and the API Call in JSON format.




The change may be approved or rejected directly from the detail information box, or you may click "Close" to exit.

Approve / Reject a single change request

To Approve or Reject any single change request, click either the "Approve" or "Reject" button for the pending item.




Approving or Rejecting a request may be done from the Pending Approvals list, the detail view for the item, or from the DNS "Resources awaiting approval" module.




Bulk Approve / Reject

Bulk Approve or Reject actions may only be done from the **Approvals** tab **Pending Approvals** list.

Select the checkboxes for the items that you want to bulk approve or deny, then click either "Approve All" or "Reject All" buttons to apply the response to the selected requests.




If you wish to select all items in the Pending Approvals list for the same response type, click the "select all" checkbox to the left of the "ID" column name. All of your pending items will be selected, and you may choose to "Approve All" or "Reject All" from the top of the page.




Resources Awaiting Approval Module (DNS Tab)

A **Resources Awaiting Approval** module will display in DNSv3 areas, if a change has been submitted on that page either by the current user, or that the current user may Approve/Deny.


Users who submitted the request will be able to view the request details, but will be unable to take any actions on the request.



Admin users with Approve/Reject Ability will see Approve/Reject buttons available to immediately respond to the request.




Details for the change may be viewed by clicking the "Details" button in the module.



View / Send Request Status Change Notifications

Email notifications of changes in status are an optional feature that may be set up by Approval Permission Group for the desired action types.

The emails provide the current status, approval ID, links to the log event and change request details, and details on the user, time, and date.



In order to send email notifications to affected groups of a change in the status of an Approval event:

1. Notifications must be enabled for the Group, for the family-action type of the requested change
2. A scheduler task ("Approvals - Process Subscription") must be created and running to process the notification and send the email

Enabling notifications for approval events is done in the **Permission Groups** subtab of Approvals, see the Working with Permission Groups page for additional information on setting up notifications.

The "Approvals - Process Subscription" task processes approval request events and handles the sending of notification emails to subscribed Approvals Groups. If Approvals are in use with notifications, it is recommended to create this task with a run time of "every 5 minutes" and no end date. For details on setting up this task, see documentation for the Scheduler Tab.

Delete Old Approval Events (Scheduler)

Old Approval events may be purged from the system by enabling and running the scheduler event "Approvals - Delete events older than 1 month". This task deletes any Approvals history events older than 30 days, and It is recommended to run this task monthly to clear out obsolete approvals items and reduce approvals page load time.

For information on setting up scheduler events, see documentation for the Scheduler Tab.


Additional Information

See the following areas for more information on Approvals and using Approvals with DNS:

- DNS Tab
- Approvals
- Permission Groups
- Scheduler Tab

Approval Permission Groups

Approvals Permission Groups



The **Approvals** Tab **Permission Groups** subtab is where admins may view and manage assignments, actions, and settings for Approvals permission groups.

Currently, **Approvals** is available only for **DNS** related actions, while we gather feedback and use cases to inform possible future updates. If you are interested in providing feedback, a use case, or requests for future additions to the Approvals system, please contact feedback@6connect.com.

- Approvals Permission Groups
- Permission Groups - Overview
  - Groups
    - Group Assignment (Assign Button)
    - Group Details Page
  - Actions
    - Actions - View Groups Page
    - Actions - Assign Groups
- Working with Approval Permission Groups
  - Sort or Filter the Group List
  - View/Edit Existing Assignments
    - Groups Tab
    - Actions Tab
  - Assign a new Permission Group policy
    - Assign a Policy from the Groups Tab
    - Assign a Policy from the Actions Tab
  - Manage Approval Notifications for Groups
    - Set up the "Approvals - Process Subscription" Scheduler Task
    - Enable Notifications
- Additional Information

Permission Groups - Overview

The **Permission Groups** sub-tab contains areas to manage a User Group's level of approval permissions ("Policy"), and on what actions they apply. By default, all existing ProVision User Groups are displayed under Approvals - Permission Groups. However, you may assign Approval policies to few or as many of the groups as you want.

There are two tabs available under Permission Groups - **Groups** and **Actions**. Both tabs provide similar levels of functionality to view and assign policies, but they differ in organization.

Use the **Groups** tab view if you want to:

- Assign a policy to a specific group that includes multiple action types
- View, edit, or remove the policies associated with any or all action types for a group
- Enable/disable a group's Notification setting


User the **Actions** tab view if you want to:

- View how many or what groups are assigned policies for a specific action type
- Want to confirm that an action type has group assignments covering both the "Action to be Approved" and "Must Approve" policies
- View, edit, or remove policies associated with a specific action family or action type
- Assign a single policy to a one or more groups for a specific family-action type

Before using the functions available from the **Permission Groups** page, you may wish to review the Approvals documentation page for information on best practices for setting up User Groups for use with Approvals, policy definitions, and workflows.

Groups


In the **Groups** tab, each ProVision User Group is listed with details on the status, number of users, and last updated time.



From here, you may either click on "Assign" to assign action policies to the Group, or view/edit existing settings by clicking on the Group Name to open the Group Details page.

Group Assignment (Assign Button)

Clicking the "Assign" button for a group brings up a checklist to select one or more actions to apply a policy to for that Group.



Select one or more Family/Actions to apply a specific policy to, ensure that policy is selected, and then click "Assign".


The Group assignment screen will add the new policy settings to any other existing assignments.

The Group Assignment screen does not show existing assignments or edit existing assignments - it is a quick way to add new assignments to a Group.

To view/manage existing group assignments, go to the **Group Details** page

Group Details Page


From the list of Permission Groups, click on a Group name to bring up the permission details for that Group.



Here, you may view, edit, or remove current policy assignments, and enable/disable notification emails for each action type. The list of assigned actions for the group may be sorted by Family or Method, and filtered by Family (here: "DNS Groups").

Actions


The **Actions** Tab lists the group permissions organized by Family/Action type.



Expanding a Family shows the available actions, and a matrix of how many groups are assigned under each policy.


Actions - View Groups Page

Clicking the "View Groups" button from the Actions tab shows the list of each group assigned to that action, with the option to unassign a group from that action.



Actions - Assign Groups

The "Assign Group" button on the Actions tab lets you assign a Group and Policy to that action.




This performs the same function as the earlier assignment window, but is organized to only assign a single group/policy to that action, instead of assigning multiple actions to a group.


Working with Approval Permission Groups

Sort or Filter the Group List

Sort the Permission Groups list by Name, Enabled, or Users by clicking on the column name.



To Filter the list, type all or part of the group name into the "Filter by Group" box, and the list will automatically narrow to show results.




View/Edit Existing Assignments


Viewing and editing existing assignments may be done from either the **Groups** tab or the **Actions** tab:

Groups Tab


To view details for a permission group, click on the Group Name from the Permission Groups list.



The **Group Details** page will open, displaying all Family-Action types currently assigned to the Group




Click on the "Policy" dropdown to select a different policy to apply for the action, or click the "Remove" button to remove the policy assignment completely. Changes will be automatically applied and saved.




Actions Tab

You may also view or edit current assignments as organized by action, from the **Actions** Tab.

On the Actions page, expand a Family to view the actions under each family, and how many Groups are assigned for each policy.



Click "View Groups" to view the groups assigned for each action. To remove the policy / group assignment for the action, click "Unassign".



Assign a new Permission Group policy

Three policy settings are available to assign to a Group / Action:


- **Deny** : All users in the group will have the selected actions automatically denied at an attempted change.
- **Must Approve Action:** A User in the group must approve or deny change requests submitted for the selected Family / Action(s), for any Group requiring "Action to be Approved" for the same action(s) in order for the change to execute. If multiple groups are set as "Must Approve Action" for the same type of change, then the change will be held as "Pending" or "Pending by Others" until a user from *each group* approves the change request.
- **Action to be Approved:** Users in the group will have the selected actions submitted to Pending Approvals for the change to be approved or denied. A second Permission Group must exist with the "Must Approve Action" policy assigned to the same action for the submittal to succeed.

Policies may be applied from either the Approvals **Groups** tab, or the **Action** tab, depending on whether you want to assign policies/actions to a specific group, or assign a group and policy to an action, respectively.

Assign a Policy from the Groups Tab

From **Approvals** **Permission Groups** Groups tab, Click the "Assign" button.

The Group Assignment checklist opens to select one or more actions to apply a policy to for that Group.




Select one or more Family/Actions, select the policy to apply, and then click "Assign".


Click the checkbox next to the family name (e.g. "DNS Servers")to quickly select all actions under that family!

Assign a Policy from the Actions Tab

From the **Approvals** **Permission Groups** Actions tab, click the "Assign Group" button for the Action you want to assign to a Group / Policy.




Select the Group(s) that you wish to assign, and select the policy to apply to the action. When done, click the "Assign" button to save.



Manage Approval Notifications for Groups

Email notifications of changes in status are an optional feature that may be enabled for a Permission Group for the desired action types.

The emails provide the current status, approval ID, links to the log event and change request details, and details on the user, time, and date.



In order to send email status notifications to groups associated with an Approval event:


1. A scheduler task ("Approvals - Process Subscription") must be created and running to process the notification and send the email
2. Notifications must be enabled for the Group, for the family-action type of the requested change

Set up the "Approvals - Process Subscription" Scheduler Task


Go to the **Scheduler** Tab, and verify that the "Approvals - Process Subscription" task has been created, is enabled, and is running at short, regular intervals appropriate to the needs of the users receiving the emails (recommended to run every 5 minutes).

If the task does not yet exist:

From the **Scheduler** Tab, click "Add Task"



Enter a Name for the task (including a reference to "Approvals Notifications" is recommended for clarity), select the task as "Approvals - Process Subscription", and enter an End date - or leave blank to run as a 'forever' task.




For Repeat Settings, select how often you'd like the scheduler to check for new approvals changes and send the notification emails - every 5 minutes is recommended. Select your time interval and click "Add Repeat Setting".

When done, click "Save Task".



The Approvals Email Notification task is now set up, active, and ready to process Approvals Event changes.




For additional information on working with the Scheduler, see Scheduler Tab documentation.

Enable Notifications

Once the Scheduler task is verified created and active, notifications must be enabled for the desired Groups / Actions for the status changes to be emailed to the appropriate Groups.

From the **Approvals** **Permission Groups** Groups tab, Click on the Group name that you wish to enable/disable notifications for.

In the Group Details page, click the checkbox under "Enable Notifications" to enable / disable status change notifications for the Group for the selected Family/Action types.




Additional Information

See the following areas for more information on Approvals and using Approvals with DNS:

- DNS Tab
- Approvals
- Pending Approvals
- Scheduler Tab

Constraints

Constraints



The Constraints system allows Admin users to configure custom field validation and limitations into IPAM fields. Many constraint types are available, such as mathematical comparison operators, length, enumeration, pre-set lists, RegEx, IPv4/IPv6, Phone, email, hostname, FQDN, Mac Address, and URL.

The **Constraints** Tab has one sub-tab - **Configuration** - where new constraints may be created and managed.

Currently, **Constraints** is available only for **IPAM** related actions, while we gather feedback and use cases to inform possible future updates. If you are interested in providing feedback, a use case, or requests for future additions to the Constraints system, please contact feedback@6connect.com.

- Constraints
- Constraints Tab - Overview
- Available Constraint Types
- Add a Constraint
- Test Constraint
- Edit Constraint
- Delete Constraint
- Working with Constraints in IPAM Manage
- Example: Adding an Enumeration / Constraint Containing Children
  - Create the Parent Constraint
  - Open the Parent Constraint
  - Add Child Items
  - Using the Enumeration
- Additional Information

Constraints Tab - Overview

The Constraints Tab, available to Admin users, allows for custom field validation and field restrictions to be applied to IPAM fields. The applied constraint may be anything from a numerical comparison operation, a check against a pre-determined text string, ensuring selections from a pre-set list, or forcing entries into a specific format, such as IPv4/IPv6, phone number, or RegEx.

These constraints can be applied to the following IPAM fields:

- ASN
- Custom Generic Field
- Notes
- Metadata 1-10, if enabled for the instance

Depending on the type of constraint applied, the constraint may be a simple single-value comparison needing only one constraint to be created, such as "Equals to" or "Length Max". Some other constraint types, however, may have two or more levels deep of constraint types and value checks. One example of this is "Enumeration", which requires the user to first set up an "Enumeration" constraint, and then a second level list of sub-constraint types or a list of values. For a detailed constraint tree, it may be worth

Available Constraint Types


The following constraint types are currently available:

Type	Description
Enumeration	Create a list of child enum items. Note: Set binding / control type for parent constraint (enumeration) only, do not provide for child items. Children type: Valid child enum types are: =, !=, >, <, >=, <=, regex, allow, oneof, allof, ip, ipv4, ipv6, email, url, hostname, fqdn, mac, phone, lenmax, lenmin, section_entry
Section Entry	Creates an enumeration based on all entries that belong to a given section.
Equals to	Checks to ensure a value is exactly equal to a provided value, e.g. (X == Y) is true
Not Equal to	Checks to ensure a value is not equal to a provided value, e.g. (X != Y) is true
Greater Than	Checks if the input value (left operand) is greater than a given value (right operand). e.g. (X > Y) is true
Less Than	Checks if the input value (left operand) is less than a given value (right operand). e.g. (X < Y) is true
Greater Than or Equal to	Checks if the input value (left operand) is greater than or equals to a given value (right operand). e.g. (X >= Y) is true
Less Than or Equal to	Checks if the input value (left operand) is less than or equals to a given value (right operand). e.g. (X <= Y) is true
One of	Create a list of child constraint items. It will be true if one of child constraints is true. Its children must be previously configured. Note: Set binding / control type for parent constraint (enumeration) only, do not provide for child items.
All of	Create a list of child constraint items. It will be true if all of the child constraints are true. Its children must be previously configured. Note: Set binding / control type for parent constraint (enumeration) only, do not provide for child items.
Length Max	Checks to ensure a string has, at most, the specified number of characters
Length Min	Checks to ensure a string has, at minimum, the specified number of characters
Regular Expression	Compares the input format to a provided Regular Expression
IPv4	Sets the required format for the input to an IPv4 address
IPv6	Sets the required format for the input to an IPv6 address

Email	Sets the required format for the input to an email address (uses an "@" symbol)
Hostname	Sets the required format for the input to a hostname. Hostnames may not have underscore or dash characters.
FQDN	Sets the required format for the input to a FQDN
MAC Address	Sets the required format for the input to a MAC address
URL	Sets the required format for the input to a url
Phone Number	Sets the required format for the input to a phone number

Add a Constraint


To add a new Constraint, click "Add Constraint"



In the "Add Constraint" screen, select (at mimimum, depending on the selected constraint type):

- The constraint type (here, "Length Min")
- The name for the constraint
- The attribute (IPAM Field) on which to apply the constraint
- Constraint specific comparison values, here as "Length"
- Select whether to allow empty values in the attribute field


If desired, you may enter a custom error message, customize the UI binding (although it it automatically filled in if you select a standard IPAM Attribute), or add an event hook setting.



When done, click "Add Constraint" to save.


Test Constraint

To test a Constraint, click "Test".




The test constraint form will appear - enter a test value, and you can check whether the constraint returns an appropriate invalid or valid response:

Invalid result, for "Length Min 3":




Valid result, for "Length Min 3":



Edit Constraint


To edit a Constraint, click "Edit". The constraint details will open, matching the "Add Constraint" form.




Adjust values or settings as desired, and then click "Update Constraint".

Delete Constraint

To delete a Constraint, click "Delete".




A Confirmation box will appear - confirm whether to delete the constraint, or click "Close" to exit without deletion.



Working with Constraints in IPAM Manage


When a field is viewed in IPAM Manage that has a constraint applied, a "check" icon will display next to the field input for simple input constraint checks, if empty values are allowed.

If the constraint is of a type that has been set up with a dropdown box, then the dropdown box and placeholder text will be applied:




In this example, constraint validation checks have been applied to Metadata4, Metadata7, and Metadata8, with a dropdown "One Of" constraint applied to Metadata 10.

Metadata8 has been associated with our previous constraint example, "Length Min 3", so if we enter less than three characters into that field, we should get an error, and see the "X" for the input not meeting the constraint settings:



On the other hand, a valid input will return to displaying the "valid" success checkmark:




Example: Adding an Enumeration / Constraint Containing Children

This example shows how to add a two-level constraint, such as Enumeration, All of, or One of - all of which are set up having a "parent" constraint at the top level list, and "child" items or constraints on a sub-level. Here, we will be using Enumeration as the example constraint, although All of and One of may be created similarly - just using the "add constraint" button to create children instead of the "add item" button.

Create the Parent Constraint


From the Constraints "Configuration" page, click "Add Constraint".



Select "Enumeration" for the constraint type, and enter a name, attribute binding, and select the Control type - here, we will be using a dropdown control.

For Parent/Child constraint types, you only need to enter the attribute binding and control type for the parent constraint, and do not need to enter these settings for the child items - those settings are inherited by the child items you will create later.


All other fields are optional, and may be skipped if desired.



When done, Click "Update Constraint". You will see the new constraint added to the Constraints List.

Open the Parent Constraint

Constraints that have parent/child relations show as a blue link in the constraint list. Click on the constraint name to open the parent constraint to view or add child settings.




Add Child Items


Once you have opened the parent constraint, here: Enumeration, you can add the child values that you wish to have listed as valid options.

For Enumeration, click "Add New Item", If using All of or One of types, then you will need to click "Add Constraint" to add child constraint items.

For Parent/Child constraint types such as "All of" and "One of", you only need to enter the attribute binding and control type for the parent constraint, and do not need to enter these settings for the child items.




Add a new child enum item by entering a title, name/value, and the type. Typically, the type will be "=", for "equals this value".



When done, click "Update", and repeat for any additional values that you wish to make available in your enumeration dropdown.


Here, we have added additional enum items to cover "val1" through "val 5".



From here, navigate back up to the parent constraint list that displays "enum1", and click "Test" (test will not work on individual child constraint items)




A display dropdown box will appear, click inside of it to confirm your child items show as selectable options.



Using the Enumeration

To see the constraint in action in IPAM Manage, navigate to a block and open Edit Block mode. Select the field that you applied the "enum1" element binding to (metadata 8, here), to view/select constraint items from the dropdown



Additional Information

For additional information on working with IPAM Manage or IPAM Blocks, see

- IPAM Tab
- IPAM Administration

ProVision Developer Tools

Developer Tools

6connect ProVision can integrate with your existing tools and workflow through use of the API and CLI. The 6connect API allows you to access the data and functions of the 6connect web tools to run advanced commands in ProVision, and supports a wide variety of update and deletion conditions not available in the UI.

To use the API, you will need a basic understanding of object oriented programming in PHP and the right tools installed on your system.

Table of Contents

- Developer Tools
  - API Overview
  - API v2
  - API v1 (Deprecated)
  - Portable Gadgets
  - Reverse API
  - Toolkit
  - CLI
  - Resource Concepts

API Overview

The 6Connect API is a RESTful API to access your data in the 6Connect tools. ReST relies on stateless, client-server communication, and is implemented using the HTTP protocol (the 6Connect APIv2 uses HTTPS). It is a simple and lightweight alternative to Web Services and can implemented in nearly any language. The 6Connect API operates similarly to other popular ReST APIs you may have worked with, such as Facebook or Twitter.

To learn more about request formatting, making requests, and the tools available, visit Making API Requests. You can also get the PHP SDK for PHP libraries and sample code.

Here are some important details about our ReST implementation:

- The API only comes with the full 6Connect IPAM product. If you would like to upgrade to the full version, contact sales@6Connect.com.
- All transactions are over HTTPS (SSL - port 443) only. Any transaction not using SSL will be rejected, and you will have potentially exposed sensitive data.
- All API results are formatted in JSON. XML support is coming soon.
- APIv2 requests use standard HTTP methods such as GET, PUT, POST, PATCH, and DELETE. We suggest using POST if the length of data in the request is over 8KB.
- You can use any language you would like to query the API.

API v2

APIv2 Quick Links

Public APIv2 documentation is located at https://cloud.6connect.com/APIv2/.

APIv2 documentation includes:

- IPAM API
  Includes actions for LIRs, IP aggregate and block management, VLAN, IP Rules, and SWIP.
- Resource API
  Includes actions for managing the ProVision Resource System.
  The resource API provides CRUD endpoints for resources, resource attributes, resource attachments and resource backups.
- DNS API
  ProVision DNS API allows you to manage DNS Zones, Records, Servers, Groups and ACLS.
- Users API
  Includes actions for ProVision Users, permissions and actions.
- Usergroups API
  Includes actions for ProVision Groups, permissions and actions
- Scheduler API
  The API Allows you to easily schedule tasks.

- API Composer Platform
  API Composer Platform (ACP) is an additional module in ProVision to help automate frequently used combinations of calls.

APIv2 is ProVision's currently supported RESTful API version. APIv2 adds new endpoints and upgraded functionality over APIv1, through use of HTTPS authentication, additional HTTP methods (GET, PUT, POST, etc.), and JSON payloads.

To test APIv2 queries, you may:


1. Use a browser extension REST client, such as Postman
2. Access ProVision's APIv2 Swagger documentation from your ProVision instance (*instance*/dev/swagger), which provides the ability to test inputs and responses using your ProVision instance data.
    a. Continue to the section: "APIv2 - Using Swagger" at APIv2 for more details.
3. Use CURL in the command line to authenticate and execute APIv2 endpoints. See cURL documentation at https://curl.haxx.se/.
    a. Continue to the section: "APIv2 - Using cURL" at APIv2 for more details.

APIv2 Swagger Documentation

Public APIv2 documentation is located at https://cloud.6connect.com/APIv2/.

Existing customers may also access APIv2 Documentation from your ProVision instance (user must have Admin permissions):

1. Log into your ProVision instance.
2. Go to the Admin area of ProVision and click on the **API** Tab.
3. Under "OpenAPI 3.0 Specification" click the Swagger link provided.



API v1 (Deprecated)

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

It is **highly recommended** that any customer utilizing ProVision's APIv1 for custom scripting refer to APIv2 documentation instead, and consider upgrading existing APIv1 scripts to use APIv2.

However, APIv1 documentation will remain accessible in order to support legacy uses.

Portable Gadgets

ProVision's Portable Gadgets are drop-in code snippets that use the ProVision API to bring in data to other systems or web pages. Portable Gadgets allow for quick data access and increased integration.

Currently, four Gadgets are available: Global Search, IPAM Search, DHCP Search, and Log. Each Gadget comes in various default option types for display style, number of records return, or behavior. Additional client-side style customizations may be made to further integrate the gadget with company styles.

Reverse API

ProVision's Reverse API calls and UI elements allow for integration with outside APIs to improve workflow and create custom display content. In the ProVision user interface, the Reverse API page allows for endpoints to be built and provides a text editor to create presentation JavaScript commands. This JavaScript presentation code is then displayed in the Reverse API Gadget.

Toolkit

6connect provides customers with additional CLI modules for ProVision power users in the /tools directory.

CLI

Command line interface offering basic IPAM commands, such as Add, Update, Direct Assign, Smart Assign, and Unassign.

Resource Concepts

A developer-oriented overview of ProVision's Resource System.

Table of Contents

- APIv2
- API v1 (Deprecated)
- Portable Gadgets
- Reverse API
- Toolkit
- CLI (Alpha)
- Resource Concepts

APIv2

APIv2

- APIv2
  - API v2 Overview
  - APIv2 Access Options
  - APIv2 - Using Swagger
    - Accessing Swagger
    - Viewing APIv2 Information
    - Testing/Executing Endpoints in Swagger
  - APIv2 - Using cURL
    - cURL syntax template for APIv2:
    - cURL Examples
      - Example: cURL APIv2 Authentication
      - Example: cURL APIv2 POST Command
  - Additional Information

API v2 Overview

APIv2 is ProVision's currently supported RESTful API version. APIv2 improvements include:

- HTTP Basic Authentication
- Use of HTTP Methods (GET, PUT, POST, etc.)
- Supports JSON payloads
- Additional endpoints and ProVision functionality

APIv2 Access Options

To test or execute APIv2 queries, you may:

1. Use a browser extension / desktop REST client, such as Postman
   a. Postman is the current industry standard: Go to https://www.getpostman.com/ to install, and visit the Postman Learning Center for user documentation, training videos, and support help.
2. Access ProVision's APIv2 Swagger documentation from your ProVision instance (*instance*/dev/swagger), which provides the ability to test inputs and responses using your ProVision instance data.
   a. Continue to the section below: "APIv2 - Using Swagger" for more details, or see the ProVision Developer Tools page for a broader overview.
3. Use CURL in the command line to authenticate and execute APIv2 endpoints. See cURL documentation at https://curl.haxx.se/.
   a. Continue to the section below: "APIv2 - Using cURL" for more details, examples, and tips.

APIv2 - Using Swagger

Accessing Swagger

Public APIv2 documentation is located at https://cloud.6connect.com/APIv2/.


APIv2 documentation includes:

- IPAM API
  Includes actions for LIRs, IP aggregate and block management, VLAN, IP Rules, and SWIP.
- Resource API
  Includes actions for managing the ProVision Resource System.
  The resource API provides CRUD endpoints for resources, resource attributes, resource attachments and resource backups.
- DNS API
  ProVision DNS API allows you to manage DNS Zones, Records, Servers, Groups and ACLS.
- Users API
  Includes actions for ProVision Users, permissions and actions.
- Usergroups API
  Includes actions for ProVision Groups, permissions and actions
- Scheduler API
  The API Allows you to easily schedule tasks.

- API Composer Platform
  API Composer Platform (ACP) is an additional module in ProVision to help automate frequently used combinations of calls.


Existing customers may access APIv2 documentation from your ProVision instance (user must have Admin permissions):

1. Log into your ProVision instance.
2. Go to the Admin area of ProVision and click on the **API** Tab.
3. Under "OpenAPI 3.0 Specification" click the Swagger link provided.




Viewing APIv2 Information

1. On the 6connect Provision API Swagger home page, click on the name link for the API family that you wish to browse (IPAM, Resource, DNS, etc).




2. Once on an API Family page, verify that the displayed server name is correct for your instance/local server.

   In most situations, only one ProVision instance/server will be displayed, with authentication already provided from your ProVision login. If your ProVision session has ended, or the server changed, you may need to re-provide ProVision credentials by clicking the "Authorize" button.




3. Scroll further down the page and begin reviewing available APIv2 calls and details. Clicking on any call will expand it to view parameter details - you can even test call responses (using your instance data) by clicking "Try it Out"!

The detail information includes a description, parameter list (required parameters are marked with a *), and response information



4. Some calls that involve a JSON request body payload (PUT, PATCH, etc) will display "Example Value" and "Model" information under a "Request Body" section - additional parameter descriptions may be displayed under "Model" Information.

Clicking on "Example Value" will show an example of a JSON request body for that call.



Clicking on "Model" will display details and descriptions of the request body parameters, if available.




5. Additional "Model" examples are available at the bottom of the page with additional descriptive information.

At the bottom of the page, click on "Models".



Then, click on the "Model" you

wish to view. Some models may contain additional information that you can expand to view, such as valid values for a parameter. In the example below, the circled "array" will display valid RIR values.




Testing/Executing Endpoints in Swagger

You may execute endpoints in Swagger by using the "Try it out" button for any call.


1. Navigate to the call that you want to try out.
2. Expand the call to view its details, then click the "Try it out" button.




3. Input the desired parameters to test, and click "Execute".



If the call is a method that uses a JSON request body, you will have the option to edit the body text in the "Example Value" box - when done, click "Execute".



4. The example response will display under "Responses" after being executed. The "Response" section also includes the cURL command, Request URL, and Response Headers.



APIv2 - Using cURL

One option to execute an APIv2 call is to use CURL from the Command Line.

If you do not already have cURL installed, you may download it and access its documentation at https://curl.haxx.se/.

cURL syntax template for APIv2:

When using cURL, the general layout of the cURL command will be as follows:

1. Invoke cURL:
    a. *curl -X PATCH "https://your-instance-domain/instance-name/api/v2/config" -H "Content-Type:application/json; charset=utf-8" -u testing@6connect.com:password -d "{\"auto_merge_limits\":\"10\"}"*
2. Use the Request Flag (-X):
    a. *curl -X PATCH "https://your-instance-domain/instance-name/api/v2/config" -H "Content-Type:application/json; charset=utf-8" -u testing@6connect.com:password -d "{\"auto_merge_limits\":\"10\"}"*
    b. This specifies a custom request method to use when communicating with the HTTP server. The specified request method will be used instead of the method otherwise used (which defaults to GET)
3. Specify the HTTP Action:
    a. *curl -X PATCH "https://your-instance-domain/instance-name/api/v2/config" -H "Content-Type:application/json; charset=utf-8" -u testing@6connect.com:password -d "{\"auto_merge_limits\":\"10\"}"*
4. In quotes, specify the URL of the APIv2 endpoint you are executing. This should be similar to: "https://[ProVisionInstance]/api/v2/[endpoint family-action]"
    a. *curl -X PATCH "https://https://your-instance-domain/instance-name/api/v2/config" -H "Content-Type:application/json;charset=utf-8" -u testing@6connect.com:password -d "{\"auto_merge_limits\":\"10\"}"*
5. Use the Header Flag (-H):
    a. *curl -X PATCH "https://https://your-instance-domain/instance-name/api/v2/config" -H "Content-Type:application/json;charset=utf-8" -u testing@6connect.com:password -d "{\"auto_merge_limits\":\"10\"}"*
    b. Denotes an extra header to include in the request when sending HTTP to a server. You may specify any number of extra headers. Note that if you should add a custom header that has the same name as one of the internal ones curl would use, your externally set header will be used instead of the internal one. This allows you to make even trickier stuff than curl would normally do.
6. Add endpoint-specific data, such as specifying a JSON payload or attribute setting. This may involve one or more additional flags or information sets, depending on the endpoint:

a. *curl -X PATCH "https://https://your-instance-domain/instance-name/api/v2/config" -H "Content-Type:application/json;charset=utf-8" -u testing@6connect.com:password -d "{\"auto_merge_limits\":\"10\"}"*

Tip!

Swagger displays cURL commands and request URLs in the execution response!

Use the "Try it Now" feature from your instance's Swagger page (Accessed from Admin API Tab APIv2 Swagger Documentation) for the endpoint/attribute changes you wish to make, and view the cURL command for that change. Copy the command text, and use it as a template for your next cURL execution of the command!



For help using Swagger to test endpoints, see "Testing Endpoints in Swagger" in this APIv2 documentation page.

cURL Examples

Example: cURL APIv2 Authentication

This example authenticates a ProVision user, so that you may perform APIv2 commands as that user.

```
curl -X GET "https://2-dev.6connect.com/qa-7.3.0/api/v2/config" -H "accept: */*" -u testing@6connect.com
```

This will ask for a password. To hard-code it with a password, add it to the end like so:

```
curl -X GET "https://2-dev.6connect.com/qa-7.3.0/api/v2/config" -H "accept: */*" -u testing@6connect.com:
password
```

APIv2 commands are executed as the user provided, so their permissions must be set appropriately. The Swagger "execute" feature produces CURL strings that can be used to test specific API commands.

Example: cURL APIv2 POST Command

This example illustrates how to provide POST/PATCH data to an APIv2 command via cURL. This command updates the ProVision automerge configuration setting:

```
curl -X PATCH "https://2-dev.6connect.com/qa-7.3.0/api/v2/config" -H "Content-Type:application/json;
charset=utf-8" -u testing@6connect.com:password -d "{\"auto_merge_limits\":\"10\"}"
```

Review the general CURL documentation at https://curl.haxx.se/ can offer greater insight into what other flags can be used.

Additional Information

See the following areas for additional information:

- ProVision Developer Tools
- Public APIv2 Swagger documentation: https://cloud.6connect.com/APIv2/.

API v1

API v1 (Deprecated)

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

It is highly recommended that any customer utilizing ProVision's API for custom scripting refer to APIv2 documentation instead, and consider upgrading existing APIv1 scripts to use APIv2.

However, APIv1 documentation will remain accessible from the links below in order to support legacy uses.

APIv1 - Overview

The 6Connect API is a RESTful API to access your data in the 6Connect tools. ReST relies on stateless, client-server communication, and is usually always implemented using the HTTP protocol (the 6Connect API uses HTTPS). It is a simple and lightweight alternative to Web Services and can implemented in nearly any language. The 6Connect API operates similarly to other popular ReST APIs you may have worked with, such as Facebook or Twitter. You simply create an HTTP GET or POST request according to our standard, send it to the server, and receive data back.

To learn more about request formatting, making requests, and the tools available, visit Making API Requests.
You can also get the PHP SDK for PHP libraries and sample code.

Here are some important details about our ReST implementation:

- The API only comes with the full 6Connect IPAM product. If you would like to upgrade to the full version, contact sales@6Connect.com.
- All transactions are over HTTPS (SSL - port 443) only. Any transaction not using SSL will be rejected, and you will have potentially exposed sensitive data.
- All API results are formatted in JSON. XML support is coming soon.
- All requests are either HTTP GET or POST requests. We suggest using POST if the length of data in the request is over 8KB.
- You can use any language you would like to query the API. We currently have an SDK for PHP. Looking at the sample code would probably help you implement it in any language though.

Making APIv1 Requests

API requests can be generated within the web UI by the API Request Generator, or generated programmatically in any language.

An API request looks like this:
https://cloud.6connect.com/ex/api/v1/api.php?target=ipam&action=get&type=IP&mask=24

An API response is a JSON-encoded text string, and looks like this:


```
{"success":1, "message":"1 blocks found", "data":[{"id":"7539","oct1":"1","oct2":"2","oct3":"3","oct4":"0","
mask":"24","child1":null,"child2":null,"is_assigned":"0","is_swipped":"0", "is_aggregate":"1","custid":"
holding","last_updated_time":"2012-03-20 09:49:00","description":null,"parent":null,"rir":"ARIN","notes":"
2012-03-20 09:49:00","generic_code":null,"region":null,"vlan":null,"arin_net_id":null,"arin_cust_id":null,"
arin_swip_time":"0000-00-00 00:00:00","assigned_time":"2012-03-20 09:45:12"}]}
```


Instructions on decoding this return data can be found in the API endpoint documentation pages.

Using API Keys:
When using the API without pre-established authentication to ProVision, you must include both your API Key and a specially-prepared query hash parameter, like so:

https://cloud.6connect.com/ex/api/v1/api.php?target=ipam&action=get&type=IP&mask=24&apiKey=116-MX15LUYY78ZZTW5&hash=8jxj4IApYmgb5IZ0wBY4tFv+WilXb5JuVpjrwupyXQo=

API Keys can be generated from your ProVision instance by navigating to the Admin panel by using the gear icon in the upper right hand corner, then navigating to the API tab. The API tab will present the API authentication information in the following format:

API Key: 38-TMHQV8CV2XZYC2ZS

Secret Key: 6e04e5822ce90feaa8947ded46c46878

The secret key serves as an API password and is used in the creation of the API Authentication hash. The formula for creating a API query hash from an API query and a Secret Key is the following:

Hash = Base64Encode(Sha256HMACHash (QueryString, SecretKey))

In PHP, this would be performed with the following line of code:

$hash = *base64_encode(hash_hmac('sha256', $_SERVER['QUERY_STRING'], $secretKey, TRUE));*

Because the hash function is computed based on the query string, you must calculate a unique hash for every API request!

Example

Lets say you wanted to create a hash for the following API request:

https://cloud.6connect.com/6c_375/api/v1/api.php?target=ipam&action=get&type=IP&mask=24

And that your API Key and Secret Key are as follows:

API Key: 32-5DAYTJQY2TZHOFOB

Secret Key: 48b278ec873bda4738923dbc467f8669

The first step is to append your API Key to the URL. The API Key indicates which user is executing the API query.

https://cloud.6connect.com/6c_375/api/v1/api.php?target=ipam&action=get&type=IP&mask=24&apiKey=32-5DAYTJQY2TZHOFOB

The next step is to isolate the Query String from the request URL. The Query String is everything which follows the question mark. So,

Query String: target=ipam&action=get&type=IP&mask=24&apiKey=32-5DAYTJQY2TZHOFOB

The next step is to calculate the SHA256 hash of this string with your Secret Key. In PHP, this would be:

$sha256 = hash_hmac('sha256', "target=ipam&action=get&type=IP&mask=24&apiKey=32-5DAYTJQY2TZHOFOB", "48b278ec873bda4738923dbc467f8669", TRUE);

As this value has been 256-bit hashed, it will contain many unprintable characters. The solution to this is to encode it in base 64 for transport. Again, in PHP:

$hash = *base64_encode($sha256);*

Calculating it out yields the completed hash:

$hash = yneSFMyxPPe+3W4IOkVp50K3VStatBcRRak+2ygDUWQ=

The calculated hash can then be appended to the full API Query URL to form a completed request:

https://cloud.6connect.com/6c_375/api/v1/api.php?target=ipam&action=get&type=IP&mask=24&apiKey=32-5DAYTJQY2TZHOFOB&hash=yneSFMyxPPe+3W4IOkVp50K3VStatBcRRak+2ygDUWQ=

A Note on False Positives

ProVision utilizes several possible authentication schemes of which key-based API authentication is only one. Session-based, username /password authentication is used for the majority of user interaction with the ProVision front end. Because session information is stored in browsers cookies, a browser can be authenticated to execute API commands as long as the session is active.

Unfortunately, this can lead to confusion when using a machine-based API as the user might use an authenticated browser session to test API-Key based API queries. These queries will always succeed regardless of whether the API Query Hash was calculated correctly as the system defaults to Session-based authentication when it is available.

To ensure that session-based authentication is not polluting your API-Key based testing, always use a separate browser which is not logged in to your ProVision instance to test API queries.

Other Languages

The 6Connect API can be used in just about any scripting or programming language. We have a PHP SDK that provides example code, and several useful functions for interacting with the API. Even if you don't want to use PHP, the samples will help you create code in other languages

APIv1 - Getting Started with the SDK

The 6connect API allows you to access to data and functions of the 6connect web tools. The SDK for PHP or Python will help you get this setup quickly by outlining the requirements, prerequisites and provide sample code.

SDK for PHP

Prerequisites

The API only comes with a licensed 6connect ProVision application. If you would like access to a ProVision license please contact sales@6connect.com.

Create Your API Credentials

To use the 6connect SDK for PHP, you will need a 6connect API Key and Secret Key.

To create your API Key and Secret Key:

- Log into your 6connect instance (hosted or local)
- Click on the Admin icon, and go into the Administration section.
- Click on the "API" tab.
- Select the user from the drop down you want to enable API access for, and click "Generate Keys".
- The API Key and the Secret Key will now appear directly below that.

*Note that generating a new API will automatically revoke an older API Key.

6connect recommends that each user accessing the API have their own API key configured. However, you can alternatively setup API users by functionality or roles. While the platform is flexible, you should follow your organizations security policies.

Important!

Your Secret Key is a secret! Only you and 6connect should ever know this information. It is important to keep it confidential to protect the privacy of your data. Store it securely and never share this key with other users or place it on other systems. Never include the secret key in requests to 6connect, support requests to 6connect, and never e-mail it to anyone. Do not share it outside your organization. No one who legitimately represents 6connect will ever ask you for your Secret Key.

Requirements

Aside from following the prerequisites, you will need a basic understanding of object oriented programming in PHP and the right tools installed on your system to use the API.

Minimum Requirements

- PHP 5.5 or newer.
- PHP JSON and PCRE extensions (XML will be coming soon).
- Curl PHP extension compiled with OpenSSL libraries. Click here for more information on curl.

If you aren't sure what is running on your system, you can create a php page on your system and call phpinfo() and view this page in a browser, or run php -i on the command line.

Install the SDK

Download the file "6connect_ProVision_PHP_SDK_5_1_4.tar" from the attachments list below:

File	Modified

Configure the SDK Security Credentials

- Extract the zipped tar file to a directory.
- Open the api-config.php located in the downloaded SDK files.
- Read through the file and place in your instance name (or path for local installs), API Key and Secret Key information as specified.
- Make sure all files are in the same directory (the core class looks for a config file in the same directory by default).
- Run the sample code api-examples.php!

Important!

You must setup user API access before running the sample. See the previous section "Create Your API Credentials" for more information.

SDK for Python

Install the SDK

Download the file "6c-api-examples-python.zip" from the attachments list below:

File	Modified

Configure the SDK Security Credentials

- Extract the zipped tar file to a directory.
- Open the apiclient.py located in the downloaded SDK files.
- Read through the file and place in your instance name (or path for local installs), API Key and Secret Key information as specified.
- Make sure all files are in the same directory (the core class looks for a config file in the same directory by default).
- Run the sample code api-examples.php!

Important!

You must setup user API access before running the sample. See the previous section "Create Your API Credentials" for more information.

APIv1 Documentation (Deprecated)

- API Module - Admin and Audit
- API Module - DHCP
- API Module - DNS
- API Module - IPAM
- API Module - LIR
- API Module - Peering
- API Module - Resource
- API Module - VLAN
- APIv1 SDK
- How Do I...

API Module - Admin and Audit

Admin and Audit

This section covers the functions found under the Admin section of ProVision.

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

Table of Contents

- Authentication Testing
- Backup
- Log Management
- Scheduler API
- Zone Templates

Authentication Testing

- Authentication Testing
  - testSSH
  - testLDAP
  - testSecure64

Authentication Testing

testSSH

URL	/api/v1/api.php?target=auth&action=testSSH
Description	Returns success or failure of a connection to an external server via SSH.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Success!"} ERROR: *{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
SSHServer	STRING	totally.awesome.com	IP or FQDN of server.
SSHPort	NUMBER	22	Port ssh is running on.

Optional Parameters

Name	Type	Example	Description
username	STRING	jsmith	Username on target server.
password	STRING	password123	Password for user.
directory	STRING	/tmp	Directory to attempt to access after successful login.

Example URL	/api/v1/api.php?target=auth&action=testSSH&username=jsmith&password=password123&directory=%2Fvar%2Fnamed%2F6connect%2Fqa4&SSHPort=22&SSHServer=myssh.awesome.com

testLDAP

URL	/api/v1/api.php?target=auth&action=testLDAP
Description	Test basic connectivity to an LDAP server. Does not test actual authenticaion against server.
Returns	**Examples:** SUCCESSFUL: *{'success':1, 'id':'12345'}* ERROR: *{'success':0, 'message':'unable to add block'}>*

Required Parameters

Name	Type	Example	Description
ldapServer	STRING	ldap.awesome.com	IP or FQDN of the LDAP server.

	ldapPort	NUMBER	389	User-defined block code as defined in Admin-IPAM settings: Generic Code Per Block Name
	ldapMode	STRING	SSL	Options are: SSL, TLS, or None.
Optional Parameters	None			
Example URL	/api/v1/api.php?target=auth&action=testLDAP&ldapPort=389&ldapServer=ldap.awesome.com&ldapMode=None			

testSecure64

URL	/api/v1/api.php?target=auth&action=testSecure64
Description	Returns success or failure of a connection to an Secure64 DNS appliance.
Returns	**Examples:** SUCCESSFUL {"success":1,"message":"Success!"} ERROR *{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
SSHServer	STRING	totally.awesome.com	IP or FQDN of server.
SSHPort	NUMBER	22	Port ssh is running on.

Optional Parameters

Name	Type	Example	Description
username	STRING	jsmith	Username on target server.
password	STRING	password123	Password for user.
directory	STRING	/tmp	Directory to attempt to access after successful login.

Example URL: /api/v1/api.php?target=auth&action=testSecure64&username=jsmith&password=password123&directory=%2Fvar%2Fnamed%2F6connect%2Fqa4&SSHPort=22

Backup

- Backup
  - backup now

Backup

backup now

URL	/api/v1/api.php?target=backup&action=now
Description	Performs a manual backup to the designated location.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Backup via curl complete: "} ERROR: *{"success":0, "message":"Error Message"}>*
Required Parameters	

Name	Type	Example	Description
type	STRING	curl	File transfer type. Acceptable values are 'curl' or 'scp'

Optional Parameters

Name	Type	Example	Description
resource	INTEGER	2213	The server resource id to backup to. If left blank, backs up to the 6connect cloud.

Example URL	**Backup to designated server:** /api/v1/api.php?target=backup&action=now&type=scp&resource_id=2213 **Backup to 6connect cloud:** /api/v1/api.php?target=backup&action=now&type=curl

When specifying a backup server resource ID, that server must have the Hostname, Username, and Password fields correctly provided in ProVision.

Log Management

- Log Management
  - Get

Log Management

Get

URL	/api/v1/api.php?target=log&action=get
Description	Returns a list of log entries. Use optional parameters to filter the list.

Returns

Examples:

SUCCESSFUL	*{"success":1,"message":"Search Successful.","data":[{"logId":"31568","time": "2012-05-07 17:44:43", "logLevel":"INFO","userId":"39","userName": "user@6connect.com","logCategory": "User","message": "User Doe (user@6connect.com) logged in via local authentication","ip":"107.111.0.228"}]}*
ERROR	*{'success':0, 'message':'error message'}*

Data Detail

Name	Type	Example	Description
log_id	INTEGER	24	Unique log entry id.
time	DATETIME	2012-05-07 22:10:07	Date and time year to second.
log_level	STRING	NOTICE	Standard syslog log levels in verbose format (EMERG, ALERT, CRIT, ERR, WARNING, NOTICE, INFO, DEBUG).
user_id	INTEGER	11	The unique user id associated with the log entry.
username	STRING	user@6connect.com	The unique user name associated with the log entry.
log_category	STRING	IPAM	The 6connect category for the log entry (User, IPAM, Resource Holder, DNS, Peering, Assistant, NTP, Reporting).
message	STRING	Created new children from 1.0.0.0/24	The detailed log message.
ip	STRING	107.111.0.228	The remote IP address of the user who took the action being logged.

Required Parameters

None*

*There are no required parameters, but at least one optional parameter must be provided for the call to succeed.

Optional Parameters

Name	Type	Example	Description
block_id	INTEGER	310	Id of the IPAM netblocks to which the logs belong
get_attributes	BOOLEAN	1	Display the log attributes along with the log into the client's response. (The attributes for each log record). Valid values are 1 (true) and 0 (false).
log_id	INTEGER	24	Unique log entry id.
time_min	DATETIME	2015-05-07 [21:00:00]	Retrieve logs starting at this Date and optional time year to second.
time_max	DATETIME	2015-05-07 [22:	Retrieve logs ending at this Date and optional time year to second.

			00:00]	
	limit	INTEGER	100	Total log entries to retrieve. Default limit is 1000 records.
	orderby	STRING	log_id	Order results by log_id, time, log_level
	order	STRING	ASC	Order by ascending / descending (ASC / DESC).
	offset	INTEGER	50	Offset from 0 to retrieve log entries
	username	STRING	user@6connect.com	The unique user name associated with the log entry.
	log_category	STRING	IPAM	The 6connect category for the log entry (User, IPAM, Resource Holder, DNS, Peering, Assistant, NTP, Reporting).
	log_level	STRING	NOTICE	Standard syslog log levels in verbose format (EMERG, ALERT, CRIT, ERR, WARNING, NOTICE, INFO, DEBUG).
	ip	STRING	1.2.3.4	The remote IP address of the user whose action was logged
	search	STRING	Aggregate Added	Search for a string in the logs. It searches in 'message', 'username', 'time', 'ip' and 'log_category'
	time	DATETIME	2015-05-07 [21:00:00]	Search logs from a specific time.
Example URL	/api/v1/api.php?target=log&action=get&block_id=310&order_by=log_id&order=DESC			

Scheduler 1

This API is in beta and subject to change.

- Scheduler
  - addTask
  - updateTask
  - deleteTask
  - executeTask
  - getTaskHistory
  - getTasks

Scheduler

addTask

URL	/api/v1/api.php?target=scheduler&action=addTask
Description	Add a new scheduled task. Request is POST-only. Params are a single JSON object:
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Message "} ERROR: *{"success":0, "message":"Error Message"}>*

Required Parameters

Name	Type	Example	Description
user_id	INTEGER	100	User ID
name	STRING	Process Holding Tank	Name given to the new
class_name	STRING	\scheduler\Tasks\ProcessHoldingTask	PHP-namespaced name for the task class. Currently available: \scheduler\Tasks\ProcessHoldingTask \scheduler\Tasks\BackupTask \scheduler\Tasks\DNSPushTask
data		{}	
active	BOOL	true	
repeat_items			

Optional Parameters

Name	Type	Example	Description
repeat_start	STRING	2015-05-06	Date to start repeating task. Date must be in YYYY-MM-DD format.
repeat_end	STRING	null	Date to end repeating task or null. Date must be in YYYY-MM-DD format.
repeat_hour	INTEGER	8	Hour of day to repeat, from 0-23
repeat_minute	INTEGER	0	Minute of that hour to repeat, from 0-59
repeat_day	INTEGER	1	Day of month, from 1-31
repeat_week	INTEGER	1	Week of month, from 1-5
repeat_weekday	INTEGER	1	Days to repeat. Sun-Sat are from 0-6 respectively

updateTask

URL	/api/v1/api.php?target=scheduler&action=updateTask
Description	Update a scheduler task
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"*Message*"} ERROR: *{"success":0, "message":"Error Message"}>*

Required Parameters

Name	Type	Example	Description
id	INTEGER	4	ID of the task to be updated
user_id	INTEGER	100	User ID
name	STRING	Process Holding Tank	Name given to the new
class_name	STRING	\scheduler\Tasks\ProcessHoldingTask	PHP-namespaced name for the task class. Currently available: \scheduler\Tasks\ProcessHoldingTask \scheduler\Tasks\BackupTask \scheduler\Tasks\DNSPushTask
data		{}	
active	BOOL	true	
repeat_items			

Optional Parameters

Name	Type	Example	Description
repeat_start	STRING	2015-05-06	Date to start repeating task. Date must be in YYYY-MM-DD format.
repeat_end	STRING	null	Date to end repeating task or null. Date must be in YYYY-MM-DD format.
repeat_hour	INTEGER	8	Hour of day to repeat, from 0-23
repeat_minute	INTEGER	0	Minute of that hour to repeat, from 0-59
repeat_day	INTEGER	1	Day of month, from 1-31
repeat_week	INTEGER	1	Week of month, from 1-5
repeat_weekday	INTEGER	1	Days to repeat. Sun-Sat are from 0-6 respectively

deleteTask

URL	/api/v1/api.php?target=scheduler&action=deleteTask
Description	Delete a scheduler task
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Task \"New Task\" (2) deleted","data":null} ERROR: *{"success":0, "message":"Error Message"}>*

Required Parameters

Name	Type	Example	Description
taskId	INTEGER	4	ID of the task to delete

Optional Parameters	None
Example URL	/api/v1/api.php?target=scheduler&action=deleteTask&taskId=2

executeTask

URL	/api/v1/api.php?target=scheduler&action=executeTask
Description	Execute a task immediately
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Holding tank processed. 0 IPv4 and 0 IPv6 blocks moved to the available pool. ","data":null} ERROR: *{"success":0, "message":"Error Message"}>*
Required Parameters	**Name** / **Type** / **Example** / **Description** taskId / INTEGER / 4 / ID of the task to run
Optional Parameters	None
Example URL	/api/v1/api.php?target=scheduler&action=executeTask&taskId=1

getTaskHistory

URL	/api/v1/api.php?target=scheduler&action=getTaskHistory
Description	Get history for a specific task
Returns	**Examples:** SUCCESSFUL: { "success": 1, "data": [{ "log_id": "1005037", "time": "2015-05-07 12:29:45", "log_level": "6", "user_id": "31", "username": "usernamehere", "log_category": "System", "message": "task_id=1 task=Process Holding Tank action=finished message=Holding tank processed. 0 IPv4 and 0 IPv6 blocks moved to the available pool.", "ip": null }, { "log_id": "1005033", "time": "2015-05-07 12:28:50", "log_level": "6", "user_id": "31", "username": "usernamehere", "log_category": "System", "message": "task_id=1 task=Process Holding Tank action=finished message=Holding tank processed. 1 IPv4 and 0 IPv6 blocks moved to the available pool.", "ip": null }, { "log_id": "1005030", "time": "2015-05-07 12:28:14", "log_level": "6", "user_id": "31", "username": "usernamehere", "log_category": "System", "message": "Task \"Process Holding Tank\" (1) added", "ip": null }] } ERROR: *{"success":0, "message":"Error Message"}>*
Required Parameters	**Name** / **Type** / **Example** / **Description** taskId / INTEGER / 1 / ID of the task to view
Optional Parameters	None
Example URL	/api/v1/api.php?target=scheduler&action=getTaskHistory&taskId=1

getTasks

URL	/api/v1/api.php?target=scheduler&action=getTasks
Description	Gets a list of scheduled tasks and their repeat settings
Returns	

	Examples: SUCCESSFUL: { "success": 1, "data": [{ "id": "1", "user_id": "31", "name": "Process Holding Tank", "class_name": "\\scheduler\\Tasks\\ProcessHoldingTask", "active": true, "data": null, "last_run": "2015-05-07 12:29:45", "repeat_items": [{ "id": "1", "task_id": "1", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "4", "repeat_hour": "20", "repeat_minute": "0" }, { "id": "2", "task_id": "1", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "5", "repeat_hour": "20", "repeat_minute": "0" }, { "id": "3", "task_id": "1", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "6", "repeat_hour": "20", "repeat_minute": "0" }, { "id": "4", "task_id": "1", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "0", "repeat_hour": "20", "repeat_minute": "0" }] }, { "id": "2", "user_id": "31", "name": "New Task", "class_name": "\\scheduler\\Tasks\\TestTask", "active": true, "data": null, "last_run": "2015-05-07 12:35:41", "repeat_items": [{ "id": "5", "task_id": "2", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "1", "repeat_hour": "21", "repeat_minute": "0" }, { "id": "6", "task_id": "2", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "2", "repeat_hour": "21", "repeat_minute": "0" }, { "id": "7", "task_id": "2", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "3", "repeat_hour": "21", "repeat_minute": "0" }, { "id": "8", "task_id": "2", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "4", "repeat_hour": "21", "repeat_minute": "0" }, { "id": "9", "task_id": "2", "repeat_start": "2015-05-06", "repeat_end": null, "repeat_interval": null, "repeat_year": "*", "repeat_month": "*", "repeat_day": "*", "repeat_week": "*", "repeat_weekday": "5", "repeat_hour": "21", "repeat_minute": "0" }] }] } ERROR: *{"success":0, "message":"Error Message"}>*
Required Parameters	None
Optional Parameters	None
Example URL	/api/v1/api.php?target=scheduler&action=getTasks

Zone Templates

- Zone Templates
  - Get
  - Update
  - Delete

Zone Templates

Get

URL	/api/v1/api.php?target=zoneTemplate&action=get
Description	Returns success or failure of a connection to an external server via SSH.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Found 1 records for template \"Awesome Template\".","data":{"templateId":"1011","name":"Awesome Template","created":"2013-07-31 14:01:24","modified":"2013-07-31 14:01:24","userId":"112","soa":null,"refresh":"14400","retry":"3600","expire":"604800","minimum":null,"ttl":null,"userName":"joe@smith.com","records":[{"templateRecordId":"4","templateId":"1011","host":"www","type":"A","ttl":"3600","value":"1.2.3.4","ordering":"0"}]}} ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	None
Optional Parameters	**Name** / **Type** / **Example** / **Description** templateId / NUMBER / 3 / ID of the specific template to get.
Example URL	/api/v1/api.php?target=zoneTemplate&action=get

Update

URL	/api/v1/api.php?target=zoneTemplate&action=update
Description	Create a new template or update an existing template.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Template updated","data":{"templateId":"1011","name":"Awesome Template","created":"2013-08-05 23:15:52","modified":"2013-08-05 23:15:52","userId":"112","soa":"ns1.test.net hostmaster.ns1.test.net","refresh":"14400","retry":"3600","expire":"604800","minimum":null,"ttl":false,"userName":"anna@6connect.com","records":"1"}} ERROR: *{'success':0, 'message':'Error updating template: error details'}>*
Required Parameters	**Name** / **Type** / **Example** / **Description** name / STRING / Test Template / The name of the template to be created or updated.
Optional	

Parameters

Name	Type	Example	Description
soa	STRING	ns1.test.net hostmaster.ns1.test.net	A valid SOA for the template in for format
ttl	INTEGER	86400	The TTL for the zone template, which is the default expiration time for all records witho own TTL.
refresh	INTEGER	14400	The time period for slaves to refresh the zone.
retry	INTEGER	3600	Time that a slave should retry refreshing the zone in case of incident.
expire	INTEGER	604800	Time for a slave to expire a zone.
mininum	INTEGER	3600	The maximum caching time in the event of failed lookups.
count_records	INTEGER	5	Number of host records submitted with the update. All the following parameters names followed with their position in the count. In this example, the first record would have all parameters for the first record followed by _1, the second record _2, and so on. This w order all records in the template follow.
host_1	STRING		The DNS record value.
ttl_1	INTEGER	3600	TTL of the specific host record.
type_1	STRING	A	A valid DNS record type.
value_1	IP	1.2.3.4	A valid IPv4 or IPv6 address.

Example URL

api/v1/api.php?target=zoneTemplate&action=update&templateId=1011&count_records=1&name=Awesome+Template&soa=ns1.te net+hostmaster.ns1.test.net

&refresh=14400&retry=3600&expire=604800&minimum=3600&value_0=undefined+undefined&host_1=www&ttl_1=3600&type_1=A 2.3.4

Delete

URL: /api/v1/api.php?target=zoneTemplate&action=delete

Description: Deletes a DNS template.

Returns

Examples:

SUCCESSFUL	{"success":1,"message":"Template \"Test Template\" delete."}
ERROR	{"success":0,"message":"No template found for templateId \"1005\"."}

Required Parameters

Name	Type	Example	Description
templateId	INTEGER	3	ID of the template to delete.

Optional Parameters: None.

Example URL: /api/v1/api.php?target=zoneTemplate&action=delete&templateId=1005

API Module - DHCP

DHCP Management Version 2

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

- DHCP Management Version 2
  - Overview
  - API Updates
  - DHCP API How-To
    - Relate with Resources
    - Create DHCP IP Aggregates
    - Subnets and Hosts
    - Linking Subnets and Hosts with DHCP Servers
    - Pushing Configurations
  - Detailed API Specification

Overview

DHCP Management Version 2 integrates DHCP management with ProVision's resource and permissions hierarchy, as well as the IP Management system. Individual DHCP servers can be assigned via Resource Permissions to different internal user groups, to be managed by only the appropriate parties.

Under DHCPv2 there is no distinct “DHCP Server” type or section – instead there is a “DHCP Module” which, when attached as a child to an existing resource, transforms it into a DHCP-enabled device. The most common use is to take the generic “Server” Section and turn it into a DHCP Server by attaching the DHCP Module as a child. This configuration allows users to add functionality to a basic resource and provides a cleaner management interface.

API Updates

The DHCPv1 API operated via calls to the DHCPServer and the DHCPEntry endpoint families. However, now that DHCPv2 is contained entirely within the resource system, most of the API calls to manipulate DHCP data do so using the Resource family of API endpoints to modify specific Resource attributes reserved for DHCP functionality.

DHCP API How-To

Relate with Resources

The DHCPv2 system builds upon the ProVision Resource API. With the exception of a few configuration commands all DHCPv2 API commands use the Resource family of API endpoints.

As described above, DHCPv2 functionality is enabled on a particular resource by attaching a DHCP Module as a child. A command to do this is as follows:

```
            [ProVision root]/api/v1/api.php?target=resource&action=add

            data:
meta[type]: dhcp_module
meta[name]: [parent resource id] DHCP Module
meta[parent_id]: [parent resource id]
```

The special resource type “dhcp_module” indicates to ProVision that the DHCP system is enabled for the parent object. The attributes associated with the “dhcp_module” resource govern the DHCP system's behavior.

Updating the attributes of a DHCP Server uses a Resource Update command:

```
[ProVision root]/api/v1/api.php?target=resource&action=update&meta[id]=2178 &meta[type]=dhcp_module&fields
[_dhcp_attributes][]={"type":"ISC","notes":"notes go here","username":"username","port":"port","
config_test":"/etc/init.d/dhcpd configtest","server_stop":"/etc/init.d/dhcpd stop","server_start":"/etc/init.
d/dhcpd start","config_path":"/tmp/dhcpd.conf","option_routers":"192.168.0.0","option_domain_name_servers":"
ns1.6connect.com","option_domain_name":"6connect.com","authoritative":"1","default_lease_time":"600","
max_lease_time":"7200","local_port":"67","log_facility":"local7","password":"password","server_ip":"
192.168.0.1","freeLines":3,"freeLine1":"free line 1","freeLine2":"free line 2","freeLine3":"free line 3"}
```

This command appears rather complicated, but can be broken apart into reasonable pieces. The first section:

```
target=resource&action=update&meta[id]=2178&meta[type]=dhcp_module
```

is familiar from other parts of ProVision. We are updating a resource of type “dhcp_module” whose resource id is 2178. The second section of the command details the update values, starting with

```
 fields[_dhcp_attributes][]=
```

which contains a JSON-encoded string of all the fields specific to a DHCP server's function. When expanded into its full object form it is substantially easier to digest:

```
{
            "type":"ISC",
            "notes":"notes go here",
            "username":"username",
            "port":"port",
            "config_test":"/etc/init.d/dhcpd configtest",
            "server_stop":"/etc/init.d/dhcpd stop",
            "server_start":"/etc/init.d/dhcpd start",
            "config_path":"/tmp/dhcpd.conf",
            "option_routers":"192.168.0.0",
            "option_domain_name_servers":"ns1.6connect.com",
            "option_domain_name":"6connect.com",
            "authoritative":"1",
            "default_lease_time":"600",
            "max_lease_time":"7200",
            "local_port":"67",
            "log_facility":"local7",
            "password":"password",
            "server_ip":"192.168.0.1",
            "freeLines":3,
            "freeLine1":"free line 1",
            "freeLine2":"free line 2",
            "freeLine3":"free line 3"
}
```

This object describes all the most common DHCP server configuration options. For a full explanation of each of the fields, see the Detailed API Specification later in this document.

Please note that the object above must be passed to the DHCP system as a JSON-encoded string. It must be passed into the special “_dhcp_attributes” attribute for it to be functional, as in the example URL.

Create DHCP IP Aggregates

For details on how to manage IP aggregates using ProVision's IPAM API, see API Module - IPAM.

Of particular interest to DHCP management is the addition of DHCP aggregates, which are sections of IP space marked as available for use by the DHCPv2 system.

An example command to add a DHCP Aggregate is:

```
[ProVision root]/api/v1/api.php?target=ipam&action=add&block=192.168.0.0/24&rir=
1918&vlan=&tags=&region=&resourceId=1282&allowSubAssignments=true
```

The important part to note is that the IP block is being assigned to resourceId 1282, which corresponds to the DHCP Available resource. The DHCP Available resource is a system-level resource which is used to hold all unassigned DHCP IP addresses. Every instance has its own DHCP Available resource, whose id can be found with the following command:

```
[ProVision root]/api/v1/api.php?target=resource&action=get&slug=dhcp-available
```

New DHCP subnets and hosts draw their IPs from this pool. If there are no IPs in the DHCP Available pool new subnets and hosts will not be able to be created.

DHCP IP aggregates are fetched, updated, split, and deleted using the standard IPAM management API endpoints. Please see the IPAM API Documentation. for details.

Subnets and Hosts

Every DHCP configuration file consists primarily of Subnet and Host declarations, mapping out what IP addresses are available for what purpose. In DHCPv2, DHCP Pools are reusable components that can be attached to several DHCP Servers in order to build flexible, responsive DHCP configurations.

In ProVision DHCPv2 all DHCP Pools regardless of whether they span Subnets or individual Hosts require that a “dhcp_pool” resource be created to govern them.

Similar to how the “dhcp_module” resource was created above, the command to create a DHCP Pool is as follows:

```
[ProVision root]/api/v1/api.php?target=resource&action=add&meta[type]=dhcp_pool &meta[name]=New Subnet&fields
[_dhcp_type][]=subnet&fields[_dhcp_pool_attributes][]={"mac":"","rangeStart":"","rangeEnd":"","freeLines":3,"
freeLine1":"Free Line 1","freeLine2":"Free Line 2","freeLine3":"Free Line 3"}
```

The first half of this command is relatively straightforward:

```
target=resource&action=add&meta[type]=dhcp_pool&meta[name]=New Subnet
```

This section informs the API that we wish to create a new, empty “dhcp_pool” resource whose name is “New Subnet.”

```
fields[_dhcp_type][]=subnet&fields[_dhcp_pool_attributes][]={"mac":"","rangeStart":"", "rangeEnd":"","
freeLines":3,"freeLine1":"Free Line 1","freeLine2":"Free Line 2","freeLine3":"Free Line 3"}
```

The second half of the command behaves in a similar manner to the “dhcp_module.” The “_dhcp_pool_attributes” field holds a JSON-encoded string which describes the dhcp_pool resource. When expanded, the JSON string becomes the following object:

```
{
            "mac":"",
            "rangeStart":"",
            "rangeEnd":"",
            "freeLines":3,
            "freeLine1":"Free Line 1",
            "freeLine2":"Free Line 2",
            "freeLine3":"Free Line 3"
}
```

For a full explanation of each of the fields, see the Detailed API Specification.

Please note that the object above must be passed to the DHCP system as a JSON-encoded string. It must be passed into the “_dhcp_pool_attributes” attribute for it to be functional, as in the example URL.

Once a dhcp_pool resource is in the system it can be updated with IP data obtained from the IP Management system. Under DHCPv2, the DHCP system uses all the standard IPAM API endpoints and can make use of both the smartAssign and the directAssign methods. Please see the IPAM API documentation for details.
An example command for smart-assigning a DHCP IP range from the DHCP Available resource to a newly-created dhcp_pool resource is as follows:

```
[ProVision root]/api/v1/api.php?target=ipam&action=smartAssign&resourceId=2180&
type=ipv4&mask=31&rir=1918&assignedResourceId=1282
```

In this example we are using the IPAM API endpoint to smart-assign an IPv4 /31 from the DHCP Available resource (resource id 1282) to the newly-created dhcp_pool object (resource id 2180). This action removes this IP range from the available pool and prevents it from being used by other parts of ProVision.

Once an IP block is assigned to a dhcp_pool it should be updated with the proper range start and range end. A Resource Update command is used for this.

```
[ProVision root]/api/v1/api.php?target=resource&action=update&meta[type]=dhcp_pool& meta[name]=Another
Test&fields[_dhcp_type][]=subnet&fields[_dhcp_pool_attributes][]={"mac":"","rangeStart":"10.10.10.4","
rangeEnd":"10.10.10.5","freeLines":3,"freeLine1":"example1","freeLine2":"example2","freeLine3":"example3"}
&fields[_dhcp_ip_id][]=92430&meta[id]=2180
```

The key information here is that the “rangeStart” and the “rangeEnd” fields in the JSON-encoded '_dhcp_pool_attributes' attribute have been populated with the beginning and end of the IP range assigned by smart-assign. Also note that a new field is being populated as '_dhcp_ip_id', which contains the IPAM id of the newly-assigned IP block.

When assigning dhcp_pools covering a single host the steps are much the same, but the 'mac' field in the '_dhcp_pool_attributes' object must be populated with the MAC address of the host in question.

Linking Subnets and Hosts with DHCP Servers

DHCP Pools exist as re-usable components which can be individually assigned to any number of DHCP Servers in order to assemble flexible DHCP Configurations. Once created, a DHCP Pool is not attached to any DHCP Server in the system. DHCP Pools must be linked to a server for the pool to be included in DHCP configuration pushes.

An example of building a link between a dhcp_pool and a DHCP Server is:

```
[ProVision root]/api/v1/api.php?target=resource&action=addLink&resource_id1=2178&
resource_id2=1452&relation=dhcpPoolLink
```

The Resource Linkage system controls which DHCP Pools are associated with a given DHCP Server. In the case of linking a DHCP Pool to a DHCP Server, the relation used is “dhcpPoolLink”. This is a directional link, so it is important that resource_id1 and resource_id2 do not get confused.

```
relation:  "dhcpPoolLink"
resource_id1:  the id of the dhcp_module this pool is being linked to
resource_id2:  the id of the dhcp_pool being linked
```

It is very important that resource_id1 not be confused with resource_id2. The link will not function with the values reversed.

To undo the above and break a DHCP Pool link, use the same command but substitute “deleteLink” for the action “addLink”.

```
[ProVision root]/api/v1/api.php?target=resource&action=deleteLink&resource_id1=2178&
resource_id2=2179&relation=dhcpPoolLink
```

Pushing Configurations

Pushing configuration files and restarting a DHCP server is a fairly straightforward process.

Once the server has been configured according to the previous sections, hitting the following API endpoint will trigger a DHCP push:

```
[ProVision root]/api/v1/api.php?target=dhcp&action=push&id=2178
```

The “id” in the above string is the id of the dhcp_module resource attached to the server you whose configuration is to be pushed. The API return payload will contain success or failure codes, as well as a description of any errors which might have occurred.

When a DHCP configuration file is pushed an SSH connection is opened to the configured server using the user, password, and port supplied to the '_dhcp_attributes' attribute on the dhcp_module resource. If the system successfully connects, it will assemble a DHCP configuration from the information given to the dhcp_module's '_dhcp_attribute' attribute and then parse and add in all linked dhcp_pool resources.

After the assembled file has been transferred to the DHCP server it will be placed in the location given by 'config_path' on the dhcp_module, and then the command described in 'config_test' will be run to determine whether or not this new file parses correctly. If 'config_test' is blank or omitted, this step is skipped.

If the file parses correctly the DHCP will be stopped and restarted according to the 'server_stop' and 'server_start' commands on the DHCP module. If there are errors at any point the system backs out, replaces old config files, and reports the errors via the 'message' return field of the API call.

Detailed API Specification

A detailed listing of API endpoints related to DHCP Servers, Pools, and Links can be found here:

- API Module - DHCPv2

API Module - DHCPv2

- DHCPv2 Module
  - get all DHCP-enabled resources
  - create a new DHCP-enabled resource
  - update a DHCP-enabled resource with new configuration info
  - remove DHCP functionality from a resource
  - get all DHCP Pools
  - create a new DHCP Pool resource
  - update a DHCP Pool
  - delete a DHCP Pool
  - assigning an IP address or blocks to a DHCP Pool
  - get all DHCP Pool linkages
  - add a new DHCP Pool linkage
  - delete DHCP Pool linkages
  - push a DHCP config
  - DHCP search
- Data Attributes
  - _dhcp_attributes
  - _dhcp_pool_attributes

DHCPv2 Module

The DHCPv2 system is built upon the Resource API, so actions relating to DHCP tasks are largely expressed in terms of Resource actions.

This section describes common DHCP tasks and how they are accomplished via the DHCPv2 system.

get all DHCP-enabled resources

Description	Finds all resources from section 'dhcp_module,' which indicates that their parents are DHCP-enabled. Adding in other Resource-Get API parameters can filter this list further.
URL	/api/v1/api.php?target=resource&action=get&type=dhcp_module
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Search successful","data":[{"id":"1432", "name":"1392 DHCP Module" ,"slug":"1392-dhcp-module", "type":"dhcp_module", "parent_id":"1392", "category_id":null, "attr":{"_dhcp_attributes":"{\"type\":\"ISC\", \"notes\":\"\", \"username\":\"\", \"port\":\"\", \"config_test\":\"\/etc\/init.d\/dhcpd configtest\", \"server_stop\":\"\/etc\/init.d\/dhcpd stop\", \"server_start\":\"\/etc\/init.d\/dhcpd start\", \"config_path\":\"\", \"option_routers\":\"\", \"option_domain_name_servers\":\"\", \"option_domain_name\":\"\", \"authoritative\":\"1\", \"default_lease_time\":\"600\", \"max_lease_time\":\"7200\", \"local_port\":\"67\", \"log_facility\":\"local7\", \"password\":\"\", \"server_ip\":\"10.0.0.0\", \"freeLines\":0}", "_dhcp_config_id":"33"}}], "result_count":1, "found_count":1}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	ID of the dhcp_module resource
name	STRING	The name of the dhcp_module
slug	STRING	The unique reference string for this resource
type	STRING	Always 'dhcp_module
parent_id	INTEGER	The resource to which the dhcp_module is attached
category_id	INTEGER	The category to which this dhcp_module is associated

result_count	INTEGER	How many dhcp_modules are returned in this search.
found_count	INTEGER	How many dhcp_modules were found in this query, without pagination.

Attributes:

Key	Type	Description
_dhcp_attributes	JSON	A JSON-encoded string containing all the specific configuration parameters which govern this DHCP server. An expansion of the JSON object is given below in the Data Attributes section.
_dhcp_config_id	INTEGER	A reference to the DHCP Config file written within the system. This field is maintained by the DHCPv2 system itself and should not be set externally.

create a new DHCP-enabled resource

Description	A resource becomes a DHCP-enabled by adding a special "dhcp_module" resource as a child. This action is identical to a normal Resource Create command.
URL	/api/v1/api.php?target=resource&action=add&meta[type]=dhcp_module&meta[name]=2163 DHCP Module&meta[parent_id]=2163
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Resource added","data":{"id": 2165,"name" :"2163 DHCP Module","slug": "2163-dhcp-module-2","type" :"dhcp_module","parent_id": 2163,"category_id": null,"attr":[]}}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	ID of the newly created dhcp_module
name	STRING	The name of the dhcp_module
slug	STRING	The unique reference string for this resource
type	STRING	Always 'dhcp_module'
parent_id	INTEGER	The resource to which the dhcp_module is attached
category_id	INTEGER	The category to which this dhcp_module is associated

update a DHCP-enabled resource with new configuration info

Description	Modifying an existing dhcp_module uses the identical commands as all other Resource-Update actions. An example of configuring a DHCP server is given below.
URL	/api/v1/api.php?target=resource&action=update&meta[id]=2178 &meta[type]=dhcp_module&fields[_dhcp_attributes][]={"type":"ISC","notes":"notes go here","username":"username","port":"port","config_test":"/etc/init.d/dhcpd configtest","server_stop":"/etc/init.d/dhcpd stop","server_start":"/etc/init.d/dhcpd start","config_path":"/tmp/dhcpd.conf","option_routers":"192.168.0.0","option_domain_name_servers":"ns1.6connect.com","option_domain_name":"6connect.com","authoritative":"1","default_lease_time":"600","max_lease_time":"7200","local_port":"67","log_facility":"local7","password":"password","server_ip":"192.168.0.1","freeLines":3,"freeLine1":"free line 1","freeLine2":"free line 2","freeLine3":"free line 3"}
Returns	**Examples:**

SUCCESSFUL:	{"success": 1,"message": "Resource Updated","data": {"id":"2166" ,"name":"2163 DHCP Module", "slug":" 2163-dhcp-module-3" ,"type":"dhcp_module", "parent_id":"2163", "category_id":null ,"attr": {"_dhcp_attributes": "{\"type\":\"ISC\", \"notes\":\"notes go here\", \"username\":\"username\", \"port\":\"port\", \"config_test\":\"\\\/etc\\\/init.d\\\/dhcpd configtest\" ,\"server_stop\":\"\\\/etc\\\/init.d\\\/dhcpd stop\" ,\" server_start\":\"\\\/etc\\\/init.d\\\/dhcpd start\",\"config_path\":\"\\\/tmp\\\/dhcpd.conf\", \"option_routers\":\" 192.168.0.0\", \"option_domain_name_servers\":\"ns1.6connect.com\", \"option_domain_name\":\"6connect. com\", \"authoritative\":\"1\", \"default_lease_time\":\"600\", \"max_lease_time\":\"7200\", \"local_port\":\"67\", \" log_facility\":\"local7\" ,\"password\":\"**********\", \"server_ip\":\"192.168.0.1\", \"freeLines\":3, \"freeLine1\":\" free line 1\", \"freeLine2\":\"free line 2\", \"freeLine3\":\"free line 3\"}"}}}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	ID of the newly created dhcp_module
name	STRING	The name of the dhcp_module
slug	STRING	The unique reference string for this resource
type	STRING	Always 'dhcp_module'
parent_id	INTEGER	The resource to which the dhcp_module is attached
category_id	INTEGER	The category to which this dhcp_module is associated

Attributes:

Key	Type	Description
_dhcp_attributes	JSON	A JSON-encoded string containing all the specific configuration parameters which govern this DHCP server. An expansion of the JSON object is given below in the Data Attributes section.

remove DHCP functionality from a resource

Description	To remove DHCP functionality, delete the dhcp_module child resource. This operation uses general Resource->Delete functionality.
URL	/api/v1/api.php?target=resource&action=delete&id=2166
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Deleted 2163-dhcp-module-3 (#2166)"}
ERROR:	{"success":0, "message":"error message"}

get all DHCP Pools

Description	As with the dhcp_module commands, the API endpoints governing DHCP IP Pools use the general Resource system. All the modifiers that can be applied to a Resource-Get can be used to filter this query.
URL	/api/v1/api.php?target=resource&action=get&type=dhcp_pool
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Search successful","data":[{"id":"1482","name":"Blah","slug":"blah","type":" dhcp_pool","parent_id":"1","category_id":null,"attr":{"_dhcp_type":"subnet","_dhcp_pool_attributes":"{\"mac\":

	\"\",\"rangeStart\":\"13.0.0.0\",\"rangeEnd\":\"13.0.0.255\",\"freeLines\":0}","_dhcp_ip_id":"80902"}}],"result_count":1,"found_count":1}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	ID of the dhcp_pool resource
name	STRING	The name of the dhcp_pool
slug	STRING	The unique reference string for this resource
type	STRING	Always 'dhcp_pool'
parent_id	INTEGER	The resource to which the dhcp_pool is attached
category_id	INTEGER	The category to which this dhcp_pool is associated
result_count	INTEGER	How many dhcp_pools are returned in this search.
found_count	INTEGER	How many dhcp_pools were found in this query, without pagination.

Attributes:

Key	Type	Description
_dhcp_type	STRING	Either 'subnet' or 'host'. Determines whether this DHCP Pool is describing a Subnet or a Host.
_dhcp_pool_attributes	JSON	A JSON-encoded string containing all the specific configuration parameters which govern this DHCP Pool. An expansion of the JSON object is given below in the Data Attributes section.
_dhcp_ip_id	INTEGER	The id of the IPAM subnet or host which is assigned to this DHCP Pool

create a new DHCP Pool resource

Description	Uses the general Resource-Add endpoint to create a DHCP Pool resource.
URL	/api/v1/api.php?target=resource& action=add& meta[type]=dhcp_pool& meta[name]=New Subnet& fields[_dhcp_type][]=host& fields[_dhcp_pool_attributes][]={"mac":"aa:bb:cc:dd:ee:ff", "rangeStart":"", "rangeEnd":"", "freeLines":3, "freeLine1":"Free Line 1", "freeLine2":"Free Line 2", "freeLine3":"Free Line 3"}
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Resource added","data":{"id":2167,"name":"New Subnet","slug":"new-subnet","type":"dhcp_pool ","parent_id":1,"category_id":null,"attr":[]}}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	ID of the newly created dhcp_pool
name	STRING	The name of the dhcp_pool
slug	STRING	The unique reference string for this resource
type	STRING	Always 'dhcp_pool'
parent_id	INTEGER	The parent resource; by default the TLR.

category_id	INTEGER	The category to which this dhcp_pool is associated

update a DHCP Pool

Description	Modifying an existing dhcp_pool uses the identical commands as all other Resource-Update actions.
URL	/api/v1/api.php?target=resource& action=update& meta[type]=dhcp_pool& meta[name]=Another Test& fields[_dhcp_type][] =subnet& fields[_dhcp_pool_attributes][]={"mac":"", "rangeStart":"10.10.10.4", "rangeEnd":"10.10.10.5", "freeLines":3, "freeLine1":"example1", "freeLine2":"example2", "freeLine3":"example3"}&fields[_dhcp_ip_id][]=92430&meta[id]=2165
Returns	**Examples:**

SUCCESSFUL:	{"success":1, "message":"Resource Updated", "data":{"id":"2165", "name":"Another Test", "slug":"2163-dhcp-module-2", "type":"dhcp_module", "parent_id":"2163", "category_id":null,"attr":{"_dhcp_type":"subnet" ," _dhcp_pool_attributes":"{\"mac\":\"\", \"rangeStart\":\"10.10.10.4\", \"rangeEnd\":\"10.10.10.5\", \"freeLines\": 3, \"freeLine1\":\"example1\", \"freeLine2\":\"example2\", \"freeLine3\":\"example3\"}", "_dhcp_ip_id":" 92430"}}}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	ID of the newly created dhcp_module
name	STRING	The name of the dhcp_module
slug	STRING	The unique reference string for this resource
type	STRING	Always 'dhcp_module'
parent_id	INTEGER	The resource to which the dhcp_module is attached
category_id	INTEGER	The category to which this dhcp_module is associated

Attributes:

Key	Type	Description
_dhcp_type	STRING	Either 'subnet' or 'host'. Determines whether this DHCP Pool is describing a Subnet or a Host.
_dhcp_pool_attributes	JSON	A JSON-encoded string containing all the specific configuration parameters which govern this DHCP Pool. An expansion of the JSON object is given below in the Data Attributes section.
_dhcp_ip_id	INTEGER	The id of the IPAM subnet or host which is assigned to this DHCP Pool

delete a DHCP Pool

Description	To delete a DHCP Pool, use the standard Resource-Delete functionality
URL	/api/v1/api.php?target=resource&action=delete&id=2165
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Deleted 2165-another-subnet-3 (#2165)"}

ERROR:	{"success":0, "message":"error message"}

assigning an IP address or blocks to a DHCP Pool

Description	Assigning IP addresses or blocks to a DHCP Pool resource removes them from the available pool so they cannot be assigned out again. This procedure uses all the standard IPAM assignment functions, so long as the resource assigned **from** is the DHCP Available resource.
URL	/api/v1/api.php?target=ipam&action=smartAssign&resourceId=2162&type=ipv4&mask=31&rir=1918&assignedResourceId=1282
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Assigned 10.8.1.4\/31 to 208.39.104.106 (2162) via Smart Assign","id":94468,"data":{"id":94468,"type":"ipv4","top_aggregate":44616,"cidr":"10.8.1.4\/31","formatted_ip":"10.8.1.4\/31","address":"168296708","end_address":"168296709","mask":31,"netmask":"255.255.255.254","child1":null,"child2":null,"is_assigned":1,"is_swipped":0,"is_aggregate":1,"custid":2162,"resource_id":2162,"resource_name":null,"last_updated_time":"2015-03-15 20:17:32","description":null,"parent":80882,"rir":"1918","lir_id":null,"notes":null,"generic_code":null,"code":null,"region":"Quito","region_name":"Quito","vlan":null,"arin_net_id":null,"arin_cust_id":null,"org_id":null,"arin_swip_time":null,"assigned_time":"2015-03-15 20:17:32","asn":null,"allowSubAssignments":false,"permissions":[],"range":"10.8.1.4 - 10.8.1.5","tags":["DHCP"]}} ERROR: {"success":0, "message":"error message"} **Return Detail:** For a detailed breakdown of this endpoint's return data, please see the IPAM documentation.

get all DHCP Pool linkages

Description	The association between DHCP Pools and DHCP Modules belongs to the Resource Linkage family of endpoints. The 'relation' field should be set to the 'dhcpPoolLink' type to pull only DHCP Pool linkage information.
URL	/api/v1/api.php?target=resource&action=getLink&relation=dhcpPoolLink
Returns	**Examples:** SUCCESSFUL: {"success":1 ,"message":"Search successful", "data":{"meta":{"totalRecords":"3", "retrieved":3}, "0":{"id":"22", "resource_id1":"1292", "resource_id2":"1302", "relation":"dhcpPoolLink"}, "1":{"id":"2", "resource_id1":"1292", "resource_id2":"1452", "relation":"dhcpPoolLink"}, "2":{"id":"12", "resource_id1":"1422", "resource_id2":"1482", "relation":"dhcpPoolLink"}}} ERROR: {"success":0, "message":"error message"} **Return Detail:**

Name	Type	Description
id	INTEGER	Id of the pool-module linkage
resource_id1	INTEGER	The id of the dhcp_module resource
resource_id2	INTEGER	The id of the dhcp_pool resource
relation	STRING	The relation type. Always 'dhcpPoolLink'

Meta Attributes:

Name	Type	Description

totalRecords	INTEGER	How many records were found by this query, without pagination.
retrieved	INTEGER	How many records were returned by this query, with pagination.

Optional Attributes:

Name	Type	Description
resultsPerPage	INTEGER	How many records to include per page display.*
page	INTEGER	Which page to display, when used with "resultsPerPage"*
*Example pagination: api.php?target=resource&action=getLink&relation=dhcpPoolLink&resultsPerPage=100&page=2		

add a new DHCP Pool linkage

Description	Adds a new link between a DHCP Pool and a dhcp_module resource. A single pool can be linked to many dhcp_modules, and a single dhcp_module can have any number of linked pools.
URL	/api/v1/api.php?target=resource&action=addLink&resource_id1=1292&resource_id2=2162&relation=dhcpPoolLink
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Resource link added"}
ERROR:	{"success":0, "message":"error message"}

Data Detail:

Name	Type	Description
resource_id1	INTEGER	The id of the dhcp_module resource
resource_id2	INTEGER	The id of the dhcp_pool resource
relation	STRING	The relation type being added. Always 'dhcpPoolLink'

delete DHCP Pool linkages

Description	Deletes a link between a dhcp_module and a dhcp_pool. Uses the standard Resource Linkage endpoints.
URL	/api/v1/api.php?target=resource&action=deleteLink&id=22
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Resource link(s) deleted."}
ERROR:	{"success":0, "message":"error message"}

push a DHCP config

Description	Builds a DHCP configuration from the attributes assigned to a dhcp_module and all of the linked dhcp_pools. Pushes that config to the configured DHCP server, tests it against the config parsing function, then restarts the server with the new configuration.
URL	/api/v1/api.php?target=dhcp&action=push&id=1292
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Pushes Attempted.","data":[[1,"1292","381 DHCP Module","Configuration successfully pushed."]]}
ERROR:	{"success":0, "message":"error message"}

Data Detail

Name	Type	Description
id	INTEGER	The id of the dhcp_module resource whose configuration is to be pushed.

DHCP search

Description	Searches DHCP information by name, mac, or IP.
URL	/api/v1/api.php?target=dhcp&action=search&searchType=name&searchValue=Blah /api/v1/api.php?target=dhcp&action=search&searchType=mac&searchValue=22: /api/v1/api.php?target=dhcp&action=search&searchType=ip&searchValue=13.0.0.255
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Search Successful","data":[{"id":"1482","name":"BlahBlah","slug":"blah","type":"dhcp_pool","parent_id":"1","category_id":null,"attr":{"_dhcp_type":"subnet","_dhcp_pool_attributes":"{\"mac\":\"\",\"rangeStart\":\"13.0.0.0\",\"rangeEnd\":\"13.0.0.255\",\"freeLines\":0}","_dhcp_ip_id":"80902"},"dhcp_links":["1422","3673"]}]}
ERROR:	{"success":0, "message":"error message"}

Return Detail

Name	Type	Description
id	INTEGER	ID of the dhcp_module resource
name	STRING	The name of the dhcp_module
slug	STRING	The unique reference string for this resource
type	STRING	Always 'dhcp_pool'
parent_id	INTEGER	The resource to which the dhcp_module is attached
category_id	INTEGER	The category to which this dhcp_module is associated

Attributes

Key	Type	Description
_dhcp_type	STRING	Either 'subnet' or 'host'. Determines whether this DHCP Pool is describing a Subnet or a Host.
_dhcp_pool_attributes	JSON	A JSON-encoded string containing all the specific configuration parameters which govern this DHCP Pool. An expansion of the JSON object is given below in the Data Attributes section.
_dhcp_ip_id	INTEGER	The id of the IPAM subnet or host which is assigned to this DHCP Pool.
_dhcp_links	INTEGER	The id of dhcp links.

Required Parameters

Name	Type	Example	Description
searchType	STRING	name	Type of search performing. Valid values are 'name', 'mac', and 'ip'.
searchValue	STRING	Blah	If searchType is 'IP': searchValue must be a valid IP address or IP Block. if searchType"is 'mac': searchValue must be a full or partial mac address. Not required if searchType is 'name', but is recommended to filter results.

Optional Parameters

Name	Type	Example	Description
selectOffset	INTEGER	10	Start number for the first result to show on the page to set pagination. For example, a selectOffset=15 with a selectCount=10 would return result numbers 15 through 25 on the page. Default value is 0 if not specified.
selectCount	INTEGER	5	The number of results to return on the page, if return results exceed the number of selectCount. Default value is 10
linkedTo	INTEGER	1422	The ID of the resource's DHCP link(s)

Data Attributes

_dhcp_attributes

Description: The _dhcp_attributes data attribute holds the specific settings used to generate a DHCP configuration file, place it on a server via SCP, and restart that server via a SSH session.

Example:

{"type":"ISC", "notes":"notes here", "username":"username", "port":"22", "config_test":"/etc/init.d/dhcpd configtest", "server_stop":"/etc/init.d/dhcpd stop", "server_start":"/etc/init.d/dhcpd start", "config_path":"/tmp/dhcpd.conf", "option_routers":"", "option_domain_name_servers":"", "option_domain_name":"", "authoritative":"1", "default_lease_time":"600", "max_lease_time":"7200", "local_port":"67", "log_facility":"local7", "password":"", "server_ip":"10.0.0.0", "freeLines":0}

Data Description

Name	Type	Description
type	STRING	The type of DHCP server being administered. Currently only 'ISC' is supported.
notes	STRING	Notes associated with this DHCP server
server_ip	STRING	The IP address of the DHCP server
username	STRING	The SSH username employed when transferring the DHCP configuration file to the server.
password	STRING	The SSH password employed when transferring the DHCP configuration file to the server.
port	INTEGER	The SSH port employed when transferring the DHCP configuration file to the server.
config_test	STRING	The command to test if a configuration file parses correctly. ex: /etc/init.d/dhcpd configtest
server_stop	STRING	The command to stop the DHCP server. ex: /etc/init.d/dhcpd stop
server_start	STRING	The command to start the DHCP server. ex: /etc/init.d/dhcpd start
config_path	STRING	Where to place the configuration file on the server.
authoritative	BOOL	Whether or not this DHCP server is authoritative.
default_lease_time	INTEGER	The default lease time for IPs distributed by this DHCP server.
max_lease_time	INTEGER	The max lease time for IPs distributed by this DHCP server.

local_port	INTEGER	The port on which this DHCP server listens
option_routers	STRING	The information which populates the "routers" option in the DHCP configuration
option_domain_ name_servers	STRING	The information which populates the "domain_name_servers" option in the DHCP configuration
option_domain_name	STRING	The information which populates the "domain_name" option in the DHCP configuration
log_facility	STRING	The log facility to which this DHCP Server sends its logging information
freeLines	INTEGER	As this system cannot hope to support all the thousands of different DHCP configurations, ProVision's DHCPv2 system includes a mechanism for adding "free lines" to the end of certain DHCP config sections so that administrators can customize their DHCP config file to their needs. The "freeLines" field indicates how many of these lines exist to be inserted after the general server definition section but before the subnets and hosts are enumerated.
freeLine#	STRING	Free line data to be inserted after the general server definition section but before the subnets and hosts are enumerated. There can be multiple instances of this attribute, numbered appropriately. ex: "freeLine1", "freeLine2", "freeLine3", etc. The number of freeLine# entries must match the number in the "freeLines" attribute.

_dhcp_pool_attributes

Description	A JSON-encoded string containing all the specific configuration parameters which govern this DHCP Pool.
Example:	{"mac":"ab:cc:de:ff:aa:bc","rangeStart":"13.0.0.0","rangeEnd":"13.0.0.255","freeLines":1,"freeLines1":"free line"}

Data Description

Name	Type	Description
mac	STRING	Only used when setting up a DHCP Host-type Pool. Holds the MAC address of the system to which the IP will be associated.
rangeStart	STRING	Only used when setting up a DHCP Subnet-type Pool. Holds the beginning of the Subnet range being allocated.
rangeEnd	STRING	Only used when setting up a DHCP Subnet-type Pool. Holds the end of the Subnet range being allocated.
freeLines	INTEGER	As this system cannot hope to support all the thousands of different DHCP configurations, ProVision's DHCPv2 system includes a mechanism for adding "free lines" to the end of certain DHCP config sections so that administrators can customize their DHCP config file to their needs. The "freeLines" field indicates how many of these lines exist to be inserted within the DHCP Pool declaration.
freeLine#	STRING	Free line data to be inserted after the general server definition section but before the subnets and hosts are enumerated. There can be multiple instances of this attribute, numbered appropriately. ex: "freeLine1", "freeLine2", "freeLine3", etc. The number of freeLine# entries must match the number in the "freeLines" attribute.

API Module - DNS

DNS Server Control

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

- DNS Server Control
  - get
  - add
  - delete
  - update
  - transferServer
  - transferSingle
- DNS Zone Control
  - get
  - search
  - update
  - add
  - delete
  - getRecordTypes
  - getFile
  - getDSFile
  - checkZone
  - getArchivedZone
- DNS Record Control
  - get
  - update
  - add
  - delete
  - switch
- Server-Zone Linkage
  - get
  - add
  - delete
- Name Server Control
  - get
  - add
  - delete
  - setDefault
  - orderUp
  - orderDown

get

URL	/api/v1/api.php?target=dnsServer&action=get
Description	If provided with an id, fetches that DNS Server from the database. If not, fetches a list of all stored DNS Servers
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Fetch Sucessful.","data":[{"id":"10","server":"mrbomasm-dns-4.onnet.net", "username":"user", "password":"vwvddp","port":"2600","customer_name":null,"transfer_type": "SCP"," remote_directory":"zones", "named_conf_path":"\/etc\/zones","active":"1","post_command":null," pre_command":null,"dyn_DNSSEC_contact":null, "powerdns_backend":"Bind","db_username":null," db_password":"(","db_port":null,"db_name":null, "server_type":"slave","SOA":null,"master_id":null,"options": "{\"customer_name\":\"\",\"server_type\":\"slave\" ,\"SOA\":\"\",\"remote_directory\":\"zones\", \" named_conf_path\":\"\\\/etc\\\/zones\", \"dyn_DNSSEC_contact\" :\"\",\"post_command\":\"\" ,\" pre_command\":\"\",\"powerdns_backend\":\"Bind\", \"db_username\":\"\",\"db_password\":\"(\",\"db_port\":\"\", \"db_name\":\"\",\"enable_views\":\"1\"}", "testID":"963","zoneCount":"8","views":"[{\"id\":\"1\", \"server_id\":\" 10\",\"name\":\"_6connectDefault\",\"extras\":\"[]\",\"description\":\"\",\"timestamp\":\"1371789181\"},{\"id\":\"3\", \"server_id\":\"10\",\"name\":\"internal\",\"extras\":\"[]\",\"description\":null,\"timestamp\":\"1374686650\"}]"}]}

ERROR:	{"success":0, "message":"error message"}

Data Detail:

Name	Type	Description
id	INTEGER	Server ID
server	STRING	Server Name
username	STRING	Login Name
password	CRYPT	Login Password
port	INTEGER	Port the Server listens on
zoneCount	INTEGER	The number of zones attached to this server.
options	JSON	The options entry is a JSON-encoded string containing a variety of server-specific configuration options. This string will vary widely by server type and configuration. The following are a selection of common settings.
transfer_type	STRING	Protocol used for transfer of DNS zones and records. Valid settings include SCP, PowerDNS, Secure64, Secure64Signer
server_type	STRING	Whether this server is a master or a slave server
SOA	STRING	The SOA entry to be used for zones on this server
remote_directory	STRING	The directory where SCP will place the zone files.
named_conf_path	STRING	The path to the zone files used within the named.conf file.
pre_command	STRING	The command executed on the server before the zones are transferred
post_command	STRING	The command executed on the server after the transfer is complete
enable_views	INTEGER	Whether or not Views are enabled
views	JSON	The views entry is a JSON-encoded string containing all the information about the Views attached to this server, if any exist.
id	INTEGER	The View ID
server_id	INTEGER	The ID of the server the View is attached to
name	STRING	The name of the View
description	STRING	A description of the View
timestamp	INTEGER	The UNIX timestamp of when the view was created.
extras	JSON	A JSON-encoded array of the extra attributes printed out in the view definition in the config file.

Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
id	INTEGER	15	The server id to fetch.

Example URL	/api/v1/api.php?target=dnsServer&action=get&id=15

add

URL	/api/v1/api.php?target=dnsServer&action=add
Description	Adds a new DNS Server
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Add Successful."} ERROR: {"success":0, "message":"error message"}

Required Parameters

Name	Type	Example	Description
server	STRING	dns.yourdomain.com	IP or FQDN of the DNS Server
password	STRING	password1	Login password for Server
transferType	STRING	SCP	Protocol used for transfer of DNS zones and records. Valid settings include SCP, PowerDNS, Secure64, Secure64Signer
serverType	STRING	Master	Values are 'Master' or 'Slave' only
displayName	STRING	Primary NS	The name displayed representing the DNS server, can be the same as server or different
SOA	STRING	ns1.6connect.com. hostmaster.6connect.com.	Server of Authority record for DNS server

Optional Parameters

These optional parameters vary according to what type of server is being configured.

Name	Type	Example	Description
customerName	STRING	/tmp/zones	Customer Name
remoteDirectory	STRING	/tmp/zones	Zone Directory on Server
port	INTEGER	22	Port for ssh or scp access to server
namedConfPath	STRING	/tmp	The path to the zone files used within the named.conf file.
preCommand	STRING	/path/to/stuff /precommand	Command to execute before zone transfer
postCommand	STRING	/path/to/stuff /postcommand	Command to execute after zone transfer
DNSSECContact	STRING	joeuser	For use with Dyn dns service
username	STRING	bobuser	Login name for Server
active	INTEGER	0	Values 0 or 1 only, sets the server to inactive on 0 value
masterId	INTEGER	53	Master server ID. If a server is a slave, masterId points to its master.
powerDNSBackend	STRING	Bind or MySQL	pDNS server backend type
dbDatabaseName	STRING	pdns_1	DB name for pDNS servers with MySQL powerDNSBackend type
dbPort	INTEGER	3306	Port for for pDNS servers with MySQL powerDNSBackend type
dbUsername	STRING	someuser	DB username for pDNS servers with MySQL powerDNSBackend type
dbPassword	STRING	somepass	DB password for pDNS servers with MySQL powerDNSBackend type

Example URL	/api/v1/api.php?target=dnsServer&action=add&server=dns.yourdomain.com&transferType=Secure64&displayName=PrimaryNS&serverType=master&password=password1&SOA=ns1.6connect.com.+hostmaster.6connect.com.

delete

URL	/api/v1/api.php?target=dnsServer&action=delete
Description	Deletes a DNS Server
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Delete Successful."} ERROR: {"success":0, "message":"error message"}
Required Parameters	**Name** / **Type** / **Example** / **Description** id / INTEGER / 5 / ID of server to delete
Optional Parameters	None
Example URL	/api/v1/api.php?target=dnsServer&action=delete&id=5

update

URL	/api/v1/api.php?target=dnsServer&action=update
Description	Updates an existing DNS Server with new information.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Update Successful."} ERROR: {"success":0, "message":"error message"}

Required Parameters

Name	Type	Example	Description
id	INTEGER	5	ID of server
server	STRING	dns.yourdomain.com	IP or FQDN of the DNS Server
SOA	STRING	ns1.6connect.com. hostmaster.6connect. com.	Server of Authority record for DNS server
transferType	STRING	SCP	Protocol used for transfer of DNS zones and records. Valid settings include SCP, PowerDNS, Secure64, Secure64Signer

Optional Parameters

These optional parameters vary according to what type of server is being configured.

Name	Type	Example	Description
active	INTEGER	0	Values 0 or 1 only, sets the server to inactive on 0 value
customerName	STRING	/tmp/zones	Customer Name
dbDatabaseName	STRING	pdns_1	DB name for pDNS servers with MySQL powerDNSBackend type
dbPassword	STRING	somepass	DB password for pDNS servers with MySQL powerDNSBackend type
dbPort	INTEGER	3306	Port for for pDNS servers with MySQL powerDNSBackend type
dbUsername	STRING	someuser	DB username for pDNS servers with MySQL powerDNSBackend type
displayName	STRING	Primary NS	The name displayed representing the DNS server, can be the same as server or different

DNSSECContact	STRING	joeuser	For use with Dyn dns service
enable_views	INTEGER	1	Whether or not Views are enabled. Valid values are '1' for enable or '0' for do not enable
masterId	INTEGER	53	Master server ID. If a server is a slave, masterId points to its master.
namedConfPath	STRING	/tmp	The path to the zone files used within the named.conf file.
password	STRING	password1	Login password for Server
port	INTEGER	22	Port for ssh or scp access to server
powerDNSBackend	STRING	Bind or MySQL	pDNS server backend type
postCommand	STRING	/path/to/stuff /postcommand	Command to execute after zone transfer
preCommand	STRING	/path/to/stuff /precommand	Command to execute before zone transfer
remoteDirectory	STRING	/tmp/zones	Zone Directory on Server
serverType	STRING	Master	Values are 'Master' or 'Slave' only
username	STRING	bobuser	Login name for Server

Example URL	/api.php?target=dnsServer&action=update&id=74&transferType=SCP&server=dns.yourdomain.com&SOA=ns1.6connect.com.+hostmaster.6connect.com.

transferServer

URL	/api/v1/api.php?target=dnsServer&action=transferServer
Description	Performs a full zone push on a DNS Server, executing pre and post commands, transferring files, and restarting services.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Transfer Successful."} ERROR: {"success":0, "message":"error message"}
Required Parameters	**Name** / **Type** / **Example** / **Description** push / INTEGER / 1 / The ID of the server to push zones to
Optional Parameters	None
Example URL	/api/v1/api.php?target=dnsServer&action=transferServer&push=1

transferSingle

URL	/api/v1/api.php?target=dnsServer&action=transferSingle
Description	Transfers a single Zone file to all its associated DNS Servers, along with updated server configurations. Performs pre and post commands on the target servers, transfers the zone file(s), and restarts services.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Updated Zone: $name.zone on $server via SCP"} ERROR: {"success":0, "message":"error message"}
Required Parameters	**Name** / **Type** / **Example** / **Description**

	zoneId | INTEGER | 35 | The ID of the zone to push
Optional Parameters	None
Example URL	/api/v1/api.php?target=dnsServer&action=transferSingle&zoneId=35

DNS Zone Control

get

URL	/api/v1/api.php?target=zone&action=get
Description	Accepts search criteria to retrieve a list of all matching DNS Zones and associated Records. Search can be performed on any combination of Zone and Record attributes.
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Search Successful.","data":[{"zoneId":"932","zoneName":"185.160.209.in-addr.arpa","zoneResourceId":"81", "zoneSerial":"2013040302","zoneRefresh":"28800","zoneRetry":"7200","zoneExpire":"604800","zoneMinimum":"86400","zoneSOA":null, "zoneTTL":"28800","zoneAutoCheck":"1","zoneEnableDNSSEC":null,"recordId":"154110","recordZoneId":"932", "recordHost": "185.160.209.inaddr.arpa.","recordType":"NS","recordValue":"auth01.veroxity.net.","recordDescription":null,"recordTTL":"28800", "recordOrdering":"1", "recordErrors":null,"assetId":"0","userCanCreate":0,"userCanDelete":1,"userCanUpdate":1}]}
ERROR:	{"success":0, "message":"error message"}

Data Detail:

Name	Type	Description
zoneId	INTEGER	The Id of the Zone entry. A single Zone entry might have multiple Records.
zoneName	STRING	The Zone name.
zoneResourceId	INTEGER	The resource Id associated with this Zone.
zoneSerial	INTEGER	Zone Serial.
zoneRefresh	INTEGER	Zone Refresh.
zoneRetry	INTEGER	Zone Retry.
zoneExpire	INTEGER	Zone Expire.
zoneMinimum	INTEGER	Zone Minimum.
zoneSOA	STRING	Zone SOA.
zoneTTL	STRING	Zone TTL.
zoneEnableDNSSEC	BOOL	Whether or not DNSSEC is enabled for this Zone.
zoneAutoCheck	BOOL	Whether or not this zone is configured to be automatically validated on load/edit.
recordId	INTEGER	The Id of this Record Entry. It is always included with its parent Zone.
recordHost	STRING	The Hostname of this Record.
recordType	STRING	The Record Type (MX,NS,A,PTR,etc)
recordValue	STRING	The Value of this Record.

recordDescription	STRING	A short description of this Record.
recordTTL	STRING	The TTL of this Record.
recordOrdering	INTEGER	The numerical order in which the record appears in the zone.
recordErrors	STRING	A string containing any detected problems with this record
userCanCreate	BOOL	Whether or not the user has DNS CREATE permissions on this zone's resource
userCanUpdate	BOOL	Whether or not the user has DNS UPDATE permissions on this zone's resource
userCanDelete	BOOl	Whether or not the user has DNS DELETE permissions on this zone's resource
unpagedRows	INTEGER	If pagination is used, this value will contain a total count of records had the pagination not been used.

Required Parameters: None

Optional Parameters

Name	Type	Example	Description
likeFlag	BOOL	1	When 1, string searches are done via LIKE with wildcards at both ends. When 0, strict comparison is used.
generalFlag	BOOL	1	When 1, searches over the provided parameters using OR. If 0 or omitted, uses AND.
selectCount	INTEGER	30	When supplied only returns the first X entries

Name	Type	Example	Description
zoneId	INTEGER	123	The Zone Id to search for.
zoneName	STRING	foo	The Zone Name to search for.
zoneResourceId	INTEGER	5	The Resource Id to search for.
zoneSerial	INTEGER	2012033001	The Zone Serial to search for.
zoneRefresh	INTEGER	36000	The Zone Refresh to search for.
zoneRetry	INTEGER	800	The Zone Retry to search for.
zoneExpire	INTEGER	6090000	The Zone Expire to search for.
zoneMinimum	INTEGER	10	The Zone Minimum to search for.
zoneSOA	STRING	200	The Zone SOA to search for.
zoneTTL	INTEGER	3600	The Zone TTL to search for.
zoneEnableDNSSEC	INTEGER	1	Search based on DNSSEC settings.
recordId	INTEGER	123	The Record Id to search for.
recordZoneId	INTEGER	123	The parent Zone to search for.
recordHost	STRING	@	The Record Host to search for.
recordType	STRING	NS	The Record Type to search for.
recordValue	STRING	ns1.dns.6connect.com.	The Record Value to search for.
recordDescription	STRING	Description	Search based on Record Description.
recordTTL	STRING	3600	The Record TTL to search for.

Example URL: /api/v1/api.php?target=zone&action=get&zoneId=123

search

URL	/api/v1/api.php?target=zone&action=search
Description	Accepts search criteria to retrieve a list of all matching DNS Zones but NO associated Records. Search can be performed on any combination of Zone and Record attributes.
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Search Successful.","data":[{"zoneId":"123","zoneName":"foobs.net","zoneResourceId":"483","zoneIpver":null,"zoneMask":null,"zoneSerial":"2012121803","zoneRefresh":null,"zoneRetry":null,"zoneExpire":null,"zoneMinimum":null,"zoneSOA":null,"zoneTTL":"3600","zoneEnableDNSSEC":"1","zoneLocalSigning":"1","assetId":"0","recordCount":"1","unpagedRows":"215"}]}
ERROR:	{"success":0, "message":"error message"}

Data Detail:

Name	Type	Description
zoneId	INTEGER	The Id of the Zone entry. A single Zone entry might have multiple Records.
zoneName	STRING	The Zone name.
zoneResourceId	INTEGER	The resource Id associated with this Zone.
zoneSerial	INTEGER	Zone Serial.
zoneRefresh	INTEGER	Zone Refresh.
zoneRetry	INTEGER	Zone Retry.
zoneExpire	INTEGER	Zone Expire.
zoneMinimum	INTEGER	Zone Minimum.
zoneSOA	STRING	Zone SOA.
zoneTTL	STRING	Zone TTL.
zoneEnableDNSSEC	BOOL	Whether or not DNSSEC is enabled for this Zone.
zoneAutoCheck	BOOL	Whether or not this zone is configured to be automatically validated on load/edit.
recordCount	INTEGER	How many records are associated with this zone.
userCanCreate	BOOL	Whether or not the user has DNS CREATE permissions on this zone's resource
userCanUpdate	BOOL	Whether or not the user has DNS UPDATE permissions on this zone's resource
userCanDelete	BOOl	Whether or not the user has DNS DELETE permissions on this zone's resource
unpagedRows	INTEGER	If pagination is used, this value will contain a total count of records had the pagination not been used.

Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
likeFlag	BOOL	1	When 1, string searches are done via LIKE with wildcards at both ends. When 0, strict comparison is used.
generalFlag	BOOL	1	When 1, searches over the provided paramenters using OR. If 0 or omitted, uses AND.
selectCount	INTEGER	30	When supplied only returns the first X entries
selectOffset	INTEGER	10	When supplied, only returns entries after record X
sortArray	JSON	{"zoneName":"desc","zoneMask":"asc"}	A JSON-encoded object containing a list of columns to sort on and the direction in which to sort. Any API variable may be used for sorting. Valid sort directions are ASC and DESC.

Name	Type	Example	Description
zoneId	INTEGER	123	The Zone Id to search for.
zoneName	STRING	foo	The Zone Name to search for.
zoneResourceId	INTEGER	5	The Resource Id to search for.
zoneSerial	INTEGER	2012033001	The Zone Serial to search for.
zoneRefresh	INTEGER	36000	The Zone Refresh to search for.
zoneRetry	INTEGER	800	The Zone Retry to search for.
zoneExpire	INTEGER	6090000	The Zone Expire to search for.
zoneMinimum	INTEGER	10	The Zone Minimum to search for.
zoneSOA	STRING	200	The Zone SOA to search for.
zoneTTL	INTEGER	3600	The Zone TTL to search for.
zoneEnableDNSSEC	INTEGER	1	Search based on DNSSEC settings.
recordId	INTEGER	123	The Record Id to search for.
recordZoneId	INTEGER	123	The parent Zone to search for.
recordHost	STRING	@	The Record Host to search for.
recordType	STRING	NS	The Record Type to search for.
recordValue	STRING	ns1.dns.6connect.com.	The Record Value to search for.
recordDescription	STRING	Description	Search based on Record Description.
recordTTL	STRING	3600	The Record TTL to search for.

Example URL	/api/v1/api.php?target=zone&action=search&zoneId=123

update

URL	/api/v1/api.php?target=zone&action=update
Description	First performs a search based on the submitted Zone and Record criteria, then performs an Update across those entries based on new values.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Update Successful."} ERROR: {"success":0, "message":"error message"}
Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
likeFlag	BOOL	1	When 1, string searches are done via LIKE with wildcards at both ends. When 0, strict comparison is used.
generalFlag	BOOL	1	When 1, searches over the provided parameters using OR. If 0 or omitted, uses AND.

Name	Type	Example	Description
searchZoneId	INTEGER	123	The Zone Id to search for.
searchZoneName	STRING	foo	The Zone Name to search for.
searchZoneResourceId	INTEGER	5	The Resource Id to search for.

searchZoneSerial	INTEGER	2012033001	The Zone Serial to search for.
searchZoneRefresh	INTEGER	36000	The Zone Refresh to search for.
searchZoneRetry	INTEGER	800	The Zone Retry to search for.
searchZoneExpire	INTEGER	6090000	The Zone Expire to search for.
searchZoneMinimum	INTEGER	10	The Zone Minimum to search for.
searchZoneSOA	STRING	200	The Zone SOA to search for.
searchZoneTTL	INTEGER	3600	The Zone TTL to search for.
searchZoneEnableDNSSEC	INTEGER	1	Search based on DNSSEC settings.
searchRecordId	INTEGER	123	The Record Id to search for.
searchRecordHost	STRING	@	The Record Host to search for.
searchRecordType	STRING	NS	The Record Type to search for.
searchRecordValue	STRING	ns1.dns.6connect.com.	The Record Value to search for.
searchRecordDescription	STRING	Description	Search based on Record Description.
searchRecordTTL	STRING	3600	The Record TTL to search for.

Name	Type	Example	Description
updateZoneName	STRING	foo	The Zone name to replace into the searched rows.
updateZoneSerial	INTEGER	2012033001	The Zone Serial to replace into the searched rows.
updateZoneRefresh	INTEGER	36000	The Zone Refresh to replace into the searched rows.
updateZoneRetry	INTEGER	800	The Zone Retry to replace into the searched rows..
updateZoneExpire	INTEGER	6090000	The Zone Expire to replace into the searched rows.
updateZoneMinimum	INTEGER	10	The Zone Minimum to replace into the searched rows.
updateZoneSOA	STRING	200	The Zone SOA to replace into the searched rows.
updateZoneTTL	INTEGER	3600	The Zone TTL to replace into the searched rows.
updateZoneEnableDNSSEC	INTEGER	1	Update DNSSEC Settings.
updateRecordHost	STRING	@	The Record Host to replace into the searched rows.
updateRecordType	STRING	NS	The Record Type to replace into the searched rows.
updateRecordValue	STRING	ns1.dns. 6connect.com.	The Record Value to replace into the searched rows.
updateRecordDescription	STRING	Description	Update Record Descriptions.
updateRecordTTL	STRING	3600	The Record TTL to replace into the searched rows.
updateZoneAutoCheck	BOOL	1	Whether or not this zone is configured to be automatically validated on load/edit.

Name	Type	Example	Description
recordZoneId	INTEGER	123	The parent zone ID

Example URL	/api/v1/api.php?target=zone&action=update&searchZoneId=123&updateZoneExpire=6090000

add

URL	/api/v1/api.php?target=zone&action=add
Description	Adds a new DNS Zone.

Returns

Examples:

SUCCESSFUL:	{"success":1,"message":"Add Successful.","data":123}
ERROR:	{"success":0, "message":"error message"}

Data Detail:

Name	Type	Description
data	INTEGER	The Id of the new Zone entry.

Required Parameters

Name	Type	Example	Description
zoneName	STRING	254.221.67.in-addr.arpa	The name for the new Zone.

Optional Parameters

Name	Type	Example	Description
likeFlag	BOOL	1	When 1, string searches are done via LIKE with wildcards at both ends. When 0, strict comparison is used.
zoneIpver	STRING	IPv6	The IP Version.
zoneLocalSigning	BOOL	1	Whether or not this zone should be signed by the ProVision server when DNSSEC is enabled. If set to false, ProVision will deliver the zone unsigned to the DNS server and the signing / updating process should be triggered by the post-push command
zoneSerial	INTEGER	2012033001	Serial for the new Zone.
zoneRefresh	INTEGER	36000	Refresh for the new Zone.
zoneRetry	INTEGER	800	Retry for the new Zone.
zoneExpire	INTEGER	6090000	Expire for the new Zone.
zoneMinimum	INTEGER	10	Minimum for the new Zone.
zoneSOA	STRING	200	SOA for the new Zone.
zoneTTL	STRING	3600	TTL for the new Zone.
zoneEnableDNSSEC	INTEGER	1	Whether or not this new zone uses DNSSEC.

Example URL

/api/v1/api.php?target=zone&action=add&zoneName=254.221.67.in-addr.arpa&zoneSerial=2012033001

delete

URL

/api/v1/api.php?target=zone&action=delete

Description

Performs a search over the Zones and Records dataset and deletes all found Zones, plus all associated Records of those Zones.

Returns

Examples:

SUCCESSFUL:	{"success":1,"message":"Zones and Associated Records Deleted."}
ERROR:	{"success":0, "message":"error message"}

Required Parameters

No specific parameter is required, however, one or more optional parameters must be used for a successful return

Optional Parameters

Name	Type	Example	Description

deleteZoneId	INTEGER	123	The Zone Id to search for.
deleteZoneName	STRING	foo	The Zone Name to search for.
deleteZoneResourceId	INTEGER	5	The Resource Id to search for.
deleteZoneSerial	INTEGER	2012033001	The Zone Serial to search for.
deleteZoneRefresh	INTEGER	36000	The Zone Refresh to search for.
deleteZoneRetry	INTEGER	800	The Zone Retry to search for.
deleteZoneExpire	INTEGER	6090000	The Zone Expire to search for.
deleteZoneMinimum	INTEGER	10	The Zone Minimum to search for.
deleteZoneSOA	STRING	200	The Zone SOA to search for.
deleteZoneTTL	INTEGER	3600	The Zone TTL to search for.
deleteZoneEnableDNSSEC	INTEGER	1	Search based on DNSSEC settings.
deleteRecordId	INTEGER	123	The Record Id to search for.
deleteRecordHost	STRING	@	The Record Host to search for.
deleteRecordType	STRING	NS	The Record Type to search for.
deleteRecordValue	STRING	ns1.dns.6connect.com.	The Record Value to search for.
deleteRecordDescription	STRING	Description	Search based on Record Description.
deleteRecordTTL	STRING	3600	The Record TTL to search for.
deleteRecordZoneId	INTEGER	123	The parent zone ID

Example URL	/api/v1/api.php?target=zone&action=delete&deleteZoneId=123

getRecordTypes

URL	/api/v1/api.php?target=zone&action=getRecordTypes
Description	Returns a list of all Record Types allowed by the system.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Search Successful.","data":[{"recordType":"A"},{"recordType":"AAAA"},{"recordType":"MX"},{"recordType":"CNAME"},{"recordType":"PTRG"},{"recordType":"NS"},{"recordType":"TXT"},{"recordType":"DNSKEY"},{"recordType":"SRV"},{"recordType":"DS"},{"recordType":"TEST"}]} ERROR: {"success":0, "message":"error message"} **Data Detail:** **Name** / **Type** / **Description** recordType / STRING / A Record Type
Required Parameters	None
Optional Parameters	None
Example URL	/api/v1/api.php?target=zone&action=getRecordTypes

getFile

URL	/api/v1/api.php?target=zone&action=getFile&zoneId=50
Description	Returns a fully written zone file. If one does not exist, returns false.
Returns	A Zone File
Required Parameters	

Name	Type	Example	Description
zoneId	INTEGER	50	The Id of the zone to retrieve.
format	ENUMERATED	'html' or ''	If html, the zone file will be formatted for display via a web browser. If blank or omitted, the zone file will be formatted for display in a file system.
unsigned	BOOL	1	For a DNSSEC-enabled zone, determines whether or not the system retrieves the signed or unsigned zone file. Ignored for non-DNSSEC zones.

Optional Parameters	None
Example URL	/api/v1/api.php?target=zone&action=getFile&zoneId=50&zoneId=50&format=html&unsigned=1

getDSFile

URL	/api/v1/api.php?target=zone&action=getDSFile
Description	Returns a fully written zone DS key file. If one does not exist, returns false.
Returns	A Zone DS Key File
Required Parameters	

Name	Type	Example	Description
zoneId	INTEGER	50	The Id of the zone whose DS keys are to be retrieved.

Optional Parameters	None
Example URL	/api/v1/api.php?target=zone&action=getDSFile&zoneId=50

checkZone

URL	/api/v1/api.php?target=zone&action=checkZone
Description	Runs a zone file through Named checkzone
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"No errors found."}
ERROR:	{"success":0,"message":"21: ignoring out-of-zone data (veggie.com) 22: ignoring out-of-zone data (veggie.com) dns_rdata_fromtext: 23: near '2001:db8:': bad IPv6 address dns_rdata_fromtext: 24: near '1.2.3.': bad dotted quad dns_rdata_fromtext: 25: near '2001::db8::\/32': bad IPv6 address "}

Required Parameters	

Name	Type	Example	Description
zoneId	INTEGER	50	The Id of the zone to check.

Optional Parameters	None
Example URL	/api/v1/api.php?target=zone&action=checkZone&zoneId=50

getArchivedZone

URL	/api/v1/api.php?target=zone&action=getArchivedZone
Description	Searches for all archived versions of the a zone. Zones are archived every time changes are pushed to their DNS Server.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Search Successful.","data":[{"zoneArchiveId" :"2768","zoneId":"1227", "zoneArchiveTimestamp":"1375298692", "zoneArchiveFingerprint":" d060e59d69606326d80b2e55b50f0bc9","zoneName":"6connect.com","zoneIpver":null, "zoneMask":null," zoneSerial": "2013073105","zoneRefresh":"14400","zoneRetry":"2000","zoneExpire":"604800", "zoneMinimum":"3600", "zoneSOA":null,"zoneTTL":"3600","zoneEnableDNSSEC":"1", "zoneResourceId":" 1013","zonePreviousViewLinkage":"[]"}]} ERROR: {"success":0, "message":"error message"} **Data Detail:**

Name	Type	Description
zoneId	INTEGER	The Id of the Zone entry to find archived versions of.
zoneArchiveId	INTEGER	The ID of the Archive Entry
zoneArchiveTimestamp	INTEGER	A timestamp marking when this zone was archived.
zoneArchiveFingerprint	STRING	A hash value identifying this zone. Used for comparing versions.
zoneName	INTEGER	Zone Name.
zoneSerial	INTEGER	Zone Serial.
zoneRefresh	INTEGER	Zone Refresh.
zoneRetry	INTEGER	Zone Retry.
zoneExpire	INTEGER	Zone Expire.
zoneMinimum	INTEGER	Zone Minimum.
zoneSOA	STRING	Zone SOA.
zoneTTL	INTEGER	Zone TTL.
zoneEnableDNSSEC	STRING	Whether or not this version had DNSSEC enabled.
zoneResourceId	STRING	Zone Resource ID
zonePreviousViewLinkage	JSON	A JSON-encoded array of views this zone was linked to.

Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
zoneId	INTEGER	123	The Zone Id to search for.
zoneArchiveId	INTEGER	123	The Zone Archive Id
zoneArchiveTimestamp	INTEGER	2012033001	The Zone Archive Timestamp
fetchArchiveFile	BOOL	1	Whether or not to return the full Zone file with the result set..

Example URL	/api/v1/api.php?target=zone&action=getArchivedZone&zoneId=123

DNS Record Control

get

URL	/api/v1/api.php?target=record&action=get
Description	Accepts search criteria to retrieve a list of all matching DNS Records. Search can be performed on any combination of Zone and Record attributes.

Returns

Examples:

SUCCESSFUL:	{"success":1,"message":"Search Successful.","data":[{"recordId":"30894","recordZoneId":"229","recordHost":"@","recordType":"NS","recordValue":"ns1.domain.com.","recordDescription":"","recordTTL":""}]}
ERROR:	{"success":0, "message":"error message"}

Data Detail:

Name	Type	Description
recordId	INTEGER	The ID of this Record Entry. It is always included with its parent Zone.
recordZoneId	INTEGER	The ID of this Record's parent Zone.
recordHost	STRING	The Hostname of this Record.
recordType	STRING	The Record Type (MX,NS,A,PTR,etc)
recordValue	STRING	The Value of this Record.
recordDescription	STRING	A short description of this Record.
recordTTL	STRING	The TTL of this Record.

Required Parameters: None

Optional Parameters

Name	Type	Example	Description
likeFlag	BOOL	1	When 1, string searches are done via LIKE with wildcards at both ends. When 0, strict comparison is used.
selectCount	INTEGER	30	When supplied only returns the first X entries
selectOffset	INTEGER	10	When supplied, only returns entries after record X

Name	Type	Example	Description
recordId	INTEGER	123	The Record ID to search for.
recordZoneId	INTEGER	123	The parent Zone to search for.
recordHost	STRING	@	The Record Host to search for.
recordType	STRING	NS	The Record Type to search for.
recordValue	STRING	ns1.dns.6connect.com.	The Record Value to search for.
recordDescription	STRING	Description	Search based on Record Description.
recordTTL	STRING	3600	The Record TTL to search for.

Name	Type	Example	Description
zoneId	INTEGER	123	The Zone Id to search for.
zoneName	STRING	foo	The Zone Name to search for.

zoneResourceId	INTEGER	5	The Resource Id to search for.
zoneCustName	STRING	foo	The Customer Name to search for.
zoneIpver	STRING	IPv6	The IP Version to search for.
zoneSerial	INTEGER	2012033001	The Zone Serial to search for.
zoneRefresh	INTEGER	36000	The Zone Refresh to search for.
zoneRetry	INTEGER	800	The Zone Retry to search for.
zoneExpire	INTEGER	6090000	The Zone Expire to search for.
zoneMinimum	INTEGER	10	The Zone Minimum to search for.
zoneSOA	STRING	200	The Zone SOA to search for.
zoneTTL	INTEGER	3600	The Zone TTL to search for.
zoneEnableDNSSEC	INTEGER	1	Search based on DNSSEC settings.

Example URL	/api/v1/api.php?target=record&action=get&selectCount=30&zoneId=123

update

URL	/api/v1/api.php?target=record&action=update
Description	First performs a search based on the submitted Zone and Record criteria, then performs an Update across those entries based on new values.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Update Successful."} ERROR: {"success":0, "message":"error message"}
Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
likeFlag	BOOL	1	When 1, string searches are done via LIKE with wildcards at both ends. When 0, strict comparison is used.
generalFlag	BOOL	1	When 1, searches over the provided parameters using OR. If 0 or omitted, uses AND.

Name	Type	Example	Description
searchZoneId	INTEGER	123	The Zone ID to search for.
searchZoneName	STRING	foo	The Zone Name to search for.
searchZoneCustId	INTEGER	5	The Customer ID to search for.
searchZoneSerial	INTEGER	2012033001	The Zone Serial to search for.
searchZoneRefresh	INTEGER	36000	The Zone Refresh to search for.
searchZoneRetry	INTEGER	800	The Zone Retry to search for.
searchZoneExpire	INTEGER	6090000	The Zone Expire to search for.
searchZoneMinimum	INTEGER	10	The Zone Minimum to search for.
searchZoneSOA	STRING	200	The Zone SOA to search for.
searchZoneTTL	INTEGER	3600	The Zone TTL to search for.
searchZoneEnableDNSSEC	INTEGER	1	Search based on DNSSEC settings.

searchRecordId	INTEGER	123	The Record ID to search for.
searchRecordHost	STRING	@	The Record Host to search for.
searchRecordType	STRING	NS	The Record Type to search for.
searchRecordValue	STRING	ns1.dns.6connect.com.	The Record Value to search for.
searchRecordDescription	STRING	Description	Search based on Record Description.
searchRecordTTL	STRING	3600	The Record TTL to search for.
searchZoneResourceId	INTEGER	5	The Resource Id to search for.
searchRecordZoneId	INTEGER	123	The Zone ID of the Record to search for.

Name	Type	Example	Description
updateZoneName	STRING	foo	The Zone name to replace into the searched rows.
updateZoneSerial	INTEGER	2012033001	The Zone Serial to replace into the searched rows.
updateZoneRefresh	INTEGER	36000	The Zone Refresh to replace into the searched rows.
updateZoneRetry	INTEGER	800	The Zone Retry to replace into the searched rows..
updateZoneExpire	INTEGER	6090000	The Zone Expire to replace into the searched rows.
updateZoneMinimum	INTEGER	10	The Zone Minimum to replace into the searched rows.
updateZoneSOA	STRING	200	The Zone SOA to replace into the searched rows.
updateZoneTTL	INTEGER	3600	The Zone TTL to replace into the searched rows.
updateZoneEnableDNSSEC	INTEGER	1	Update DNSSEC Settings.
updateRecordHost	STRING	@	The Record Host to replace into the searched rows.
updateRecordType	STRING	NS	The Record Type to replace into the searched rows.
updateRecordValue	STRING	ns1.dns. 6connect.com.	The Record Value to replace into the searched rows.
updateRecordDescription	STRING	Description	Update Record Descriptions.
updateRecordTTL	STRING	3600	The Record TTL to replace into the searched rows.
updateZoneResourceId	INTEGER	5	The Resource Id to replace into the searched rows.
updateZoneAutoCheck	BOOL	1	Whether or not this zone is configured to be automatically validated on load/edit.

Example URL	/api/v1/api.php?target=record&action=update&searchZoneId=123&updateZoneTTL=3600

add

URL	/api/v1/api.php?target=record&action=add
Description	Adds a new Record to a supplied Zone.
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Add Successful.","data":123}
ERROR:	{"success":0, "message":"error message"}

Data Detail:

Name	Type	Description
data	INTEGER	The ID of the new Record entry.

Required Parameters

Name	Type	Example	Description
newRecordZoneId	INTEGER	123	The Zone ID of the new Record.
newRecordHost	STRING	@	New Host Name.
newRecordType	STRING	PTR	New Record Type.
newRecordValue*	STRING	123	New Record Value.
*newRecordValue required only for certain Record Types			

Optional Parameters

Name	Type	Example	Description
likeFlag	BOOL	1	When 1, string searches are done via LIKE with wildcards at both ends. When 0, strict comparison is used.
newRecordDescription	STRING	Description.	Notes for the Record.
newRecordTTL	INTEGER	3600	Record TTL.

Example URL: /api/v1/api.php?target=record&action=add&newRecordZoneId=123&newRecordHost=@host&newRecordType=PTR&newRecordTTL=3600

delete

URL: /api/v1/api.php?target=record&action=delete

Description: Performs a search over the Zones and Records dataset and deletes all found Records, but leaves their parent Zones intact.

Returns

Examples:

SUCCESSFUL:	{"success":1,"message":"Deletion Successful."}
ERROR:	{"success":0, "message":"error message"}

Required Parameters: None

Optional Parameters

Name	Type	Example	Description
deleteZoneId	INTEGER	123	The Zone ID to search for.
deleteZoneName	STRING	foo	The Zone Name to search for.
deleteZoneCustId	INTEGER	5	The Customer ID to search for.
deleteZoneIpver	STRING	IPv6	The IP Version to search for.
deleteZoneSerial	INTEGER	2012033001	The Zone Serial to search for.
deleteZoneRefresh	INTEGER	36000	The Zone Refresh to search for.
deleteZoneRetry	INTEGER	800	The Zone Retry to search for.
deleteZoneExpire	INTEGER	6090000	The Zone Expire to search for.
deleteZoneMinimum	INTEGER	10	The Zone Minimum to search for.
deleteZoneSOA	STRING	200	The Zone SOA to search for.
deleteZoneTTL	INTEGER	3600	The Zone TTL to search for.
deleteZoneEnableDNSSEC	INTEGER	1	Search based on DNSSEC settings.
deleteRecordId	INTEGER	123	The Record ID to search for.
deleteRecordHost	STRING	@	The Record Host to search for.

	deleteRecordType	STRING	NS	The Record Type to search for.
	deleteRecordValue	STRING	ns1.dns.6connect.com.	The Record Value to search for.
	deleteRecordDescription	STRING	Description	Search based on Record Description.
	deleteRecordTTL	STRING	3600	The Record TTL to search for.
	deleteZoneResourceId	INTEGER	5	The Resource Id to search for.
	deleteZoneCustName	STRING	foo	The Customer Name to search for.
Example URL	/api/v1/api.php?target=record&action=delete&deleteZoneName=foo			

switch

URL	/api/v1/api.php?target=record&action=switch
Description	Switches the order of two record entries.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Record Moved."} ERROR: {"success":0, "message":"error message"}
Required Parameters	**Name** / **Type** / **Example** / **Description** moveWhichId / INTEGER / 123 / The Record Id to be moved. moveAfterId / INTEGER / 42 / The Id of the Record the first Record is to be moved after.
Optional Parameters	None
Example URL	/api/v1/api.php?target=record&action=switch&moveWhichId=123&moveAfterId=42

Server-Zone Linkage

get

URL	/api/v1/api.php?target=zoneLinkage&action=get
Description	Searches for Server-Zone Linkages. If no search parameters are supplied, all linkages are returned.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"2 rows retrieved.","data":[{"id":"285","zoneId":"64","serverId":"1","serverName":"173.164.182.169","serverType":"SCP","serverMasterType":"master","zoneName":"bind.com","resourceId":"483"},{"id":"287","zoneId":"371","serverId":"1","serverName":"173.164.182.169","serverType":"SCP","serverMasterType":"master","zoneName":"132.235.198.in-addr.arpa","resourceId":"577"}} ERROR: {"success":0, "message":"error message"} **Data Detail:** **Name** / **Type** / **Description** id / INTEGER / The Linkage Id. zoneId / INTEGER / The ZoneId involved in this link.

serverId	INTEGER	The ServerId involved in this link.
serverName	STRING	The server name
serverType	STRING	The server transfer type
serverMasterType	STRING	Whether this server is a master or a slave.
zoneName	STRING	The zone name
resourceId	INTEGER	The Resource Id the Zone is attached to.

Required Parameters	None

Optional Parameters

Name	Type	Example	Description
id	INTEGER	15	Fetches the linkage with the matching id.
serverId	INTEGER	15	Fetches all linkages with the matching serverId.
zoneId	INTEGER	15	Fetches all linkages with the matching zoneId.

Example URL	/api/v1/api.php?target=zoneLinkage&action=get&id=15

add

URL	/api/v1/api.php?target=zoneLinkage&action=add
Description	Adds a new link between a DNS Server and a Zone

Returns

Examples:

SUCCESSFUL:	{"success":1,"message":"Link Added."}
ERROR:	{"success":0, "message":"error message"}

Required Parameters

Name	Type	Example	Description
serverId	INTEGER	16	The DNS Server Id.
zoneId	INTEGER	105	The Zone Id.
serverSlave	BOOL	1	Whether or not this zone is a master or a slave on the linked server. Values are: 1 for slave, 0 for master.

Optional Parameters	None
Example URL	/api/v1/api.php?target=zoneLinkage&action=add&serverId=16&zoneId=105&serverSlave=0

delete

URL	/api/v1/api.php?target=zoneLinkage&action=delete
Description	Deletes a link between a DNS Server and a Zone

Returns

Examples:

SUCCESSFUL:	{"success":1,"message":"Link Deleted."}
ERROR:	{"success":0, "message":"error message"}

Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
id	INTEGER	15	Fetches the linkage with the matching id.
serverId	INTEGER	15	Fetches all linkages with the matching serverId.
zoneId	INTEGER	15	Fetches all linkages with the matching zoneId.

Example URL	/api/v1/api.php?target=zoneLinkage&action=delete

Name Server Control

get

URL	/api/v1/api.php?target=nameServer&action=get
Description	Fetches a list of all stored Name Servers
Returns	**Examples:**

SUCCESSFUL:	*{"success":1,"message":"Fetch Sucessful.","data":[{"id":"1","nameserver":"ns1.dns.6connect.net","add_to_zones_default":"1","ordering":"10","uses":"34"},{"id":"10","nameserver":"ns2.dns.6connect.net","add_to_zones_default":"1","ordering":"11","uses":"46"},{"id":"9","nameserver":"ns4.dns.6connect.net","add_to_zones_default":"1","ordering":"14","uses":"12"},{"id":"3","nameserver":"ns3.dns.6connect.net","add_to_zones_default":"1","ordering":"15","uses":"46"}]}*
ERROR:	*{"success":0, "message":"error message"}*

Data Detail:

Name	Type	Description
id	INTEGER	Server ID
nameserver	STRING	Server Name
add_to_zones_default	BOOL	Whether or not this is a default server.
ordering	INTEGER	Display order
uses	INTEGER	How many zones have been assigned to this NameServer

Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
default	INTEGER	1	Set server as default

Example URL	/api/v1/api.php?target=nameServer&action=get&default=1

add

URL	/api/v1/api.php?target=nameServer&action=add
Description	Adds a new DNS Server
Returns	**Examples:**

	SUCCESSFUL: *{"success":1,"message":"Add Successful."}* ERROR: *{"success":0, "message":"error message"}*
Required Parameters	**Name** | **Type** | **Example** | **Description** newServer | STRING | ns.yourdomain.com | Name of the NameServer
Optional Parameters	None
Example URL	/api/v1/api.php?target=nameServer&action=add&newServer=ns.yourdomain.com

delete

URL	/api/v1/api.php?target=nameServer&action=delete
Description	Deletes a NameServer
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Server Deleted."}* ERROR: *{"success":0, "message":"error message"}*
Required Parameters	**Name** | **Type** | **Example** | **Description** id | INTEGER | 5 | ID of server to delete.
Optional Parameters	None
Example URL	/api/v1/api.php?target=nameServer&action=delete&id=5

setDefault

URL	/api/v1/api.php?target=nameServer&action=setDefault
Description	Default NameServers have all new zones added to them as they are created. Multiple NameServers can be classified as Default.
Returns	**Examples:** SUCCESSFUL: *{"success":1, "message":"Success."}* ERROR: *{"success":0, "message":"error message"}*
Required Parameters	**Name** | **Type** | **Example** | **Description** id | INTEGER | 5 | ID of server to modify. value | INTEGER | 1 | 1 = Default, 0 = Normal
Optional Parameters	None
Example URL	/api/v1/api.php?target=nameServer&action=setDefault&id=3&value=1

orderUp

URL	/api/v1/api.php?target=nameServer&action=orderUp
Description	Swaps the index order of the targeted NameServer with that of the one above it.
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Reordering Successful."}* ERROR: *{"success":0, "message":"error message"}*
Required Parameters	**Name** / **Type** / **Example** / **Description** id / INTEGER / 5 / ID of server to modify.
Optional Parameters	None
Example URL	/api/v1/api.php?target=nameServer&action=orderUp&id=3

orderDown

URL	/api/v1/api.php?target=nameServer&action=orderDown
Description	Swaps the index order of the targeted NameServer with that of the one below it.
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Reordering Successful."}* ERROR: *{"success":0, "message":"error message"}*
Required Parameters	**Name** / **Type** / **Example** / **Description** id / INTEGER / 5 / ID of server to activate.
Optional Parameters	None
Example URL	/api/v1/api.php?target=nameServer&action=orderDown&id=5

API Module - IPAM

IP Address Management (IPv4 and IPv6)

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

- IP Address Management (IPv4 and IPv6)
  - IP Block Management
    - Get
    - Add
    - Update
    - Delete
    - Add Tag
    - Delete Tag
    - Smart Assign
    - Direct Assign
    - Unassign
    - Aggregate
    - Split
    - Scan Block
    - Get Scan Results
    - Get Options
    - Get VLAN
    - Get Resource Hierarchy
  - IP Subnets List
    - Get Subnet List
  - IP Tag List
    - Get Tags List
    - Add Tag To List
    - Delete Tag From List
  - IP Regions List
    - Get Regions List
    - Add Region To List
    - Get Utilization
    - Get Host Utilization
  - Holding Tank
    - Override Holding
    - Process Holding Tank
  - Reports
    - Mask Report
- IPAM SWIP Calls:
  - Deassign
  - Get RIR List
  - Simple Reassign
- IPAM API Calls Subject to Change:
  - Get Attribute List

IP Block Management

Get

URL	/api/v1/api.php?target=ipam&action=get
Description	Returns a list of IP blocks. Use optional parameters to filter the list. If multiple parameters are specified, only blocks matching all parameters will be returned.
Returns	**Examples:** SUCCESSFUL: *{ "success": 1, "message": "1 blocks found. ", "data": [{ "id": 5890, "type": "ipv4", "top_aggregate": null, "cidr":*

	"192.168.0.0\/24", "formatted_ip": "192.168.0.0\/24", "address": "3232235520", "end_address": "3232235775", "mask": 24, "child1": null, "child2": null, "is_assigned": 0, "is_swipped": 0, "is_aggregate": 1, "custid": 81, "resource_id": 81, "resource_name": "Available", "last_updated_time": null, "description": null, "parent": null, "rir": "1918", "lir_id": null, "notes": null, "generic_code": null, "code": null, "region": "SFO", "vlan": 100, "arin_net_id": null, "arin_cust_id": null, "org_id": null, "arin_swip_time": null, "assigned_time": null, "asn": null, "allowSubAssignments": false, "permissions": { "permissionIPAMRead": "1", "permissionIPAMUpdate": "1", "permissionIPAMCreate": "1", "permissionSWIP": "1", "permissionAdmin": "1" }, "range": "192.168.0.0 - 192.168.0.255", "tags": ["Customer", "PTP"] }]}
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters: None

Optional Parameters

Name	Type	Example	Description
address	INTEGER	1125449728	IP address of the block in decimal format
asn	INTEGER	1000	Filters blocks based on their ASN
allowSubAssignments	BOOL	true	Filters blocks based on wether they allow sub-assignments or not. Acceptable values: "true" or "false"
block	STRING	213.37.29.0 /24	CIDR block description
code	STRING	Code X	User-defined block code as defined in Admin-IPAM settings: Generic Code Per Block Name
endAddress	INTEGER	1125453823	End IP address of the block in decimal format
id	INTEGER	1234	The ID of the block
includeAttributes	BOOL	true	Allows loading and display of the attributes for all of the blocks in the collection.
isAggregate	BOOL	true	Indicates if the block has been split into children or not. A value of 'true' will return blocks with no children.
isAssigned	BOOL	true	Acceptable values: "true" or "false"
isSwipped	BOOL	true	Acceptable values: "true" or "false"
lastUpdateTime	DATETIME	=2015-8-19 21:08:54	SQL Datetime format, prefaced by an "=" for exact time updated, "=>" for blocks updated after the given time, or "=<" for blocks updated before the given time.
lirId	INTEGER	101	The numeric ID of an LIR resource the block should be linked to
mask	INTEGER	24	Integer bitmask
notes	STRING	note123	Returns blocks with exact matches in the notes field against the provided "notes" string.
region	STRING	SFO	The value from the list of name/value pairs which make up the list of available regions
resourceHolderId	STRING	`cust-001`	(**Deprecated**: Use resourceQuery instead) A custom ID which can be used to link resources in the 6Connect database back to your organization.
resourceId	INTEGER	1234	The ID of the resource the block is assigned to
resourceQuery	JSON	{"parent_id": 15}	A JSON object representing a valid resource query. Any parameters that can be used for a Resource GET API call can be used. Use of the resourceQuery parameter will return blocks assigned to any of the resources returned by that query.
rir	STRING	ARIN	Acceptable values: ARIN, RIPE, APNIC, AfriNIC, LACNIC, 1918
search	STRING	192.168	If a search term is provided, all IPAM fields including assigned Resource Holder name will be checked with a LIKE comparison to find

			matching blocks
selectCount	INTEGER	50	# of blocks to get
selectOffset	INTEGER	25	Offset for results set; useful for paging (e.g. selectCount = 50, selectOffset = 100 would return the 3rd page of 50 results)
sortField	STRING	cidr	Attribute to sort blocks by. Accepable values: cidr, mask, rir, vlan, code, updateTime
sortOrder	INTEGER	ASC	ASC or DESC
tags	STRING	customer,vpn	Comma-separated list of tags to filter by. If used in conjunction with 'search', performs the search operation and then filters results by the provided tag. Use with tagsMode to specify filter approach.
tagsMode	STRING	"strict"," exclude", "intersection", or "union".	Denotes how the "tags" parameter is handled: "strict" - matches only blocks that have the exact set of tags of specified. "exclude" - matches only blocks which are note tagged with any of the blocks specified. "intersection" - matches any blocks which has all of the tags. "union" - matches all blocks which has any one of the tags. If not otherwise specified, tagsMode defaults to "intersection".
topAggregateId	INTEGER	1234	The ID of the aggregate block to which the block belongs
type	STRING	"ipv4" or "ipv6"	IP type
vlan	INTEGER	123	VLAN for the block

Example URL	/api/v1/api.php?target=ipam&action=get&rir=ARIN&tags=customer,vpn

Add

URL	/api/v1/api.php?target=ipam&action=add
Description	Adds an IPv4 or IPv6 block

Returns

Examples:

SUCCESSFUL	*{"success":1,"message":"Block 192.168.0.0/24 (12345) added", "id":12345, "data":{ "id":12345, "cidr": 192.168.0.0/24", ...} }*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
block	STRING	213.37.29.0/24	CIDR block description
rir	STRING	ARIN	Acceptable values: ARIN, RIPE, APNIC, AfriNIC, LACNIC, 1918

Optional Parameters

Name	Type	Example	Description
allowDuplicate	BOOL	true	Allow the creation of duplicate blocks. The default behavior is to reject duplicates.
allowSubAssignments	BOOL	true	Does the block allow sub-assignments? If the block is assigned and allowSubAssignments is "true", children split from this block will be able to be assigned to different resources. Acceptable values: "true" or "false"

	asn	INTEGER	1000	ASN for the block
	code	STRING	Code X	User-defined block code as defined in Admin-IPAM settings: Generic Code Per Block Name
	region	STRING	SFO	The value from the list of name/value pairs which make up the list of available regions
	resourceId	INTEGER	1234	The ID of the resource the block is assigned to
	tags	STRING	customer, vpn	Comma-separated list of tags
	vlan	INTEGER	123	VLAN for the block
Example URL	/api/v1/api.php?target=ipam&action=add&block=213.37.29.0/24&rir=ARIN			

Update

URL	/api/v1/api.php?target=ipam&action=update
Description	Updates detail data about an IP block.

Returns

Examples:

SUCCESSFUL	SINGLE BLOCK	*{"success":1,"message":"Block 192.168.0.0/24 (12345) updated", "data":{ "id":12345, "cidr": 192.168.0.0/24", ...} }*
SUCCESSFUL	MULTIPLE BLOCKS	*{"success":1,"message":"3 blocks updated", "data":[{ "id":12345, "cidr":192.168.0.0/24", ...}, {"id":12346, "cidr", "192.168.0.1/32", ...}] }*
ERROR		*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Allow Multiple	Description
id*	INTEGER	125	Yes	ID of the IP block. Multiple block IDs can be specified in a comma-separated list.
block*	STRING	192.0.0.0 /24	Yes	CIDR or the block. Multiple CIDRs can be specified in a comma-separated list.
*Either block or id can be used, but only one must be provided				

Optional Parameters

Name	Type	Example	Description
allowSubAssignments	BOOL	true	Does the block allow sub-assignments? If the block is assigned and allowSubAssignments is "true", children split from this block will be able to be assigned to different resources. Acceptable values: "true" or "false"
asn	INTEGER	1000	ASN for the block
code	STRING	Code X	Arbitrary user-defined block code
lirId	INTEGER	101	The numeric ID of an LIR resource the block should be linked to
notes	STRING	Words	Misc. Notes
region	STRING	Chicago, IL	The region this IP block is assigned to.
propagate	BOOL	true	Propagates all attribute values to any smaller child blocks of the block being updated. ***Available in version 5.1.0***
rir	STRING	ARIN	Acceptable values: ARIN, RIPE, APNIC, AfriNIC, LACNIC, 1918

	tags	STRING	Customer, vpn	Comma-separated list of tags
	tags_action	STRING	replace	What action to take on the supplied tags. This action must be taken in conjunction with the tags parameter. Valid settings for tags_action are: replace, add, delete. When tags_action is set to 'replace', all tags on an IP block are replaced with those
	vlan	NUMERIC	123	VLAN for the block

Example URL	/api/v1/api.php?target=ipam&action=update&block=192.0.0.0/24&notes=Notes_here

Delete

URL	/api/v1/api.php?target=ipam&action=delete
Description	Deletes an aggregate block
Returns	Examples

SUCCESSFUL	*{"success":1,"message":"Aggregate deleted: 192.168.0.0/24", "data":{ "id":12345, "cidr":192.168.0.0/24", ...} }*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
block*	STRING	213.37.29.0/24	CIDR block description
id*	INTEGER	125	ID of the IP block
*Either block or id can be used, but only one must be provided			

Optional Parameters

Name	Type	Example	Description
force	BOOL	true	Forces the aggregate block to be deleted even if the block is split or contains sub blocks which are assigned. The default behavior is to reject attempts to delete blocks which have been split or are assigned.

Example URL	/api/v1/api.php?target=ipam&action=delete&block=213.37.29.0/24

Add Tag

URL	/api/v1/api.php?target=ipam&action=addTag
Description	Adds a tag to an IP block.
Returns	**Examples:**

SUCCESSFUL	*{ "success":1,"message":"Tag Added.", "data":{ "id":12345, "cidr":192.168.0.0/24", ...} }*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
id*	INTEGER	125	ID of the block
block*	STRING	192.0.0.0/24	CIDR of the block
*Either block or id can be used, but only one must be provided			
tag	STRING	Customer	The tag to add

Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=addTag&id=125&tag=Customer

Delete Tag

URL	/api/v1/api.php?target=ipam&action=deleteTag
Description	Removes a tag from an IP block.
Returns	**Examples:** SUCCESSFUL: *{ "success":1,"message":"Tag Removed.", "data":{ "id":12345, "cidr":192.168.0.0/24", ...} }* ERROR: *{ "success":0, "message":"error message" }*
Required Parameters	**Name** / **Type** / **Example** / **Description** id* / INTEGER / 125 / ID of the block block* / STRING / 192.0.0.0/24 / CIDR of the block *Either block or id can be used, but only one must be provided tag / STRING / Customer / The tag to delete
Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=deleteTag&id=125&tag=Customer

Smart Assign

URL	/api/v1/api.php?target=ipam&action=smartAssign
Description	Selects a block based on supplied parameters (rir, tags, mask size, etc.) and assigns it to a Resource Holder.
Returns	**Examples:** SUCCESSFUL: *{ "success":1,"message":"Assigned 192.168.0.0/24 to Resource (1234) via Smart Assign", "id":12345, "data":{ "id":12345, "cidr":192.168.0.0/24", ...} }* ERROR: *{ "success":0, "message":"error message" }*
Required Parameters	**Name** / **Type** / **Example** / **Description** mask / INTEGER / 24 / The size of the block to be assigned rir / STRING / ARIN / Acceptable values: ARIN, RIPE, APNIC, AfriNIC, LACNIC, 1918 resourceId* / INTEGER / 1234 / Integer ID of the resource to assign the block to resourceQuery* / JSON / `{"custom_id":"cust-001"}` / A JSON object representing a valid resource query. Any parameters that can be used for a Resource GET API call can be used. Use of the resourceQuery parameter will return blocks assigned to any of the resources returned by that query. *Either resourceId or resourceQuery can be used, but only one must be provided resourceHolderId / STRING / `cust-001` / (**Deprecated**: Use resourceQuery instead) A custom ID which can be used to link resources in the 6Connect database back to your organization.

	type	STRING	"IPv4" or "IPv6"	The type of block to assign

Optional Parameters*

Name	Type	Example	Description
assignedResourceId	STRING	"123" or "ignore"	The ID of the resource the block is assigned to, or the string "ignore". If assignedResourceId is set to "ignore", then a matching IP block is selected from the Available pool or any sub-assignable block on any resource.
code	STRING	Code X	Arbitrary user-defined block code
lirId	INTEGER	101	The ID of an LIR resource
region	STRING	Ashburn	Region to assign from
tags	STRING	customer,vpn	Comma separated string of tags. Matches blocks which have at least the set of tag specified by this parameter
tagsMode	STRING	"strict"," exclude", "intersection", or "union".	Denotes how the "tags" parameter is handled: "strict" - matches only blocks that have the exact set of tags of specified. "exclude" - matches only blocks which are note tagged with any of the blocks specified. "intersection" - matches any blocks which has all of the tags. "union" - matches all blocks which has any one of the tags. If not otherwise specified, tagsMode defaults to "intersection".
vlan	INTEGER	1023	VLAN designated to a given block

*Additional or fewer "optional" parameters may be required in order to result in a successful assignment, depending on the attributes of available blocks.

Example URL: /api/v1/api.php?target=ipam&action=smartAssign&mask=24&type=IPv4&resourceId=250&rir=ARIN

Direct Assign

URL: /api/v1/api.php?target=ipam&action=directAssign

Description: Assigns a block to an Resource Holder

Returns

Examples:

SUCCESSFUL	SINGLE BLOCK	*{ "success":1,"message":"Assigned 192.168.0.0/24 to Resource (1234)", "id":12345, "data":{ "id":12345, "cidr":192.168.0.0/24", ...} }*
SUCCESSFUL	MULTIPLE BLOCKS	*{ "success":1,"message":"Assigned 5 blocks to Resource (1234) via Direct Assign", "data":{ "ids":[12345, 12346, 12347, ...] } }*
ERROR		*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
block*	STRING	213.37.29.0/24	CIDR block description
id*	INTEGER	125	ID of the IP block, comma separated list of ids, or json encoded array of ids
*Either block or id can be used, but only one must be provided			
resourceHolderId**	STRING	`cust-001`	(**Deprecated**: Use resourceQuery instead)

			A custom ID which can be used to link resources in the 6Connect database back to your organization.
resourceId**	INTEGER	1234	Integer ID of the resource to assign the block to
resourceQuery**	JSON	`{"custom_id":"cust-001"}`	A JSON object representing a valid resource query. Any parameters that can be used for a Resource GET API call can be used. Use of the resourceQuery parameter will return blocks assigned to any of the resources returned by that query.
**Either resourceId, resourceQuery, or resourceHolderId can be used, but only one must be provided			

Optional Parameters*

Name	Type	Example	Description
code	STRING	Code X	Arbitrary user-defined block code
lirId	INTEGER	101	The ID of an LIR resource
region	STRING	Ashburn	Region to assign from
rir	STRING	ARIN	Acceptable values: ARIN, RIPE, APNIC, AfriNIC, LACNIC, 1918
tags	STRING	customer,vpn	Comma separated string of tags. Matches blocks which have at least the set of tag specified by this parameter
tagsMode	STRING	"strict","exclude", "intersection", or "union".	Denotes how the "tags" parameter is handled: "strict" - matches only blocks that have the exact set of tags of specified. "exclude" - matches only blocks which are note tagged with any of the blocks specified. "intersection" - matches any blocks which has all of the tags. "union" - matches all blocks which has any one of the tags. If not otherwise specified, tagsMode defaults to "intersection".
vlan	INTEGER	1023	VLAN designated to a given block

*Additional or fewer "optional" parameters may be required in order to result in a successful assignment, depending on the attributes of available blocks.

Example URL: /api/v1/api.php?target=ipam&action=directAssign&block=213.37.29.0/24&resourceId=1234

Unassign

URL: /api/v1/api.php?target=ipam&action=unassign

Description: Reclaims the specified block to be reassigned in the future

Returns

Examples:

SUCCESSFUL	*{ "success":1,"message":"192.168.0.0/24 unassigned", "id":12345, "data":{ "id":12345, "cidr":192.168.0.0/24", ...} }*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
block*	STRING	213.37.29.0/24	CIDR block description
id*	INTEGER	125	ID of the IP block
*Either block or id can be used, but only one must be provided			

Optional Parameters	

Name	Type	Example	Description
skipHolding	BOOL	true	If set to true (skipHolding=true) then the holding tank is skipped. If set to false, or not included, normal holding tank rules apply. Acceptable values: "true" or "false"

Example URL	/api/v1/api.php?target=ipam&action=unassign&block=213.37.29.0/24

Aggregate

URL	/api/v1/api.php?target=ipam&action=aggregate
Description	Aggregates a selected block to the mask specified. If no mask specified, re-aggregates blocks to next parent. IE. calling aggregate on a /25 will aggregate both children back to the parent /24. All child blocks must be Available for aggregation to succeed.
Returns	**Examples:**

SUCCESSFUL	`{"success":1,"message":"10.2.0.128\/25 aggregated into 10.2.0.0\/24","id":16326}`
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
id*	INTEGER	125	ID of the IP block.
block*	STRING	213.37.29.0/24	CIDR block.
*Either block or id can be used, but only one must be provided			

Optional Parameters

Name	Type	Example	Description
autoAggregateToMask	INTEGER	24	All blocks and IPs smaller than this netmask will be aggregated.
ignoreAssignments	BOOL	TRUE	If the ignoreAssignment flag is not set the aggregation operation will fail if any children beneath the supplied autoAggregateToMask are assigned or otherwise unavailable. If this option is set, it will unassign blocks prior to reaggregation.

Example URL	/api/v1/api.php?target=ipam&action=aggregate&id=125&autoAggregateToMask=24

Split

URL	/api/v1/api.php?target=ipam&action=split
Description	Splits a selected block to the mask specified. If no mask specified, it split blocks to next child. IE. calling aggregate on a /24 will split both parent to the child /25s. All parent blocks must be Available, or have Allow Sub Assignments on for a split to succeed.
Returns	**Examples:**

SUCCESSFUL	`{"success":1,"message":"10.1.0.0\/24 split into 10.1.0.0\/25 and 10.1.0.128\/25","data":{"child1":23441 ,"child2":23451}}`
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description

	id*	INTEGER	125	ID of the IP block.
	block*	STRING	213.37.29.0/24	CIDR block.
	*Either block or id can be used, but only one must be provided			

Optional Parameters

Name	Type	Example	Description
autoSplitToMask	INTEGER	24	Auto aggregate the block back to this mask size. Note all blocks up this mask size must be Available or call will fail.
autoSplitLimit	INTEGER	4	A number the power of 2 (^2).

Example URL

/api/v1/api.php?target=ipam&action=split&block=213.37.29.0/24&autoSplitLimit=4

Scan Block

URL

/api/v1/api.php?target=ipam&action=scanBlock

Description

Initiates an asynchronous ping (ICMP) scan of the target block specified. Results of the scan can be checked with get.

Returns

Examples:

SUCCESSFUL	`{"success":1,"message":"Ping scan started for 8.8.8.0\/27"}`
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
id*	INTEGER	125	ID of the IP block.
block*	STRING	213.37.29.0/24	CIDR block.
*Either block or id can be used, but only one must be provided			

Optional Parameters

None

Example

/api/v1/api.php?target=ipam&action=scanBlock&block=213.37.29.0/24

Get Scan Results

URL

/api/v1/api.php?target=ipam&action=getScanResults

Description

Initiates an asynchronous ping (ICMP) scan of the target block specified. Results of the scan can be checked with get

Returns

Examples:

SUCCESSFUL	`{"success":1,"data":{"block":"8.8.8.0\/27","date":"07\/14\/2014 11:07:10",` `"data":[{"address":"8.8.8.8","host":"google-public-dns-a.google.com","status":"Up"}],"status":"completed","hostsScanned":4,"activeHosts":4}}`
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
block	STRING	213.37.29.0/24	CIDR block.

Optional

None

Parameters	
Example	/api/v1/api.php?target=ipam&action=getScanResults&block=213.37.29.0/24

Get Options

URL	/api/v1/api.php?target=ipam&action=getOptions
Description	Returns a list of options available for the block
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Options for 14.0.0.0\/25 (125)","options":{"actions":["aggregate"],"templates":[{"name":"Auto Split","masks":[26,27,28,29,30,31,32]}]}} ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	

Name	Type	Example	Description
id	INTEGER	125	ID of the IP block

Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=getOptions&id=125

Get VLAN

URL	/api/v1/api.php?target=ipam&action=getVlan
Description	Returns the VLAN for the block
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Found VLAN 1002 (14.0.0.0\/25)","data":{"id":125,"type":"ipv4","top_aggregate":81532,"cidr":"14.0.0.0\/25","formatted_ip":"14.0.0.0\/25","address":"234881024","end_address":"234881151","mask":25,"netmask":"255.255.255.128","child1":null,"child2":null,"is_assigned":0,"is_swipped":0,"is_aggregate":1,"custid":402,"resource_id":402,"resource_name":"6connect Labz","last_updated_time":"2015-01-22 12:30:37","description":null,"parent":81532,"rir":"ARIN","lir_id":"1062","notes":"Test Notes","generic_code":"Datacenter2","code":"Datacenter2","region":"ATL","region_name":"Atlanta, GA","vlan":1002,"arin_net_id":null,"arin_cust_id":null,"org_id":null,"arin_swip_time":null,"assigned_time":"2015-01-14 10:30:31","asn":"143","allowSubAssignments":true,"permissions":{"permissionIPAMRead":"1","permissionIPAMUpdate":"1","permissionIPAMCreate":"1","permissionIPAMDelete":"1","permissionSWIP":"1","permissionAdmin":"1"},"range":"14.0.0.0 - 14.0.0.127","tags":["Customer"]}} ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	

Name	Type	Example	Description
id*	INTEGER	125	ID of the IP block
block*	STRING	213.37.29.0/24	CIDR block.
*Either block or id can be used, but only one must be provided			

Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=getVlan&id=125

Get Resource Hierarchy

URL	/api/v1/api.php?target=ipam&action=getResourceHierarchy&id=79124
Description	Returns the Parent Resource and Parent Resource id for the provided block.
Returns	**Examples:** SUCCESSFUL: {"success":"1","data":[{"id":"4208","name":"a6connectEntry"}]} ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	**Name** / **Type** / **Example** / **Description** id / INTEGER / 125 / ID of the IP block
Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=getResourceHierarchy&id=79124

IP Subnets List

Get Subnet List

URL	/api/v1/api.php?target=ipam&action=getSizes
Description	Returns the IPv4 or IPv6 Subnet Lists
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Lookup was successful","data":["36","48","56","64","126","127","128"]}* ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	**Name** / **Type** / **Example** / **Description** size / INTEGER / "4" or "6" / The IP Subnet list to return - "4" for IPv4 subnets, or "6" for IPv6 subnets.
Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=getSizes&size=6

IP Tag List

Get Tags List

URL	/api/v1/api.php?target=ipam&action=getTagList
Description	Returns a list of all valid IP Tags in the database.
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Tags Retrieved. ","data":["ActiveE DIA","Colo DIA","Customer","DSL","Fiber DIA","GPON DIA","Infra","Inhouse","LAN","LBIntf","POP","PTP","Prod","VPN","WEBHOST","Cable","Internal"]}* ERROR: *{'success':0, 'message':'error message'}*

Add Tag To List

URL	/api/v1/api.php?target=ipam&action=addTagToList
Description	Adds a tag to the IPAM tag list
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Tag Added."}* ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	**Name** / **Type** / **Example** / **Description** newTag / STRING / Loopback C / The value to add to the list of name/value pairs which make up the list of available regions
Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=addTagToList&newTag=Loopback C

Delete Tag From List

URL	/api/v1/api.php?target=ipam&action=deleteTagFromList
Description	Deletes a tag from the IPAM tag list
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Tag Deleted."}* ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	**Name** / **Type** / **Example** / **Description** tag / STRING / tag123 / The name of the tag to be deleted.
Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=deleteTagFromList&tag=tag123

IP Regions List

Get Regions List

URL	/api/v1/api.php?target=ipam&action=getRegionList
Description	Returns a list of all valid Regions in the database.
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Regions Retrieved.","data":[{"value":"ANY","name":"Any Region"},{"value":"ASH1","name":"Ashburn, VA"},{"value":"BOS","name":"Boston, MA"},{"value":"CHI","name":"Chicago, IL"},{"value":"DAL","name":"Dallas, TX"},{"value":"DEN","name":"Denver, CO"},{"value":"FRKT","name":"Frankfurt, DE"},{"value":"LON1","name":"London, UK"},{"value":"MIA","name":"Miami, FL"},{"value":"PAR","name":"Paris, FR"},{"value":"SFO","name":"San Francisco, CA"},{"value":"SEA","name":"Seattle, WA"},{"value":"Tokyo","name":"Tokyo"},{"value":"Singapore","name":"Singapore"},{"value":"Jakarta","name":"Jakarta"}]}* ERROR: *{'success':0, 'message':'error message'}*

Add Region To List

URL	/api/v1/api.php?target=ipam&action=addRegionToList
Description	Adds a region to the IPAM region list.
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Region Added."}* ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	**Name** | **Type** | **Example** | **Description** newRegion | STRING | SFO | The value to add to the list of name/value pairs which make up the list of available regions
Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=addRegionToList&newRegion=SFO

Utilization

Get Utilization

URL	/api/v1/api.php?target=ipam&action=utilization
Description	Gets the utilization percentages for a specific ip block or ip block and mask combination.
Returns	**Examples:** SUCCESSFUL: { "success": 1, "totalBlocks": 1, "totalHosts": "256", "hostsAssigned": 0, "hostsAllocated": "256", "hostsAvailable": "256", "hostsInHolding": 0, "availablePercentage": "100.00", "assignedPercentage": "0.00", "allocatedPercentage": "100.00", "inHoldingPercentage": "0.00", "resources": [{ "id": 351, "name": "Customer 1", "type": "entry", "hosts": "256",

	"blocks": "1", "percentage": "100.00" }], "blocksAssigned":0, "blocksAllocated": 1, "blocksAvailable": "1", "blocksInHolding": null, "blocksAssignedPercentage": "0.00", "blocksAllocatedPercentage": "100.00", "blocksAvailablePercentage": "100.00", "blocksInHoldingPercentage": "0.00" }
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
block*	STRING	213.37.29.0/24	CIDR block description
id*	INTEGER	125	ID of the IP block
*Either block or id can be used, but only one must be provided			

Optional Parameters

Name	Type	Example	Description
mask	INTEGER	24	The specific mask size to retrieve utilization for. If using this parameter, the id parameter should be the id of the aggregate.

Example URL	/api/v1/api.php?target=ipam&action=utilization&id=125

Get Host Utilization

URL	/api/v1/api.php?target=ipam&action=getHostUtilization
Description	Gets the host utilization statistics with support for filters.

Returns

Examples:

SUCCESSFUL	{ "success": 1, "totalHosts": "256", "hostsAssigned": 0, "hostsAllocated": "256", "hostsAvailable": "256", "hostsInHolding": 0, "availablePercentage": "100.00", "assignedPercentage": "0.00",

	"allocatedPercentage": "100.00",
	"inHoldingPercentage": "0.00",
	"resources": [{
	"id": 351,
	"name": "Customer 1",
	"type": "entry",
	"hosts": "256",
	"blocks": "1",
	"percentage": "100.00"
	}]
	}

ERROR	*{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
type	STRING	"ipv4" or "ipv6"	IP type

Optional Parameters

Name	Type	Example	Multiple Values	Description
code	STRING	"code-1"	Yes	User-defined block code as defined in Admin-IPAM settings: Generic Code Per Block Name
region	STRING	"SFO"	Yes	Region to assign from
rir	STRING	ARIN	No	Acceptable values: ARIN, RIPE, APNIC, AfriNIC, LACNIC, 1918
tags	STRING	"Customer"	Yes	Comma separated string of tags
vlan	INTEGER	1000	Yes	VLAN designated to a given block

NOTE: to filter using multiple values, pass the values as a JSON-encoded string representation of an array.

For example, to get utilization data for multiple tags, you could use the following URL:

/api/v1/api.php?target=ipam&action=getHostUtilization&type=ipv4&tags=["Customer","PTP"]

Example URL: /api/v1/api.php?target=ipam&action=getHostUtilization&type=ipv4&tags=["Customer","PTP"]&region=SMF

Holding Tank

Override Holding

URL	/api/v1/api.php?target=ipam&action=processHoldingTank
Description	Overrides holding for a specific block, returning the block to available status
Returns	**Examples:**

SUCCESSFUL	*{"success":1,"message":"15.15.15.128\/30 unassigned and returned to resource a6connectEntry","id":79134,"data":{"id":79134,"type":"ipv4","top_aggregate":79121,"cidr":"15.15.15.128\/30","formatted_ip":"15.15.15.128\/30","address":"252645248","end_address":"252645251","mask":30,"netmask":"255.255.255.252","child1":null,"child2":null,"is_assigned":0,"is_swipped":0,"is_aggregate":1,"custid":4208,"resource_id":4208,"*

	resource_name":"a6connectEntry","last_updated_time":"2017-11-20 12:35:08","description":null,"parent":79132,"rir":"ARIN","lir_id":null,"notes":null,"generic_code":null,"code":null,"region":"STL","region_name":"St. Louis","vlan":null,"arin_net_id":null,"arin_cust_id":null,"org_id":null,"arin_swip_time":null,"assigned_time":"2017-11-20 12:35:08","asn":null,"allowSubAssignments":true,"permissions":{"permissionIPAMRead":"1","permissionIPAMUpdate":"1","permissionIPAMCreate":"1","permissionIPAMDelete":"1","permissionSWIP":"1","permissionAdmin":"1"},"range":"15.15.15.128 - 15.15.15.131","tags":[],"attributes":{"custody_chain":"[]"}}}
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters

Name	Type	Example	Description
block*	STRING	213.37.29.0/24	CIDR block description
id*	INTEGER	125	ID of the IP block
*Either block or id can be used, but only one must be provided			

Optional Parameters: None.

Example URL: /api/v1/api.php?target=ipam&action=overrideHolding&block=213.37.29.0/24&preview=true

Process Holding Tank

URL: /api/v1/api.php?target=ipam&action=processHoldingTank

Description: Processes the Holding Tank, returning held blocks to available status

Returns

Examples:

SUCCESSFUL	{"success":1,"message":"1 IPv4 and 0 IPv6 blocks would be moved to the available pool. ","data":[{"id":77712,"type":"ipv4","top_aggregate":77552,"cidr":"23.92.0.64\/26","formatted_ip":"23.92.0.64\/26","address":"391905344","end_address":"391905407","mask":26,"netmask":"255.255.255.192","child1":null,"child2":null,"is_assigned":0,"is_swipped":0,"is_aggregate":1,"custid":188,"resource_id":188,"resource_name":"6connect holding","last_updated_time":"2014-10-29 11:25:41","description":null,"parent":77682,"rir":"ARIN","lir_id":"451","notes":null,"generic_code":null,"code":null,"region":"PHX","region_name":"Phoenix, AZ","vlan":null,"arin_net_id":null,"arin_cust_id":null,"org_id":null,"arin_swip_time":null,"assigned_time":"2014-10-29 11:20:34","asn":null,"allowSubAssignments":false,"permissions":{"permissionIPAMRead":"1","permissionIPAMUpdate":"1","permissionIPAMCreate":"1","permissionIPAMDelete":"1","permissionSWIP":"1","permissionAdmin":"1"},"range":"23.92.0.64 - 23.92.0.127","tags":["Customer","DSL"]}]}
ERROR	*{'success':0, 'message':'error message'}*

Required Parameters: None

Optional Parameters

Name	Type	Example	Description
preview	BOOL	true	Acceptable values: "true" or "false" If set to "true", returns a list of blocks that would be removed from the holding tank, but does not complete the process holding tank action. If set to "false", processes the holding tank and returns a list of blocks returned to available status.

Example URL: /api/v1/api.php?target=ipam&action=processHoldingTank&preview=true

Reports

Mask Report

URL	/api/v1/api.php?target=ipam&action=maskReport
Description	Returns a JSON report breakdown of by-mask use statistics
Returns	**Examples:** SUCCESSFUL: {"success":1,"data":{"IPv4":{"total":576,"available":21,"assigned":555,"holding":0,"allocated":446,"prefixes":{"32":{"assigned_percentage":91.666666,"holding_percentage":0,"available_percentage":8.333333,"allocated_percentage":0,"total":12,"available":1,"assigned":11,"holding":0,"allocated":0},"31":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":30,"total":20,"available":0,"assigned":20,"holding":0,"allocated":6},"30":{"assigned_percentage":50,"holding_percentage":0,"available_percentage":50,"allocated_percentage":0,"total":8,"available":4,"assigned":4,"holding":0,"allocated":0},"29":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":20,"total":40,"available":0,"assigned":40,"holding":0,"allocated":8},"28":{"assigned_percentage":66.666666,"holding_percentage":0,"available_percentage":33.333333,"allocated_percentage":33.333333,"total":48,"available":16,"assigned":32,"holding":0,"allocated":16},"27":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":50,"total":64,"available":0,"assigned":64,"holding":0,"allocated":32},"26":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":100,"total":128,"available":0,"assigned":128,"holding":0,"allocated":128},"25":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":100,"total":256,"available":0,"assigned":256,"holding":0,"allocated":256}},"assigned_percentage":96.354166,"holding_percentage":0,"available_percentage":3.645833,"allocated_percentage":77.430555},"IPv6":{"total":16777216,"available":0,"assigned":16777216,"holding":0,"allocated":0,"prefixes":{"41":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":0,"total":16777216,"available":0,"assigned":16777216,"holding":0,"allocated":0}},"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":0}}} ERROR: *{ "success":0, "message":"error message" }*
Required Parameters	None
Optional Parameters	**Name** / **Type** / **Example** / **Description** resource_id / INTEGER / 1234 / Integer value of a Resource ID. If provided, the system will display an IPAM Mask Usage report limited to blocks associated with a single resource. tags / STRING / "Customer" / Comma separated list of tags. If provided, limits the IPAM Mask Usage report to certain tags (standard tag mode). regions / STRING / "DEN" / Comma separated list of regions. If provided, limits the IPAM Mask Usage Report to blocks associated with the provided region(s).
Example URL	/api/v1/api.php?target=ipam&action=maskReport&regions=DEN

IPAM SWIP Calls:

Deassign

URL	/api/v1/api.php?target=ipam&action=deassign
Description	Performs a SWIP deassignment for the indicated IPAM block.
Returns	**Examples:** SUCCESSFUL: *{ "success":1,"message":"success message" }* ERROR: *{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
blockId	INTEGER	1234	ID of the block to deassign
block	STRING	67.221.241.0/24	the CIDR of the block being de-assigned
resourceId	INTEGER	1234	ID of resource representing the customer to deassign
lirId	INTEGER	1234	The ProVision id of the LIR which is performing the de-assignment
entityHandle	STRING	CONNE-81	The Org ID for the LIR.

Optional Parameters

Name	Type	Example	Description
netName	STRING	6CONN-67-221-241-0-24	Optional name for the network to override the default. The default net name will be created using the Net Name Prefix and IP address for the block.

Example URL: /api/v1/api.php?target=ipam&action=deassign&resourceId=1234&blockId=1234&lirId=1234&entityHandle=CONNE-81&block=67.221.241.0/24&netName=6CONN-67-221-241-0-24

Get RIR List

URL: /api/v1/api.php?target=ipam&action=getRIRList

Description: Returns a list of all valid RIRs in the database.

Returns

Examples:

SUCCESSFUL	*{"success":1,"message":"RIRs Retrieved.","data":[{"value":"ARIN","name":"ARIN"},{"value":"1918","name":"1918"},{"value":"AfriNIC","name":"AfriNIC"},{"value":"APNIC","name":"APNIC"},{"value":"LACNIC","name":"LACNIC"},{"value":"RIPE","name":"RIPE"},{"value":"1918-SJC","name":"1918-SJC"}]}*
ERROR	*{'success':0, 'message':'error message'}*

Simple Reassign

URL: /api/v1/api.php?target=ipam&action=simpleReassign

Description: ARIN SWIP - simple reassign. Creates an ARIN customer record for the assigned resource and reassigns the block to the ARIN customer record.

Returns

Examples:

SUCCESSFUL	*{ "success":1,"message":"Sent ARIN SWIP with action simpleReassign for 67.221.244.0/28 for Acme, Message: Success" }*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
blockId	INTEGER	1234	ID of the block to reassign
resourceId	INTEGER	1234	ID of resource representing the customer to reassign to
lirId	INTEGER	1234	The ProVision id of the LIR to use for reassignment
entityHandle	STRING	CONNE-81	The Org ID for the LIR.

Optional

Parameters	Name	Type	Example	Description
	netName	STRING	NET-ACME-67-221-244-0-28	Optional name for the network to override the default. The default net name will be created using the Net Name Prefix and IP address for the block.
Example URL	/api/v1/api.php?target=ipam&action=simpleReassign&resourceId=121&blockId=31559&lirId=95&entityHandle=CONNE-81&&netName=NET-ACME-67-221-244-0-28			

IPAM API Calls Subject to Change:

Calls below this point are subject to change, and are not recommended for use in production code.

Get Attribute List

URL	/api/v1/api.php?target=ipam&action=getAttributeLists
Description	Returns a list of attributes
Returns	**Examples:** SUCCESSFUL: {"asns":[],"masks":["24"],"rirs":["1918"],"lirs":[],"tags":["DHCP"],"codes":[],"vlans":[],"regions":["Quito"],"resources":[{"id":"1302","name":"Quito Lab 1","slug":"quito-lab-1","type":"dhcp_pool","parent_id":"1","category_id":null,"attr":{"_dhcp_type":"subnet","_dhcp_pool_attributes":"{\"mac\":\"\",\"rangeStart\":\"10.8.0.0\",\"rangeEnd\":\"10.8.0.255\",\"freeLines\":0}","_dhcp_ip_id":"125"}}]} ERROR: *{'success':0, 'message':'error message'}*

Required Parameters	Name	Type	Example	Description
	id	INTEGER	125	ID of the IP block

Optional Parameters	None
Example URL	/api/v1/api.php?target=ipam&action=getAttributeLists&id=125

API Module - LIR

LIR Management

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

- LIR Management
  - Get
  - Delete
  - Add
  - Update

Get

URL	/api/v1/api.php?target=lir&action=get
Description	Returns a list of LIRs
Returns	**Examples:**

SUCCESSFUL

```
{
    "success": 1,
    "message": "2 objects found",
    "data": [
        {
            "id": "100",
            "name": "RIPE Test LIR",
            "slug": "ripe-test-lir",
            "entities": [
                {
                    "mnt_by": "mntner@email.com"
                    "mnt_by_password": "password",
                    "admin_c": "test-admin-c",
                    "tech_c": "test-tech-c",
                    "api_key": null
                }
            ],
            "rir": "RIPE"
        },
        {
            "id": "101",
            "name": "ARIN Test LIR",
            "slug": "arin-test-lir",
            "entities": [
                {
                    "org_handle": "TEST-10",
                    "admin_poc": "TEST-ARIN",
                    "net_poc": "TEST-ARIN",
                    "abuse_poc": "",
                    "net_name_prefix": "PRFX",
                    "api_key": "API-XXXX-YYYY-ZZZZ-1234"
                }
            ],
            "rir": "ARIN",
            "asn": "1000"
        }
    ]
}
```

ERROR

```
{
    "success":0,
    "message":"error message"
}
```

Example URL	/api/v1/api.php?target=lir&action=get

Delete

URL	/api/v1/api.php?target=lir&action=delete&id=<ID>
Description	Deletes an LIR

Returns	**Examples:**
	SUCCESSFUL
	`{ "success": 1, "message": "LIR deleted." }`
	ERROR
	`{ "success":0, "message":"error message" }`

Example URL	/api/v1/api.php?target=lir&action=delete&id=100

Add

URL	/api/v1/api.php?target=lir&action=add
Description	Adds a new LIR. LIR creation utilizes the Resource system - see API Module - Resource - Add for details on adding a resource via the API.
Returns	**Examples:** SUCCESSFUL `{ "success":1, "message":"Resource added", "data": { "id":14063, "name":"TestLIR", "slug":"testlir", "type":"entry", "parent_id":1, "category_id":null, "date":1517513319, "modified":1517513319, "attr": { "_section":"94", "rir":"ARIN", "asn":"20202", "org-handle":"org1",`

```
"admin-poc":"admin1",
"net-poc":"tech1",
"abuse-poc":"abuse1",
"net-name-prefix":"test-",
"api-key":10,
"mnt-by":"",
"admin-c":"",
"tech-c":"",
"_gadget_data":false
},
"section":
{
"id":"94",
"name":"LIR",
"slug":"lir",
            "type":"section",
            "parent_id":"1",
            "category_id":null,
            "date":1375846025,
            "modified":1375846025,
            "attr":[]
        },
        "gadgets":false
    }
}
```


ERROR


```
{
    "success":0,
    "message":"error message"
}
```


Required Parameters

(meta[ ] =)

Name	Type	Example	Notes
meta[name]	STRING	TestLIR	Name of the new LIR resource.
meta[type]	STRING	entry	Type of resource - Adding a LIR will **always** be "entry".
meta[section]	STRING	lir	Section of the resource object. - Adding a LIR will **always** have "lir" as the section.

Fields Information

Detail on the "fields" array:		
fields []	ARRAY	Entry field values (for fields that have already been assigned to the section) can be populated when the entry is created. The format is field[field-slug][field-instance]. If the field instance is left blank, it will simply be the next value in the instance array. For example: *fields[network-fqdn][]=example.com&fields[network-fqdn][]=test.com*

would be written in JSON as

```
var fields = {
     "network-fqdn": [
          "example.com",
          "test.com"
     ]
}
```

Please note that the Field Slug might differ from the Field Name! To find the correct slug to use in adding resources with field values go the Section of the Resource you are adding, click 'Edit', then click the name of the Fields you will be populating. An Edit Field box will pop up which displays the Field's slug.

A field can be added to a section multiple times. The field instance is used to keep track of which field occurrence we are referring. In this example, the network-fqdn field had been added twice to the section so we were able to store two values for it.

Required Parameters

(fields[ ][] =)

Name	Type	Example	Notes
fields[rir][]	STRING	ARIN	The RIR for the LIR. Accepted values are "ARIN", "RIPE", "LACNIC", "AfriNIC", "APNIC", and "1918".
fields[asn][]	STRING	20202	The ASN (Autonomous System Number) for the LIR.

Optional Parameters

(fields[ ][] =)

For LIRs with RIR = "ARIN":

Name	Type	Example	Notes
fields[org-handle][]	STRING	org1	Organization Handle. **NOTE:** When providing field information, Organization handle is **required** in order for the remaining fields to populate.
fields[admin-poc][]	STRING	admin1	The admin point of contact object name.
fields[net-poc][]	STRING	tech1	The network point of contact for this object.
fields[abuse-poc][]	STRING	abuse1	The abuse point of contact object name.
fields[net-name-prefix][]	STRING	test-	The network name prefix.
fields[api-key][]	STRING	akakakakakaka	API key used to interface with RIR services

For LIRs with RIR = "RIPE", "LACNIC", "AfriNIC", "APNIC", and "1918". :

Name	Type	Example	Notes
fields[mnt-by][]	STRING	maint1	The name of the maintainer object. **NOTE:** When providing field information, Maintainer name is **required** in order for the remaining fields to populate.
fields[mnt-by-password][]	STRING	passwordabcd	The maintainer password.
fields[admin-c][]	STRING	admin1	Administrative contact for this object.
fields[tech-c][]	STRING	tech1	Technical contact for this object

Example URL	**ARIN example with only minimum required information:** /api/v1/api.php?target=lir&action=add&meta[name]=TestLIR1&meta[type]=entry&meta[section]=lir&fields[rir][]=ARIN&fields[asn][]=20202 **ARIN example with full Organization field details:** /api/v1/api.php?target=lir&action=add&meta[name]=TestLIR2&meta[type]=entry&meta[section]=lir&fields[rir][]=ARIN&fields[asn][]=20202&fields[org-handle][]=org1&fields[admin-poc][]=admin1&fields[net-poc][]=tech1&fields[abuse-poc][]=abuse1&fields[net-name-prefix][]=test-&fields[api-key][]=akakakakakaka **Non-ARIN example with only minimum required information:** /api/v1/api.php?target=lir&action=add&meta[name]=TestLIR3&meta[type]=entry&meta[section]=lir&fields[rir][]=RIPE&fields[asn][]=20202 **Non-ARIN example with full Organization field details:** /api/v1/api.php?target=lir&action=add&meta[name]=TestLIR4&meta[type]=entry&meta[section]=lir&fields[rir][]=1918&fields[asn][]=20202&fields[mnt-by][]=maint1&fields[mnt-by-password][]=passwordabcd&fields[admin-c][]=admin1&fields[tech-c][]=tech1

Update

URL	/api/v1/api.php?target=lir&action=update
Description	Updates a LIR. LIR updates utilize the Resource system - see API Module - Resource - Update for details on editing a resource via the API.
Returns	**Examples:**

SUCCESSFUL


```
{
 "success":1,
 "message":"Resource Updated",
 "data":
 {
 "id":"206",
 "name":"TestName",
 "slug":"dstl-reserved",
 "type":"entry",
 "parent_id":"191",
 "category_id":null,
 "date":1470755920,
 "modified":1517513903,
 "attr":
 {
 "mnt-by-password":11,
 "rir":"RIPE",
 "asn":"30303",
 "mnt-by":"Maint2",
 "admin-c":"admin4",
 "tech-c":"Tech5",
```

```
"_section":"162",
"_custom_id":"",
"_gadget_data":[]
},
"section":
{
"id":"162",
"name":"4BCH",
"slug":"4bch",
"type":"section",
"parent_id":"1",
"category_id":null,
"date":1468356788,
"modified":1468356788,
"attr":[]
},
"gadgets":[]
}
}
```


ERROR


```
{
    "success":0,
    "message":"error message"
}
```


Required Parameters

(meta[ ] =)

Name	Type	Example	Notes
meta[id]	INTEGER	1234	ID of the LIR resource to update.
meta[type]	STRING	entry	Type of resource - Updating a LIR will **always** be "entry".

Optional Parameters

(meta[ ] =)

Name	Type	Example	Notes
meta[name]	STRING	TestLIR	Name of the LIR resource.

Required Parameters

(fields[ ][] =)

None.

Optional Parameters

(fields[ ][] =)

For LIRs with RIR = "ARIN":			
Name	**Type**	**Example**	**Notes**
fields[rir][]	STRING	ARIN	The RIR for the LIR. Accepted values are "ARIN", "RIPE", "LACNIC", "AfriNIC", "APNIC", and "1918".

fields[asn][]	STRING	20202	The ASN (Autonomous System Number) for the LIR.
fields[org-handle][]	STRING	org1	Organization Handle. **NOTE:** When providing field information, Organization handle is **required** in order for the remaining Org. object fields to populate.
fields[admin-poc][]	STRING	admin1	The admin point of contact object name.
fields[net-poc][]	STRING	tech1	The network point of contact for this object.
fields[abuse-poc][]	STRING	abuse1	The abuse point of contact object name.
fields[net-name-prefix][]	STRING	test-	The network name prefix.
fields[api-key][]	STRING	akakakakakaka	API key used to interface with RIR services

For LIRs with RIR = "RIPE", "LACNIC", "AfriNIC", "APNIC", and "1918". :

Name	Type	Example	Notes
fields[rir][]	STRING	RIPE	The RIR for the LIR. Accepted values are "ARIN", "RIPE", "LACNIC", "AfriNIC", "APNIC", and "1918".
fields[asn][]	STRING	20202	The ASN (Autonomous System Number) for the LIR.
fields[mnt-by][]	STRING	maint1	The name of the maintainer object. **NOTE:** When providing field information, Maintainer name is **required** in order for the remaining maintainer object fields to populate.
fields[mnt-by-password][]	STRING	passwordabcd	The maintainer password.
fields[admin-c][]	STRING	admin1	Administrative contact for this object.
fields[tech-c][]	STRING	tech1	Technical contact for this object

Example URL

Update example with only the minimum required information:

This sends only the meta data required for a success response, but it does not actually change any values.

/api/v1/api.php?target=lir&action=update&meta[id]=14068&meta[type]=entry

Update example with changing RIR, ASN, and updating all field information:

This example changes a non-ARIN LIR to an ARIN LIR, and provides all updated information for the new RIR type.

/api/v1/api.php?target=lir&action=update&meta[id]=14068&meta[type]=entry&meta[name]=TestLIR4b&fields[rir][]=ARIN&fields[asn][]=30303&fields[org-handle][]=OrgABC&fields[admin-poc][]=AdminABC&fields[tech-c][]=TechABC&fields[abuse-poc][]=AbuseABC&fields[net-name-prefix][]=TestABC-&fields[api-key][]=abcdabcd

API Module - Peering

Peering

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

- Peering
  - getCommunications
  - getPeers
  - getRequests
  - getSessions
  - addSession
  - configureSession
  - deleteSession
  - updateSession
  - resestPeerStatus
  - sendRequest
  - sendEmail
  - updatePeer

getCommunications

Base URL	/api/v1/api.php?target=peering&action=getCommunications
Description	Returns all communication data on peers at a particular exchange.
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"8 records found.","data":[{"name":"1&1 Internet","asn":"8560","request_status":null,"qualified":null,"is_peer":false,"id":"262","log_data":[]},{"name":"Akamai Technologies","asn":"20940","request_status":null,"qualified":null,"is_peer":false,"id":"2","log_data":[]},{"name":"Amazon.com","asn":"16509","request_status":null,"qualified":null,"is_peer":false,"id":"1418","log_data":[]},{"name":"Atrato IP Networks","asn":"5580","request_status":null,"qualified":null,"is_peer":false,"id":"2283","log_data":[]},{"name":"OVH","asn":"16276","request_status":null,"qualified":null,"is_peer":false,"id":"1264","log_data":[]},{"name":"Verisign","asn":"7342","request_status":null,"qualified":null,"is_peer":false,"id":"873","log_data":[]},{"name":"Walmart.com","asn":"17374","request_status":null,"qualified":null,"is_peer":false,"id":"627","log_data":[]},{"name":"Windstream Communications","asn":"7029","request_status":null,"qualified":null,"is_peer":false,"id":"1820","log_data":[]},{"name":"Yahoo!","asn":"10310","request_status":null,"qualified":null,"is_peer":false,"id":"27","log_data":[]},{"name":"Zayo","asn":"19092","request_status":null,"qualified":null,"is_peer":false,"id":"3611","log_data":[]},{"name":"Zayo (Abovenet Communications Inc.)","asn":"6461","request_status":null,"qualified":null,"is_peer":false,"id":"541","log_data":[]},{"name":"tw telecom","asn":"4323","request_status":null,"qualified":null,"is_peer":false,"id":"540","log_data":[]}]} ERROR: *{'success':0, 'message':'error message'}*
Required Parameters	**Name** / **Type** / **Example** / **Description** public_id / INTEGER / 1 / The unique numerical identifier of the exchange to retrieve peering communicaiton records for.
Optional Parameters	None
Example URL	/api/v1/api.php?target=peering&action=getCommunications&public_id=1

getPeers

URL	/api/v1/api.php?target=peering&action=getPeers
Description	Returns a list of all peers available at an exchange

Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"184 peers found.","data":[{"id":"262","public_id":"1","asn":"8560","name":"1&1 Internet","qualified":true,"is_peer":0,"request_status":"sent","info_prefixes":"150","public_ips":[],"contacts":[],"log_data":[]},"id":"286","public_id":null,"asn":"3856","name":"Packet Clearing House","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"100","public_ips":[],"contacts":[],"log_data":[]},{"id":"890","public_id":null,"asn":"13768","name":"PEER 1 Hosting","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"3000","public_ips":[],"contacts":[],"log_data":[]},{"id":"1676","public_id":null,"asn":"3737","name":"PenTeleData","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"80","public_ips":[],"contacts":[],"log_data":[]},{"id":"1560","public_id":null,"asn":"23265","name":"Pocketinet Communications, Inc.","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"200","public_ips":[],"contacts":[],"log_data":[]},{"id":"576","public_id":null,"asn":"32787","name":"Prolexic","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"500","public_ips":[],"contacts":[],"log_data":[]},"id":"353","public_id":null,"asn":"27524","name":"Xeex Communications","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"3000","public_ips":[],"contacts":[],"log_data":[]},{"id":"27","public_id":null,"asn":"10310","name":"Yahoo!","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"500","public_ips":[],"contacts":[],"log_data":[]},{"id":"1751","public_id":null,"asn":"13238","name":"Yandex LLC","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"60","public_ips":[],"contacts":[],"log_data":[]},{"id":"4078","public_id":null,"asn":"19468","name":"YieldBuild Inc","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"5","public_ips":[],"contacts":[],"log_data":[]},{"id":"541","public_id":null,"asn":"6461","name":"Zayo (Abovenet Communications Inc.)","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":"20000","public_ips":[],"contacts":[],"log_data":[]},{"id":"2351","public_id":null,"asn":"14824","name":"Zynga Game Network, Inc.","qualified":true,"is_peer":0,"request_status":null,"info_prefixes":null,"public_ips":[],"contacts":[],"log_data":[]}]} ERROR: {"success":1,"message":"No peers found."}
Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
public_id	INTEGER	1	The unique numerical identifier of the exchange to retrieve peering communication records for.
id	INT	1	The unique numerical identifier of the peer in peeringDB.
asn	INT	4436	
name	STRING	GTT	
aka	STRING	nLayer	
website	STRING	http://www.gt-t.net	
notes_public	STRING		
notes_private	STRING		
irr_as_set	STRING	AS-NLAYER	
info_traffic	ENUM	1 Tbps+	enum('Not Disclosed','0-20 Mbps','20-100Mbps','100-1000Mbps','1-5Gbps','5-10Gbps','10-20Gbps','20-50 Gbps','50-100 Gbps','100+ Gbps','100-200 Gbps','200-300 Gbps','300-500 Gbps','500-1000 Gbps','1 Tbps+') DEFAULT 'Not Disclosed'
info_ratio	ENUM	Mostly Outbound	enum('Not Disclosed','Heavy Outbound','Mostly Outbound','Balanced','Mostly Inbound','Heavy Inbound') DEFAULT 'Not Disclosed'
info_scope	ENUM	Global	enum('Not Disclosed','Regional','North America','Asia Pacific','Europe','Africa','South America','Global') DEFAULT NULL
info_type	ENUM	NSP	enum('Not Disclosed','NSP','Content','Cable/DSL/ISP','Enterprise','Educational/Research','Non-Profit') DEFAULT 'Not Disclosed'
info_prefixes	INT	10000	
info_lookingglass	STRING	http://lg.nlayer.net/	
info_routeserver	STRING	telnet://route-server.nlayer.net	
info_unicast	CHAR	1	
info_multicast	CHAR		
info_ipv6	CHAR	1	

	policy_url	STRING	http://www.gt-t.net/Peering_policies.aspx	
	policy_general	ENUM	Selective	enum('Open','Selective','Restrictive','No') DEFAULT NULL
	policy_locations	ENUM	Required - International	enum('Not Required','Preferred','Required - US','Required - International') DEFAULT NULL
	policy_ratio	ENUM	No	enum('Yes','No') DEFAULT NULL
	policy_contracts	ENUM	Not Required	enum('Not Required','Private Only','Required') DEFAULT NULL
	policy_nopublic	ENUM	N	enum('Y','N') NOT NULL DEFAULT 'N'
	policy_noprivate	ENUM	N	enum('Y','N') NOT NULL DEFAULT 'N'
	date_created	DATETIME	2013-03-21 15:36:42	Date the peeringdb entry was created
	date_lastupdated	DATETIME	2013-03-21 15:36:42	Date the peeringdb entry was last updated
	include_public_ips	BOOL	TRUE	Returns a list of all public facing IPs
	include_contacts	BOOL	TRUE	Returns a list of all contacts associated with peer(s)
	include_log_data	BOOL	TRUE	Returns a list of all log data associated with the peer(s) (use with care)
Example URL	/api/v1/api.php?target=peering&action=getPeers&public_id=1			

getRequests

URL	/api/v1/api.php?target=peering&action=getRequests
Description	Returns a list of all peering requests issued
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"1 request found.","data":[{"id":"131","public_id":"5","source_participant_id":"2335","source_asn":"8038","peer_participant_id":"1418","peer_asn":"16509","peer_name":"Amazon.com","email_type":"text","email_from":"ops@6connect.com","email_to":"nalinmk@gmail.com","subject":"Peering request from 6connect, Inc.","body":"Peering,\r\n\r\n6connect, Inc., 8038, would like to peer with Amazon.com at our common locations.\r\n\r\nFacility, IP Address\r\nEquinix Ashburn - 206.126.236.68\r\nEquinix Palo Alto - 198.32.176.36\r\nEquinix Ashburn - 206.126.236.35 \r\nEquinix San Jose - 206.223.116.177\r\nLINX Juniper LAN - 195.66.225.175\r\n\r\nSincerely,\r\nOperations\r\nops@6connect.com\r\n\r\n\r\n6connect, Inc. information:\r\nEquinix Palo Alto, 2001:504:d::33\r\nEquinix Palo Alto, 198.32.176.51 \r\n\r\nPeeringDB: http:\/\/as8038.peeringdb.com\/\r\n","status":null,"created":"2014-04-23 10:31:33","modified":"2014-04-23 10:31:33"}]} ERROR: {"success":1,"message":"No request found.","data":[]}
Required Parameters	None
Optional Parameters	**Name** / **Type** / **Example** / **Description** peer_participant_id / INTEGER / 1 / The numerical id of the peer
Example URL	/api/v1/api.php?target=peering&action=getRequests&peer_participant_id=1

getSessions

URL	/api/v1/api.php?target=peering&action=getSessions
Description	Returns a list of all bgp peering sessions
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"1 sessions found.","data":[{"id":"51","source_asn":"32787","source_ipaddr":"1.2.3.4","

resource_id":"422","resource_name":"ar1.inoc.com","peer_asn":"20940","peer_name":"Akamai Technologies","
peer_participant_id":"2","peer_ipaddr":"206.126.236.102","peer_hostname":null,"peer_group":"group b","public_id":"1","
public_name":"Equinix Ashburn","ip_type":"ipv4","type":"Peer","state":"not configured","prfx_max":"20","prfx_received":null,"
password":"0","note":null},]}

ERROR: {"success":1,"message":"No peers found."}

Required Parameters

Name	Type	Example	Description
public_id	INTEGER	1	The unique numerical identifier of the exchange to retrieve peering communicaiton records for.

Optional Parameters

Name	Type	Example	Description
id	INTEGER	41	
public_id	INTEGER		
source_asn	INTEGER		
source_ipaddr	STRING		
resource_id	INTEGER		
peer_asn	INTEGER		
peer_name	STRING		
peer_participant_id	INTEGER		
peer_ipaddr	STRING		
peer_hostname	STRING		
peer_group	STRING		
password	INTEGER		
type	STRING		
state	STRING		
prfx_max	INTEGER		
prfx_received	INTEGER		
ip_type	ENUM		enum('ipv4','ipv6') NOT NULL DEFAULT 'ipv4'
note	STRING		
created	TIMESTAMP		
modified	TIMESTAMP		
deleted	INTEGER		
public_id	INTEGER		

Example URL: /api/v1/api.php?target=peering&action=getPeers&public_id=1

addSession

URL	/api/v1/api.php?target=peering&action=addSession
Description	Adds a bgp session
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Session added: Amazon.com (AS8038\/1.2.3.5) - (AS16509\/206.126.236.68)","data":{"id":111,"source_asn":"8038","source_ipaddr":"1.2.3.5","resource_id":"422","resource_name":null,"peer_asn":"16509",""

	peer_name":"Amazon.com","peer_participant_id":"1418","peer_ipaddr":"206.126.236.68","peer_hostname":null,"peer_group":"LAME-PEERS","public_id":"1","public_name":null,"ip_type":"ipv4","type":"Peer","state":"not configured","prfx_max":"200","prfx_received":null,"password":"ace12345","note":"I'm a fancy note."}} ERROR: {"success":1,"message":"No request found.","data":[]}
Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
source_asn	INTEGER	1	The numerical id of the peer
source_ipaddr	STRING		
resource_id	INTEGER		
peer_asn	INTEGER		
peer_name	STRING		
peer_participant_id	INTEGER		
peer_ipaddr	STRING		
peer_hostname	STRING		
peer_group	STRING		
public_id			
type	STRING		
ip_type	ENUM		enum('ipv4','ipv6')
state	STRING		
prfx_max	INTEGER		
note	STRING		

Example URL	/api/v1/api.php?target=peering&action=getRequests&peer_participant_id=1

configureSession

URL	/api/v1/api.php?target=peering&action=configureSession
Description	Configure a BGP session on the router
Returns	**Examples:** SUCCESSFUL: ERROR: {"success":0,"message":"Unable to authenticate "}
Required Parameters	

Name	Type	Example	Description
session_id	INTEGER	1	

Optional Parameters	

Name	Type	Example	Description
session_id	INTEGER	1	The numerical id of the peer
source_ipaddr	STRING		
resource_id	INTEGER		
peer_asn	INTEGER		
peer_name	STRING		

	peer_participant_id	INTEGER		
	peer_ipaddr	STRING		
	peer_hostname	STRING		
	peer_group	STRING		
	public_id			
	type	STRING		
	ip_type	ENUM		enum('ipv4','ipv6')
	state	STRING		
	prfx_max	INTEGER		
	note	STRING		

Example URL	/api/v1/api.php?target=peering&action=configureSession&session_id=51&username=&config=conf+t%0A%0Arouter+bgp+32787%0A%0Ano+neighbor+206.126.236.102%0A%0Aneighbor+206.126.236.102+remote-as+20940%0Aneighbor+206.126.236.102+peer-group+group+b%0Aneighbor+206.126.236.102+description+Akamai+Technologies%0Aneighbor+206.126.236.102+maximum-prefix+20+%0Aneighbor+206.126.236.102+password+0+0%0A%0Aend%0Awrite

deleteSession

URL	/api/v1/api.php?target=peering&action=deleteSession
Description	Delete sessions matching criteria
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"1 sessions deleted."} ERROR: {"success":0,"message":"No sessions found to delete."}
Required Parameters	None
Optional Parameters	

Name	Type	Example	Description
id	INTEGER	41	
public_id	INTEGER		
source_asn	INTEGER		
source_ipaddr	STRING		
resource_id	INTEGER		
peer_asn	INTEGER		
peer_name	STRING		
peer_participant_id	INTEGER		
peer_ipaddr	STRING		
peer_hostname	STRING		
peer_group	STRING		
password	INTEGER		
type	STRING		
state	STRING		
prfx_max	INTEGER		
prfx_received	INTEGER		
ip_type	ENUM		enum('ipv4','ipv6') NOT NULL DEFAULT 'ipv4'

note	STRING		
created	TIMESTAMP		
modified	TIMESTAMP		
deleted	INTEGER		
public_id	INTEGER		

Example URL	/api/v1/api.php?target=peering&action=deleteSession&id=171

updateSession

URL	/api/v1/api.php?target=peering&action=updateSession
Description	Updates session values with any new values specified
Returns	**Examples:** SUCCESSFUL:{"success":1,"message":"Session updated: 123.net (AS32787\/1.2.3.4) - (AS12129\/206.126.236.70)","data":{"id":"41","source_asn":"32787","source_ipaddr":"1.2.3.4","resource_id":"422","resource_name":"ar1.inoc.com","peer_asn":"12129","peer_name":"123.net","peer_participant_id":"3899","peer_ipaddr":"206.126.236.70","peer_hostname":null,"peer_group":"group a","public_id":"1","public_name":"Equinix Ashburn","ip_type":"ipv4","type":"Peer","state":"not configured","prfx_max":"10","prfx_received":null,"password":"0","note":"Adding an awesome note."}} ERROR:
Required Parameters	None

Optional Parameters

Name	Type	Example	Description
id	INTEGER	41	
public_id	INTEGER		
source_asn	INTEGER		
source_ipaddr	STRING		
resource_id	INTEGER		
peer_asn	INTEGER		
peer_name	STRING		
peer_participant_id	INTEGER		
peer_ipaddr	STRING		
peer_hostname	STRING		
peer_group	STRING		
password	INTEGER		
type	STRING		
state	STRING		
prfx_max	INTEGER		
prfx_received	INTEGER		
ip_type	ENUM		enum('ipv4','ipv6') NOT NULL DEFAULT 'ipv4'
note	STRING		
created	TIMESTAMP		
modified	TIMESTAMP		
deleted	INTEGER		
public_id	INTEGER		

Example URL	/api/v1/api.php?target=peering&action=updateSession&note=Adding+an+awesome+note.&peer_group=group+a

resestPeerStatus

URL	/api/v1/api.php?target=peering&action=resetPeerStatus
Description	
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"1&1 Internet status reset","data":{"id":"262","public_id":"1","asn":"8560","name":"1&1 Internet","qualified":true,"is_peer":0,"request_status":"none","info_prefixes":null,"public_ips":[],"contacts":[],"log_data":[{"message":"Peer status reset","time":"2014-05-22 23:14:54","request_id":null,"session_id":null,"public_id":"1"},{"message":"Peer status reset","time":"2014-05-22 23:14:18","request_id":null,"session_id":null,"public_id":"1"},{"message":"Session deleted: 1&1 Internet (AS32787\/1.2.3.4) - (AS8560\/206.126.236.200)","time":"2014-05-22 22:39:43","request_id":null,"session_id":"71","public_id":"1"},{"message":"Request sent: ","time":"2014-04-12 13:24:43","request_id":"121","session_id":null,"public_id":"1"},{"message":"Session added: 1&1 Internet (AS32787\/1.2.3.4) - (AS8560\/206.126.236.200)","time":"2014-04-07 11:32:37","request_id":null,"session_id":"71","public_id":"1"}]}} ERROR: {"success":0,"message":"Could not find peer matching parameters"}
Required Parameters	**Name** / **Type** / **Example** / **Description** participant_id / INTEGER / 262 / The id of the peer in from the peeringDB peerParticipants table. public_id / INTEGER / 1 / The id of the exchange point from the peeringDB mgmtPublics table.
Optional Parameters	None
Example URL	/api/v1/api.php?target=peering&action=resetPeerStatus&participant_id=262&public_id=1

sendRequest

URL	/api/v1/api.php?target=peering&action=sendRequest
Description	Send a peering request (email) to a prospective peer. This will be deprecated in the next version for a simpler call, strongly suggest
Returns	**Examples:** SUCCESSFUL: {"success":1,"message":"Request sent","data":{"id":"922","public_id":"1","asn":"10933","name":"ATX Communicatio is_peer":0,"request_status":"sent","info_prefixes":null,"public_ips":[],"contacts":[],"log_data":[{"message":"Request sent to ","time":"2 request_id":"181","session_id":null,"public_id":"1"},{"message":"Request sent to ","time":"2014-05-27 16:49:30","request_id":"171"," public_id":"1"}]}} ERROR: {"success":0,"message":"Internal error"}
Required Parameters	**Name** / **Type** / **Example** / **Description** public_id / INTEGER / / peer_participant_id / INTEGER / / source_participant_id / INTEGER / / peer_name / STRING / / peer_asn / INTEGER / / email_from / STRING / 262 / email_to / STRING / 1 / subject / STRING / / body / STRING / /

	type	ENUM	html	enum('text','html')
	status	ENUM	sent	enum('sent','accepted','rejected')

Optional Parameters	None
Example URL	https://ops.6connect.com/peering-demo/api/v1/api.php?target=peering&action=sendRequest&peer_participant_id=1909&peer_asn=28929&peer_name=ASDASD+srl&source_participant_&public_id=1&type=text&email_from=ops%406connect.com&email_to=operations%40as28929.net&cc=&bcc=&subject=Peering+re2C+Inc. &body=%0D%0APeering%2C%0D%0A%0D%0A6connect%2C+Inc.%2C+8038%2C+would+like+to+peer+with+ASDASD+srl+at+our+common+locations.%3A%0D%0APeeringDB%3A+http%3A%2F%2Fas8038.p0A

sendEmail

URL	/api/v1/api.php?target=peering&action=sendEmail
Description	Send a peering request (email) to a prospective peer. This will be deprecated in the next version for a simpler call, strongly suggest against using.
Returns	**Examples:** SUCCESSFUL: ERROR:
Required Parameters	**Name** / **Type** / **Example** / **Description** participant_id / INTEGER / 262 / public_id / INTEGER / 1 /
Optional Parameters	None
Example URL	

updatePeer

URL	/api/v1/api.php?target=peering&action=updatePeer
Description	
Returns	**Examples:** SUCCESSFUL: ERROR:
Required Parameters	**Name** / **Type** / **Example** / **Description** participant_id / INTEGER / 262 / public_id / INTEGER / 1 /
Optional Parameters	None
Example URL	

API Module - Resource

Resources

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

- Resources
  - get
  - add
  - update
  - delete
  - get resource link
  - get resource search

get

URL	/api/v1/api.php?target=resource&action=get
Description	Get a resource or resources
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Search successful","data":[{"id":"57","name":"2nd Email","slug":"6c-contact-email2","type":"field","parent_id":"1","category_id":null,"attr":[]}]}* ERROR: *{"success":0,"message":"Search failed"}*
Optional Parameters	**General Parameters:** **Limit Results by ID:** At most, one of the following:

General Parameters:

Name	Type	Notes/Example
name	STRING	Name of the resource. Example: 6Connect, Inc.
slug	STRING	The unique URL friendly name of the resource. Example: 6connect-inc
type	STRING	Type of resource (eg. *entry*, *field*, *category, dnsmodule*)
search	STRING	Search the resource system for the provided term. Performs a "LIKE" search to return similar results. Similar to GET Resource SEARCH call.
search_column	STRING	Column to perform a 'search' on.
permissions__true	STRING	Set the permissions that must be true. Typically only used for UI / Gadget permissions.
permissions__false	STRING	Set the permissions that must be false. Typically only used for UI / Gadget permissions.
getFromBackup	INTEGER	Use data from the resource_archive table instead of the standard resource table, used with "orig_id" identifying parameter.

Limit Results by ID:

At most, one of the following:

Name	Type	Notes/Example
id	INTEGER	Get the resource which has this ID
orig_id	INTEGER	The resource id from the standard resource table, used in conjunction with 'getFromBackup'.
custom_id	INTEGER	The resource custom id provided by the user for the resource.

resource__in	ARRAY	Get any resource which has any of these IDs Syntax: &resource__in[]=1771&resource__in[]=14238 (Each resource id you wish to search over gets its own phrase.)
resource__not_in	ARRAY	Get all the resources which do not have any of these IDs Syntax: &resource__not_in[]=1771&resource__not_in[]=14238 (Each resource id you wish to exclude gets its own phrase.)

At most, one of the following:

Name	Type	Notes/Example
parent_id	INTEGER	Get the resources whose parent has this ID
parent__in	ARRAY	Get any resource whose parents have any of these IDs. Syntax: &parent__in[]=162&parent__in[]=299 (Each parent id you wish to search over gets its own phrase.)
parent__not_in	ARRAY	Get all resources whose parents do not have any of these IDs Syntax: &parent__not_in[]=1771&parent__not_in[]=14238 (Each parent id you wish to exclude gets its own phrase.)

At most, one of the following:

Name	Type	Notes/Example
category_id	INTEGER	Get the resources of the category that has this ID
category__in	ARRAY	Get any resources whose categories have any of these IDs. Syntax: &category__in[]=11002&category__in[]=11003 (Each category id you wish to search over gets its own phrase.)
category__not_in	ARRAY	Get the resources of all the categories that do not have any of these IDs Syntax: &parent__not_in[]=11002&parent__not_in[]=11003 (Each category id you wish to exclude gets its own phrase.)

Limit Results by Resource Link:

For resources for which exist a Resource Link, you may limit by resource link data:

Name	Type	Notes/Example
resource_link_type	STRING	The resource linkage relation name. Valid values include: For *type* = *dnsmodule:* **Valid Value** / **Notes** dnsViewACL — Links a ACL and a Group. The View (Group) must be resource1, resource id and the ACL resource must be resource2 in the linkage table dnsViewServer — Links a View (Group) with Server (DNS Connector), and the Group resource must be as resource1 and DNS Module as resource2. Used for attaching DNS servers to DNS Groups. dnsZoneMaster — Links a DNS Zone resource with the Server that will be exported as Master. The DNS Zone must be in resource1 and the server as resource2. Used for Directly attaching zones to servers. dnsZoneSlave — Links a DNS Zone resource with the Server that will be exported as

		Slave. The DNS Zone must be in resource1 and the server as resource2. Used for Directly attaching zones to servers.
		dnsZoneServer: Links a DNS Zone resource with a Server resource. The DNS Zone must be in resource1 and the server as resource2. Used to directly attach servers to zones.
		dnsZoneView: Links a DNS Zone resource with a Group. The DNS Zone must be resource1, the Group resource as resource 2.
resource_link_column	INTEGER	The column to be used for the parameter in "resource_link_value". Valid integer values are: '1' = to use resource1 in the first column '2' = to use resource2 in the second column
resource_link_value	INTEGER	The resource id for the resource_linkage table to search (Example: "10697")

Limit Results by Attributes:

You can further limit the results based on attributes the resources may have:

Name	Type	Notes/Example

attributes	ARRAY	You can search on multiple attributes by including an array of attribute options:
		`var data = {`
		`"type: "entry",`
		`"attributes": [`
		`{`
		`"attr_key": "_section",`
		`"attr_value": "105",`
		`},`
		`{`
		`"attr_key": "address-mail-state",`
		`"attr_value": "CA",`
		`}`
		`],`
		`"resources_per_page: 10`
		`}`

attr_key	STRING	The name of the attribute. Example: network-fqdn
attr_value	STRING	The value of any attribute, or if attr_key is specified, the value of the attribute defined in attr_key.
attr_compare	STRING	If both attr_key and attr_value are given, the results are by default compared based on the value given as attr_value being equal to the value stored in the database. You can optionally change this by setting the STRING value of attr_compare to one of the following: • = *(default)* • != • >= • < • <= • LIKE • NOT LIKE • IN • NOT IN

		• BETWEEN • NOT BETWEEN When attr_compare is set to IN, NOT IN, BETWEEN, NOT BETWEEN, then attr_value must either be an array or a comma separated string.
attr_load	BOOL	Load resource attributes along with the resource entry

Result Ordering:

Name	Type	Notes/Example
order	STRING	Set the direction of the ordering of the results by ascending or descending order. Valid values are: • ASC *(default)* • DESC
orderby	STRING	The parameter to order results by. Valid values include: • none • id • name *(default)* • slug • type • parent_id • date • resource__in *(preserve order given in the resource__in array)*

Range Selection / Paging:

You can restrict the range of the resources returned.

Name	Type	Notes/Example
resources_per_page	INTEGER	How many resources to return per page, e.g.: '10' .
offset	INTEGER	How many resources to offset from the initial resource, to use as the first resource provided in the return list (the initial resource is 0, not 1).
paged	INTEGER	The page to return (starts at 1, not 0). This parameter is provided for convenience and is used to calculate the offset where: offset=(paged-1)*resources_per_page

Example URL	/api/v1/api.php?target=resource&action=get&id=7

add

URL	/api/v1/api.php?target=resource&action=add
Description	Add a resource.
Returns	**Examples:** */api/v1/api.php?target=resource&action=add&meta[name]=apitest&meta[type]=entry&meta[section]=firewall&fields[network-fqdn][]=www.example.com* SUCCESSFUL: {"success":1,"message":"Resource added","data":{"id":1077,"name":"apitest","slug":"apitest","type":"entry","parent_id":1,"category_id":"NULL","attr":{"_section":"70","network-fqdn":"www.example.com"},"section":{"id":"70","name":"Firewall","slug":"firewall","type":"section","parent_id":"1","category_id":null,"attr":{}}}} */api/v1/api.php?target=resource&action=add&meta[name]=apitest&meta[type]=entry&fields[network-fqdn][]=www.example.com* ERROR:{"success":0,"message":"Entries must be assigned to a section"}
Required	

Parameters

Name	Type	Notes/Example
meta[name]	STRING	Name of the resource
meta[type]	STRING	Type of resource (entry, section, field, etc.)

Optional Parameters

Name	Type	Notes/Example
meta[parent_id]	INTEGER	ID of the parent resource
meta[category_id]	INTEGER	ID of the category

Required Parameters

(meta [type] = entry)

One of the following:

Name	Type	Notes/Example
meta[section_id]	INTEGER	ID of the section that the entry will be assigned to
meta[section]	STRING	Slug of the section that the entry will be assigned to

Optional Parameters

(meta [type] = entry)

Name	Type	Notes/Example

fields[]	ARRAY	Entry field values (for fields that have already been assigned to the section) can be populated when the entry is created.
		
		The format is field[field-slug][field-instance]. If the field instance is left blank, it will simply be the next value in the instance array. For example:
		
		fields[network-fqdn][]=example.com&fields[network-fqdn][]=test.com
		
		would be written in JSON as
		
		`var fields = {`
		`"network-fqdn": [`
		`"example.com",`
		`"test.com"`
		`]`
		`}`
		
		Please note that the Field Slug might differ from the Field Name! To find the correct slug to use in adding resources with field values go the Section of the Resource you are adding, click 'Edit', then click the name of the Fields you will be populating. An Edit Field box will pop up which displays the Field's slug.
		
		A field can be added to a section multiple times. The field instance is used to keep track of which field occurrence we are referring. In this example, the network-fqdn field had been added twice to the section so we were able to store two values for it.

meta [custom_id]	STRING	A custom ID for the entry. In the past this has been called the Resource Holder ID or Customer ID. Most recently it was implemented as a text field with the slug "6c-resourceholder-id." Now it is a fundamental part the entry type resources.

Required Parameters

(meta [type] = field)

Name	Type	Notes/Example
meta[field_type]	STRING	Type of field • text • textarea • radios • checkboxes • choicebox

Optional Parameters

(meta [type] = field)

Name	Type	Notes/Example
meta [help_block]	STRING	Fields can have a line of text under them with instructions
meta [options]	ARRAY	Fields of type radios, checkboxes, or choicebox can have multiple options. This could be multiple radio buttons or a choicebox (dropdown) with several options. For example: meta[type]=field&meta[name]=Colors&meta[field_type]=choicebox&meta[options][]=Blue&meta [options][]=Green Will create a choicebox with dropdown options of Blue and Green.

Required Parameters

(meta [type] = gadgets)

Name	Type	Notes/Example
gadgets[x][uuid]	INTEGER	x: The nth gadget being described in the call ('0' for the first gadget, '1' for the second, and so on). uuid: User-generated ID of the gadget to be created.
gadgets[x] [code]	STRING	x: The nth gadget being described in the call ('0' for the first gadget, '1' for the second, and so on). code: Slug of the gadget code to be created. List of valid Gadget codes: • Contact Info: "_contact_info" • Contacts: "_contacts" • DHCP Server: "_dhcp_server" • DNS: "_dns" • Document Storage: "_document_storage" • IPAM: "_ipam" • Peer Groups: "_peering_peer_groups" • Peering Sessions: "_peering_sessions" • VRFs: "_peering_vrfs" • Resource Linkage: "_resource_linkage" • Resource View: "_resource_view" • Reverse API Console: "_reverse_api" • Tech Info: "_tech_info"

Example - Adding the IPAM Gadget to a Section:

api.php?target=resource&action=add&meta[type]=section&meta[name]=TestSection_1&meta[parent_id]=1&gadgets[0][uuid] =uuid-586dbd260d6ef&gadgets[0][code]=_ipam

update

URL	/api/v1/api.php?target=resource&action=update
Description	Update a resource.
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Resource Updated","data":{"id":"1055","name":"87-child-1","slug":"87-child-1","type":" entry","parent_id":"87","category_id":"65","attr":{"_section":"70"},"section":{"id":"70","name":"Firewall","slug":"firewall","type":" section","parent_id":"1","category_id":null,"attr":{}}}}* ERROR: *{"success":0,"message":"No resource found with ID: 1079"}*

Required Parameters

Name	Type	Notes/Example
meta[id]	INTEGER	ID of resource
meta[type]	STRING	Type of resource (entry, section, field, ect)

Optional Parameters

(meta [type] = entry)

Name	Type	Notes/Example
fields[]	ARRAY	See "add" documentation

Optional Parameters

(meta [type] = section)

Name	Type	Notes/Example
fields []	ARRAY	The fields value should be all the fields that are assigned to the section. Giving an empty array as the fields value will remove all fields from the section. The format is: fields[position][key] The position value is the position that the field will appear in (0 is first). The position value must always be included. An example field format for an existing field could be: fields[0][id]=2 fields[0][slug]=asset-serial-number fields[0][help_block]=something fields[0][new]=false ■ Either the id or the slug is required, not both. ■ When the "new" parameter is not included, FALSE is assumed If you want to create a new field and assign it to the section, use a format like this: fields[10][name]=TextArea fields[10][field_type]=textarea fields[10][new]=true

delete

URL	/api/v1/api.php?target=resource&action=delete
Description	Delete a resource.
Returns	**Examples:** SUCCESSFUL: *{"success":1,"message":"Resource deleted."}* ERROR: *{"success":0,"message":"No resource found with ID: 57"}*
Required Parameters	

Name	Type	Notes/Example
id	INTEGER	ID of the resource

Optional Parameters

Name	Type	Notes/Example
recursive	BOOL	When 1, deletes parent and child entries for the resource

A recursive delete will delete all resources, which are permitted to be deleted, from the bottom up.

Imagine the following hierarchy:

```
              A
     B1                B2
 C11    C12        C21    C22
```

If a recursive delete is performed on A, but C21 is not deletable, the following

	resources would still be deleted: (B1, C11, C12, C22). B2 would not be deleted because it depends on C21 and A would not be deleted because it depends on B2.
Example URL	/api/v1/api.php?target=resource&action=delete&id=57

get resource link

Description	Get available resource links. If no resource links exist for the given resource, an empty object is returned.
URL	/api/v1/api.php?target=resource&action=getLink
Returns	**Examples:**

SUCCESSFUL:	{"success":1 ,"message":"Search successful", "data":{"meta":{"totalRecords":"3", "retrieved":3}, "0":{"id":"22", "resource_id1":"1292", "resource_id2":"1302", "relation":"dhcpPoolLink"}, "1":{"id":"2", "resource_id1":"1292", "resource_id2":"1452", "relation":"dhcpPoolLink"}, "2":{"id":"12", "resource_id1":"1422", "resource_id2":"1482", "relation":"dhcpPoolLink"}}}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	Id of the resource linkage
resource_id1	INTEGER	The id of the parent resource
resource_id2	INTEGER	The id of the linked resource
relation	STRING	The relation type. Relation types include: contact, dhcpPoolLink, dnsViewACL, dnsViewServer, dnsZoneMaster, dnsZoneServer, dnsZoneView

Meta Attributes:

Name	Type	Description
totalRecords	INTEGER	How many records were found by this query, without pagination.
retrieved	INTEGER	How many records were returned by this query, with pagination.

Optional Attributes:

Name	Type	Description
resultsPerPage	INTEGER	How many records to include per page display.*
page	INTEGER	Which page to display, when used with "resultsPerPage"*
*Example pagination: api.php?target=resource&action=getLink&relation=dhcpPoolLink&resultsPerPage=100&page=2		

get resource search

Description	Search the resource system for the provided term. Performs a "LIKE" search to return similar results.
URL	/api/v1/api.php?target=resource&action=get&search=
Returns	**Examples:**

SUCCESSFUL:	{"success":1,"message":"Search successful","data":[{"id":"11011","name":"a6connectchildentry","slug":"a6connectchildentry","type":"entry","parent_id":"4210","category_id":null,"date":1499106555,"modified":

	1499106555,"attr":{"_section":"4214"},"section":{"id":"4214","name":"aQA Section","slug":"aqa-section","type":"section","parent_id":"1","category_id":null,"date":1498775688,"modified":1499106630,"attr":[]},"gadgets":[]}],"result_count":1,"found_count":1}
ERROR:	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	Id of the resource linkage
name	STRING	The resource name
slug	STRING	The resource slug
type	STRING	The resource type.
parent_id	INTEGER	ID of the parent resource
category_id	INTEGER	ID of the resource category type
date	INTEGER	Resouce creation date
modified	INTEGER	Resource last modified date
attr	JSON	A JSON list of resource attributes

Required Attributes:

Name	Type	Description
search	STRING	The search term

Example URL	/api/v1/api.php?target=resource&action=get&search=6connect

API Module - VLAN

VLAN

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

- VLAN
  - getById
  - getDomains
  - enable
  - addDomain
  - getAvailable
  - get
  - deleteDomain
  - updateDomain
  - update
  - removeTags
  - addTags
  - smartAssign

getById

URL	api/v1/api.php?target=vlan&action=getById
Description	get information of a vlan
Returns	Examples

SUCCESSFUL	{"success":1,"message":"1 VLAN found. ","data":[{"id":"11190","vlan":"176","domain_id":"1","resource_id":null,"name":"","domain_name":"DefaultDomain","tags":[],"tagsString":[]}]}
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
id	INTEGER	11190	ID of the VLAN

Optional Parameters	None
Example URL	api/v1/api.php?target=vlan&action=getById&id=11190

getDomains

URL	api/v1/api.php?target=vlan&action=getDomains
Description	get list and info of all domains or a specific domain. When specifying the domain the results will include tag info
Returns	Examples

SUCCESSFUL	{"success":1,"message":"6 Domains found. ","data":[{"id":"1","domain":"DefaultDomain","attr_6c":{"range":"S","restricted":[1,1002,1003,1004,1005]},"vlans":[{"id":"22866","vlan":"10","name":""},{"id":"1","vlan":"101","name":""},{"id":"3","vlan":"102","name":""},{"id":"22865","vlan":"104","name":""},{"id":"4","vlan":"105","name":"NewName"},{"id":"5","vlan":"106","name":"ThisIsAName"},{"id":"2","vlan":"107","name":""},{"id":"11189","vlan":"175","name":"SomeWhoCallMeTim"},{"id":"11190","vlan":"176","name":""},{"id":"11191","vlan":"177","name":""},{"id":"11192","vlan":"178","name":""},{"id":"7","vlan":"996","name":""},{"id":"8","vlan":"997","name":""},{"id":"9","vlan":"998","name":""},{"id":"10","vlan":"999","name":"CORP-DMZ"},{"id":"6","vlan":"1021","name":""}],"vlans_unnamed":null,"type":"domain","util":{"S":{"used":15,"total":1000}}},{"id":"2","domain":"6connect.com","attr_6c":{"range":"S","restricted":[1,1002,1003,1004,1005]},"vlans":[{"id":"19","vlan":"10","name":""},{"id":"20","vlan":"11","name":""},

		... {"id":"12755","vlan":"70","name":""},{"id":"12756","vlan":"71","name":""},{"id":"12757","vlan":"72","name":""}, {"id":"12758","vlan":"73","name":""},{"id":"12759","vlan":"74","name":""},{"id":"12760","vlan":"75","name":""}]," vlans_unnamed":null,"type":"domain","util":{"S":{"used":38,"total":1000},"E":{"used":0,"total":3089}}}]}
	ERROR	*{ "success":0, "message":"error message" }*
Required Parameters	None	
Optional Parameters		

Name	Type	Example	Description
id	INTEGER	2	ID of the domain

Example URL	api/v1/api.php?target=vlan&action=getDomains&id=2

enable

URL	api/v1/api.php?target=vlan&action=enable
Description	enable vlans in a domain
Returns	Examples

SUCCESSFUL	{"success":1,"message":"Success. ","data":"3 in request (0 were found already named\/available and 3 found as unavailable). 3 VLANs have been updated to unnamed available entries."}
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
domainId	INTEGER	1	the domain ID in the domain table
vlan	INTEGER or STRING	18,19,20	vlan for this domain that we want enabled

Optional Parameters	None
Example URL	api/v1/api.php?target=vlan&action=enable&domainId=1&vlan=18,19,20

addDomain

URL	api/v1/api.php?target=vlan&action=addDomain
Description	add a domain
Returns	Examples

SUCCESSFUL	{"success":1,"message":"domain 10 added","id":10,"data":[{"id":"10","domain":"sdfasfaf","attr_6c":{"range":" S","restricted":[1,1002,1003,1004,1005]},"vlans":[],"vlans_unnamed":{"1":null,"2":null,"3":null,"4":null,"5":null," 6":null,"7":null,"8":null,"9":null,"10":null,"11":null,"12":null,"13":null,"14":null,"15":null,"16":null,"17":null,"18": null,"19":null,"20":null,"21":null,"22":null,"23":null,"24":null,"25":null,"26":null,"27":null,"28":null,"29":null,"30": null,"31":null,"32":null,"33":null,"34":null,"35":null,"36":null,"37":null,"38":null,"39":null,"40":null,"41":null,"42": null,"43":null,"44":null,"45":null,"46":null,"47":null,"48":null,"49":null,"50":null,"51":null,"52":null,"53":null,"54": null,"55":null,"56":null,"57":null,"58":null,"59":null,"60":null,"61":null,"62":null,"63":null,"64":null,"65":null,"66": null,"67":null,"68":null,"69":null,"70":null,"71":null,"72":null,"73":null,"74":null,"75":null,"76":null,"77":null,"78": null,"79":null,"80":null,"81":null,"82":null,"83":null,"84":null,"85":null,"86":null,"87":null,"88":null,"89":null,"90": null,"91":null,"92":null,"93":null,"94":null,"95":null,"96":null,"97":null,"98":null,"99":null,"100":null,"101":null," 102":null,"103":null,"104":null,"105":null,"106":null,"107":null,"108":null,"109":null,"110":null,"111":null,"112": null,"113":null,"114":null,"115":null,"116":null,"117":null,"118":null,"119":null,"120":null,"121":null,"122":null,"

123":null,"124":null,"125":null,"126":null,"127":null,"128":null,"129":null,"130":null,"131":null,"132":null,"133":
null,"134":null,"135":null,"136":null,"137":null,"138":null,"139":null,"140":null,"141":null,"142":null,"143":null,"
144":null,"145":null,"146":null,"147":null,"148":null,"149":null,"150":null,"151":null,"152":null,"153":null,"154":
null,"155":null,"156":null,"157":null,"158":null,"159":null,"160":null,"161":null,"162":null,"163":null,"164":null,"
165":null,"166":null,"167":null,"168":null,"169":null,"170":null,"171":null,"172":null,"173":null,"174":null,"175":
null,"176":null,"177":null,"178":null,"179":null,"180":null,"181":null,"182":null,"183":null,"184":null,"185":null,"
186":null,"187":null,"188":null,"189":null,"190":null,"191":null,"192":null,"193":null,"194":null,"195":null,"196":
null,"197":null,"198":null,"199":null,"200":null,"201":null,"202":null,"203":null,"204":null,"205":null,"206":null,"
207":null,"208":null,"209":null,"210":null,"211":null,"212":null,"213":null,"214":null,"215":null,"216":null,"217":
null,"218":null,"219":null,"220":null,"221":null,"222":null,"223":null,"224":null,"225":null,"226":null,"227":null,"
228":null,"229":null,"230":null,"231":null,"232":null,"233":null,"234":null,"235":null,"236":null,"237":null,"238":
null,"239":null,"240":null,"241":null,"242":null,"243":null,"244":null,"245":null,"246":null,"247":null,"248":null,"
249":null,"250":null,"251":null,"252":null,"253":null,"254":null,"255":null,"256":null,"257":null,"258":null,"259":
null,"260":null,"261":null,"262":null,"263":null,"264":null,"265":null,"266":null,"267":null,"268":null,"269":null,"
270":null,"271":null,"272":null,"273":null,"274":null,"275":null,"276":null,"277":null,"278":null,"279":null,"280":
null,"281":null,"282":null,"283":null,"284":null,"285":null,"286":null,"287":null,"288":null,"289":null,"290":null,"
291":null,"292":null,"293":null,"294":null,"295":null,"296":null,"297":null,"298":null,"299":null,"300":null,"301":
null,"302":null,"303":null,"304":null,"305":null,"306":null,"307":null,"308":null,"309":null,"310":null,"311":null,"
312":null,"313":null,"314":null,"315":null,"316":null,"317":null,"318":null,"319":null,"320":null,"321":null,"322":
null,"323":null,"324":null,"325":null,"326":null,"327":null,"328":null,"329":null,"330":null,"331":null,"332":null,"
333":null,"334":null,"335":null,"336":null,"337":null,"338":null,"339":null,"340":null,"341":null,"342":null,"343":
null,"344":null,"345":null,"346":null,"347":null,"348":null,"349":null,"350":null,"351":null,"352":null,"353":null,"
354":null,"355":null,"356":null,"357":null,"358":null,"359":null,"360":null,"361":null,"362":null,"363":null,"364":
null,"365":null,"366":null,"367":null,"368":null,"369":null,"370":null,"371":null,"372":null,"373":null,"374":null,"
375":null,"376":null,"377":null,"378":null,"379":null,"380":null,"381":null,"382":null,"383":null,"384":null,"385":
null,"386":null,"387":null,"388":null,"389":null,"390":null,"391":null,"392":null,"393":null,"394":null,"395":null,"
396":null,"397":null,"398":null,"399":null,"400":null,"401":null,"402":null,"403":null,"404":null,"405":null,"406":
null,"407":null,"408":null,"409":null,"410":null,"411":null,"412":null,"413":null,"414":null,"415":null,"416":null,"
417":null,"418":null,"419":null,"420":null,"421":null,"422":null,"423":null,"424":null,"425":null,"426":null,"427":
null,"428":null,"429":null,"430":null,"431":null,"432":null,"433":null,"434":null,"435":null,"436":null,"437":null,"
438":null,"439":null,"440":null,"441":null,"442":null,"443":null,"444":null,"445":null,"446":null,"447":null,"448":
null,"449":null,"450":null,"451":null,"452":null,"453":null,"454":null,"455":null,"456":null,"457":null,"458":null,"
459":null,"460":null,"461":null,"462":null,"463":null,"464":null,"465":null,"466":null,"467":null,"468":null,"469":
null,"470":null,"471":null,"472":null,"473":null,"474":null,"475":null,"476":null,"477":null,"478":null,"479":null,"
480":null,"481":null,"482":null,"483":null,"484":null,"485":null,"486":null,"487":null,"488":null,"489":null,"490":
null,"491":null,"492":null,"493":null,"494":null,"495":null,"496":null,"497":null,"498":null,"499":null,"500":null,"
501":null,"502":null,"503":null,"504":null,"505":null,"506":null,"507":null,"508":null,"509":null,"510":null,"511":
null,"512":null,"513":null,"514":null,"515":null,"516":null,"517":null,"518":null,"519":null,"520":null,"521":null,"
522":null,"523":null,"524":null,"525":null,"526":null,"527":null,"528":null,"529":null,"530":null,"531":null,"532":
null,"533":null,"534":null,"535":null,"536":null,"537":null,"538":null,"539":null,"540":null,"541":null,"542":null,"
543":null,"544":null,"545":null,"546":null,"547":null,"548":null,"549":null,"550":null,"551":null,"552":null,"553":
null,"554":null,"555":null,"556":null,"557":null,"558":null,"559":null,"560":null,"561":null,"562":null,"563":null,"
564":null,"565":null,"566":null,"567":null,"568":null,"569":null,"570":null,"571":null,"572":null,"573":null,"574":
null,"575":null,"576":null,"577":null,"578":null,"579":null,"580":null,"581":null,"582":null,"583":null,"584":null,"
585":null,"586":null,"587":null,"588":null,"589":null,"590":null,"591":null,"592":null,"593":null,"594":null,"595":
null,"596":null,"597":null,"598":null,"599":null,"600":null,"601":null,"602":null,"603":null,"604":null,"605":null,"
606":null,"607":null,"608":null,"609":null,"610":null,"611":null,"612":null,"613":null,"614":null,"615":null,"616":
null,"617":null,"618":null,"619":null,"620":null,"621":null,"622":null,"623":null,"624":null,"625":null,"626":null,"
627":null,"628":null,"629":null,"630":null,"631":null,"632":null,"633":null,"634":null,"635":null,"636":null,"637":
null,"638":null,"639":null,"640":null,"641":null,"642":null,"643":null,"644":null,"645":null,"646":null,"647":null,"
648":null,"649":null,"650":null,"651":null,"652":null,"653":null,"654":null,"655":null,"656":null,"657":null,"658":
null,"659":null,"660":null,"661":null,"662":null,"663":null,"664":null,"665":null,"666":null,"667":null,"668":null,"
669":null,"670":null,"671":null,"672":null,"673":null,"674":null,"675":null,"676":null,"677":null,"678":null,"679":
null,"680":null,"681":null,"682":null,"683":null,"684":null,"685":null,"686":null,"687":null,"688":null,"689":null,"
690":null,"691":null,"692":null,"693":null,"694":null,"695":null,"696":null,"697":null,"698":null,"699":null,"700":
null,"701":null,"702":null,"703":null,"704":null,"705":null,"706":null,"707":null,"708":null,"709":null,"710":null,"
711":null,"712":null,"713":null,"714":null,"715":null,"716":null,"717":null,"718":null,"719":null,"720":null,"721":
null,"722":null,"723":null,"724":null,"725":null,"726":null,"727":null,"728":null,"729":null,"730":null,"731":null,"
732":null,"733":null,"734":null,"735":null,"736":null,"737":null,"738":null,"739":null,"740":null,"741":null,"742":
null,"743":null,"744":null,"745":null,"746":null,"747":null,"748":null,"749":null,"750":null,"751":null,"752":null,"
753":null,"754":null,"755":null,"756":null,"757":null,"758":null,"759":null,"760":null,"761":null,"762":null,"763":
null,"764":null,"765":null,"766":null,"767":null,"768":null,"769":null,"770":null,"771":null,"772":null,"773":null,"
774":null,"775":null,"776":null,"777":null,"778":null,"779":null,"780":null,"781":null,"782":null,"783":null,"784":
null,"785":null,"786":null,"787":null,"788":null,"789":null,"790":null,"791":null,"792":null,"793":null,"794":null,"
795":null,"796":null,"797":null,"798":null,"799":null,"800":null,"801":null,"802":null,"803":null,"804":null,"805":
null,"806":null,"807":null,"808":null,"809":null,"810":null,"811":null,"812":null,"813":null,"814":null,"815":null,"
816":null,"817":null,"818":null,"819":null,"820":null,"821":null,"822":null,"823":null,"824":null,"825":null,"826":
null,"827":null,"828":null,"829":null,"830":null,"831":null,"832":null,"833":null,"834":null,"835":null,"836":null,"
837":null,"838":null,"839":null,"840":null,"841":null,"842":null,"843":null,"844":null,"845":null,"846":null,"847":
null,"848":null,"849":null,"850":null,"851":null,"852":null,"853":null,"854":null,"855":null,"856":null,"857":null,"
858":null,"859":null,"860":null,"861":null,"862":null,"863":null,"864":null,"865":null,"866":null,"867":null,"868":
null,"869":null,"870":null,"871":null,"872":null,"873":null,"874":null,"875":null,"876":null,"877":null,"878":null,"
879":null,"880":null,"881":null,"882":null,"883":null,"884":null,"885":null,"886":null,"887":null,"888":null,"889":
null,"890":null,"891":null,"892":null,"893":null,"894":null,"895":null,"896":null,"897":null,"898":null,"899":null,"
900":null,"901":null,"902":null,"903":null,"904":null,"905":null,"906":null,"907":null,"908":null,"909":null,"910":

	null,"911":null,"912":null,"913":null,"914":null,"915":null,"916":null,"917":null,"918":null,"919":null,"920":null,"921":null,"922":null,"923":null,"924":null,"925":null,"926":null,"927":null,"928":null,"929":null,"930":null,"931":null,"932":null,"933":null,"934":null,"935":null,"936":null,"937":null,"938":null,"939":null,"940":null,"941":null,"942":null,"943":null,"944":null,"945":null,"946":null,"947":null,"948":null,"949":null,"950":null,"951":null,"952":null,"953":null,"954":null,"955":null,"956":null,"957":null,"958":null,"959":null,"960":null,"961":null,"962":null,"963":null,"964":null,"965":null,"966":null,"967":null,"968":null,"969":null,"970":null,"971":null,"972":null,"973":null,"974":null,"975":null,"976":null,"977":null,"978":null,"979":null,"980":null,"981":null,"982":null,"983":null,"984":null,"985":null,"986":null,"987":null,"988":null,"989":null,"990":null,"991":null,"992":null,"993":null,"994":null,"995":null,"996":null,"997":null,"998":null,"999":null,"1000":null,"1001":null,"1002":null,"1003":null,"1004":null,"1005":null},"type":"domain","util":{"S":{"used":0,"total":1000}}}}}
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
domain	STRING	6connect.com	Name to call new domain
range	STRING	S	'S' or 'E', depending on VLAN range: extended or standard

Optional Parameters

None

Example URL

api/v1/api.php?target=vlan&action=addDomain&domain=6connect.com&range=S

getAvailable

URL

api/v1/api.php?target=vlan&action=getAvailable

Description

get VLANs in a domain that have not been named yet (even names that are '', or just uses their number as a name)

Returns

Examples

SUCCESSFUL	{"success":1,"message":"16 VLANs found. ","data":{"1":{"2":null,"3":null,"4":null,"5":null,"6":null,"7":null,"8":null,"9":null,"12":null,"13":null,"15":null,"16":null,"17":null,"21":null,"22":null,"23":null}}}
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
domainId	INTEGER or STRING	'1,2'	ID of the domains to search for

Optional Parameters

Name	Type	Example	Description
tags	INTEGER or STRING	'111,112'	ID of the tags to search for
min	INTEGER	24	VLAN to start search
max	INTEGER	200	VLAN to end search

Example URL

api/v1/api.php?target=vlan&action=getAvailable&domainId=1&tags=111,112&min=2&max=23

get

URL

api/v1/api.php?target=vlan&action=get

Description

Searches enabled VLANs. When not given options, returns all enabled VLANs. Note: an optional parameter, unavailable, is used to get available (un-enabled) VLANs as well

Returns

Examples

SUCCESSFUL	{"success":1,"message":"2 domains found. ","data":{"1":{"id":"1","domain":"DefaultDomain","attr_6c":null,"attr_custom":null,"vlans":[{"id":"4","vlan":"105","name":"NewName"}]},"2":{"id":"2","domain":"6connect.com","attr_6c":null,"attr_custom":null,"vlans":[{"id":"20","vlan":"11","name":""}]}}}
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters	None

Optional Parameters

Name	Type	Example	Description
unavailable	STRING	true	Will return available, instead of enabled, VLANs
domainId	INTEGER	1	domain ID
id	INTEGER	21	VLAN ID in the vlan table

Example URL	api/v1/api.php?target=vlan&action=get&id=4&unavailable=true

deleteDomain

URL	api/v1/api.php?target=vlan&action=deleteDomain
Description	Deletes a VLAN domain.

Returns

Examples

SUCCESSFUL	*{"success":1,"message":"Domain #7 successfully deleted."}*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
domainId	INTEGER	7	domain ID

Optional Parameters	None
Example URL	api/v1/api.php?target=vlan&action=deleteDomain&domainId=7

updateDomain

URL	api/v1/api.php?target=vlan&action=updateDomain
Description	Updates a VLAN domain.

Returns

Examples

SUCCESSFUL	{"success":1,"message":"Domain 2 updated","id":"2","data":[{"id":"2","domain":"44.6connect.com","attr_6c":{"range":"S","restricted":[1,1002,1003,1004,1005]},"vlans":[{"id":"19","vlan":"10","name":"","tags":["105"]},{"id":"20","vlan":"11","name":"","tags":["105"]},{"id":"21","vlan":"12","name":"","tags":["105"]},{"id":"22","vlan":"13","name":"","tags":["105"]},{"id":"23","vlan":"14","name":"","tags":["105"]},{"id":"24","vlan":"15","name":"","tags":["105"]},{"id":"25","vlan":"16","name":"","tags":["105"]},{"id":"26","vlan":"17","name":"","tags":["105"]},{"id":"27","vlan":"18","name":"","tags":["105"]},{"id":"29","vlan":"20","name":"","tags":["105"]},{"id":"30","vlan":"21","name":"","tags":["105"]},{"id":"3286","vlan":"3281","name":"Bob","tags":["105"]},{"id":"3287","vlan":"3282","name":""},{"id":"3288","vlan":"3283","name":""},{"id":"3289","vlan":"3284","name":""},{"id":"3290","vlan":"3285","name":""},{"id":"3291","vlan":"3286","name":""},{"id":"3292","vlan":"3287","name":""},{"id":"3293","vlan":"3288","name":""},{"id":"3294","vlan":"3289","name":""}],"vlans_unnamed":{"1":null,"2":{"tags":["105"]},"3":{"tags":["105"]}, ... "1002":null,"1003":null,"1004":null,"1005":null},"type":"domain","util":{"S":{"used":11,"total":1000}}}]}
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
domain	STRING	6connect.com	Name of VLAN Domain
range	STRING	E	VLAN range. E for Extended or S for Standard

Optional Parameters: None.

Example URL: api/v1/api.php?target=vlan&action=updateDomain&domain=DefaultDomainnn&range=S&id=1

update

URL: api/v1/api.php?target=vlan&action=update

Description: Update properties of a VLAN: name, tags, or both.

Returns

Examples

SUCCESSFUL	*{"success":1,"message":"VLAN (table ID 11735) updated","id":"11735","data":[{"id":"11735","vlan":"50","domain_id":"7","resource_id":null,"name":"","domain_name":"lax.com","tags":[],"tagsString":[]}]}*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
id	INTEGER	11735	VLAN record ID (which is “id” of the VLANs in “get” action results)

Optional Parameters

Name	Type	Example	Description
name	STRING or empty string	HQ	name of the VLAN
tags	INTEGER or STRING or empty string	111,112	ID of tags to be assigned to this VLAN. Multiple tags IDs are assignable with a comma delimiter. Empty parameter will result in no tags being assigned.
enabled	BOOLEAN	false	Set the VLAN as enabled (true) or disabled (false).

Example URL:

api/v1/api.php?target=vlan&action=update&id=11735&name=OReilly&tags=156,159

api/v1/api.php?target=vlan&action=update&id=11735&name=OReilly

api/v1/api.php?target=vlan&action=update&id=11735&tags=156,159

api/v1/api.php?target=vlan&action=update&id=11735&name=

api/v1/api.php?target=vlan&action=update&id=11735&tags=

removeTags

URL: api/v1/api.php?target=vlan&action=removeTags

Description: Remove tags from a domain's VLAN(s).

Returns

Examples

SUCCESSFUL	*{"success":1,"message":"VLAN tags for VLANs updated","id":"1","data":[]}*
ERROR	*{ "success":0, "message":"error message" }*

Required

Parameters

Name	Type	Example	Description
domainId	INTEGER	1	domain ID for domain whose VLANs will be un-tagged
vlan	INTEGER or STRING	500 500-510	a single VLAN (not the record ID from the get action results, but actual VLAN ID), OR range of VLANs (using hyphen for minimum through maximum), OR comma-delimited list of VLANs and/or VLAN ranges
tagId	INTEGER or STRING	150,99	a single tag ID or comma-delimited list of tag ID's

Optional Parameters	None
Example URL	api/v1/api.php?target=vlan&action=removeTags&domainId=1&vlan=500-510&tagId=159 api/v1/api.php?target=vlan&action=removeTags&domainId=1&vlan=400,406,500-510&tagId=159,160

addTags

URL	api/v1/api.php?target=vlan&action=addTags
Description	Add tags to a domain's VLAN(s).

Returns

Examples

SUCCESSFUL	*{"success":1,"message":"VLAN tags for VLANs updated","id":"1","data":[]}*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
domainId	INTEGER	1	domain ID for domain whose VLANs will be un-tagged
vlan	INTEGER or STRING	515 500-510	a single VLAN (not the record ID from the get action results, but actual VLAN ID), OR range of VLANs (using hyphen for minimum through maximum), OR comma-delimited list of VLANs and/or VLAN ranges
tagId	INTEGER or STRING	150,99	a single tag ID or comma-delimited list of tag ID's

Optional Parameters	None
Example URL	api/v1/api.php?target=vlan&action=addTags&domainId=1&vlan=500-510&tagId=159 api/v1/api.php?target=vlan&action=addTags&domainId=1&vlan=400,406,500-510&tagId=159,160

smartAssign

URL	api.php?target=vlan&action=smartAssign
Description	Finds and enables an unassigned VLAN matching the provided search parameters and optionally renames it.

Returns

Examples

SUCCESSFUL	Return Data: the full domain description, plus the chosen VLAN with its new name (optional) *{"success":1,"message":"VLAN enabled. ","data":{"21":{"id":"21","domain":"Swisscom Demo","attr_6c":"{\"range\":\"E\"}","attr_custom":null,"vlans":[{"id":"46183","vlan":"1808","name":"RESERVED_DEV"}]}}}*
ERROR	*{ "success":0, "message":"error message" }*

Required Parameters

Name	Type	Example	Description
domainId	INTEGER	15	The Id number of the domain you would like to Smart Assign from.

Optional Parameters

Name	Type	Example	Description
tags	INTEGER	5,7,12	A comma-separated list of the Tag Ids being used for the Smart Assign.
name	STRING	CustomerName_13 , RESERVED_DEV	The name that will be assigned to the VLAN matching the given search parameters.

Example URL

api.php?target=vlan&action=smartAssign&domainId=21&name=RESERVED_DEV&tags=5,7,12

3 - SDK

6connect APIv1 - Getting Started with the SDK

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

The 6connect API allows you to access to data and functions of the 6connect web tools. The SDK for PHP or Python will help you get this setup quickly by outlining the requirements, prerequisites and provide sample code.

- 6connect APIv1 - Getting Started with the SDK
  - SDK for PHP
    - Prerequisites
    - Requirements
    - Install the SDK
  - SDK for Python
    - Install the SDK
  - Need More Information?

SDK for PHP

Prerequisites

The API only comes with a licensed 6connect ProVision application. If you would like access to a ProVision license please contact sales@6connect.com.

Create Your API Credentials

To use the 6connect SDK for PHP, you will need a 6connect API Key and Secret Key.

To create your API Key and Secret Key:

- Log into your 6connect instance (hosted or local)
- Click on the Admin icon, and go into the Administration section.
- Click on the "API" tab.
- Select the user from the drop down you want to enable API access for, and click "Generate Keys".
- The API Key and the Secret Key will now appear directly below that.

*Note that generating a new API will automatically revoke an older API Key.

6connect recommends that each user accessing the API have their own API key configured. However, you can alternatively setup API users by functionality or roles. While the platform is flexible, you should follow your organizations security policies.

Important!

Your Secret Key is a secret! Only you and 6connect should ever know this information. It is important to keep it confidential to protect the privacy of your data. Store it securely and never share this key with other users or place it on other systems. Never include the secret key in requests to 6connect, support requests to 6connect, and never e-mail it to anyone. Do not share it outside your organization. No one who legitimately represents 6connect will ever ask you for your Secret Key.

Requirements

Aside from following the prerequisites, you will need a basic understanding of object oriented programming in PHP and the right tools installed on your system to use the API.

Minimum Requirements

- PHP 5.5 or newer.
- PHP JSON and PCRE extensions (XML will be coming soon).
- Curl PHP extension compiled with OpenSSL libraries. Click here for more information on curl.

If you aren't sure what is running on your system, you can create a php page on your system and call phpinfo() and view this page in a browser, or run php -i on the command line.

Install the SDK

Download the file "6connect_ProVision_PHP_SDK_5_1_4.tar" from the attachments list below:

File	Modified

Configure the SDK Security Credentials

- Extract the zipped tar file to a directory.
- Open the api-config.php located in the downloaded SDK files.
- Read through the file and place in your instance name (or path for local installs), API Key and Secret Key information as specified.
- Make sure all files are in the same directory (the core class looks for a config file in the same directory by default).
- Run the sample code api-examples.php!

Important!

You must setup user API access before running the sample. See the previous section "Create Your API Credentials" for more information.

SDK for Python

In Progress

This section is in progress. More information will be added as we improve and refine our new Python SDK!

Install the SDK

Download the file "6c-api-examples-python.zip" from the attachments list below:

File	Modified

Configure the SDK Security Credentials

- Extract the zipped tar file to a directory.
- Open the apiclient.py located in the downloaded SDK files.
- Read through the file and place in your instance name (or path for local installs), API Key and Secret Key information as specified.
- Make sure all files are in the same directory (the core class looks for a config file in the same directory by default).
- Run the sample code api-examples.php!

Important!

You must setup user API access before running the sample. See the previous section "Create Your API Credentials" for more information.

Need More Information?

If you need more general information on the API, see ProVision Developer Tools.

The SDK also contains a README file with other useful information particular to php.

If you need information on methods available via the API, see the individual APIv1 Module Documentation pages:

- API Module - Admin and Audit
- API Module - DHCP
- API Module - DNS
- API Module - IPAM
- API Module - LIR
- API Module - Peering

- API Module - Resource
- API Module - VLAN
- APIv1 SDK
- How Do I...

How Do I...

How Do I... (Use Cases)

ProVision's APIv1 system has been replaced by APIv2, and is now considered deprecated.

If you want to get a jumpstart on common API use cases, you came to the right place! Expand the text areas below for walkthroughs and code samples of API calls...

- How Do I... (Use Cases)
    - IP Blocks - Update Fields
    - IP Blocks - Assign / Subassign
    - DNS
    - DHCP
- Python SDK:
    - IP Blocks

IP Blocks - Update Fields

Context: How do I update the notes field of an IP block using the API in PHP?

1) Start with providing instance information, API key, Secret Key, and DNS Server IP; set up the connection

```
<?php
//
// This file walks through an example of how to look up a block id number
// in ProVision, and then use it to attach a notes field
//
// supply the URL of your ProVision instance, your API key and your Secret key.
$proVisionURL = "https://ops.6connect.com/qa-4.2.2";
$apiKey = "32-5DAYTJEE2TZHOFOB";
$apiSecretKey = "48b278ec873bda473a323dbc467f8669";
// this example uses 6connect's PHP APIClient
require_once("APIClient.php");
// set up the connection
$apiClient = new APIClient($proVisionURL, $apiKey, $apiSecretKey);
```

2) Split the metadata you want to have showing in the notes, and find the block with which it should associate

```
// lets imagine we have some metadata in the following format:
//
$string = "10.1.245.5||DFW7|HP a5820x|its-erp.dfw7.us.corp||";
//
// And we want to insert the Colo, Server type, and hostname into the Notes field of the IP block

// first we split everything up
$pieces = explode("|", $string);
$ip = $pieces[0];
$colo = $pieces[2];
$type = $pieces[3];
$host = $pieces[4];

// then we pull the IP block using the API.
$params = array();
$params['block'] = "$ip/32";                                // the IP block we're looking for, with netmask
// make the call to the IPAM-GET endpoint
$apiResponse = $apiClient->sendRequest('ipam', 'get', $params);
if ($apiResponse->status != 1) {
        echo "Could not pull information for block: $ip/32 !\n";
        die();
}
if (trim($apiResponse->message) == "No blocks found.") {
        echo "IP block $ip/32 not found in ProVison!\n";
```

```
    die();
}

// we now have the ipObject associated with this IP block.  Lets get its block id.
$blockId = $apiResponse->data[0]['id'];
echo "IP block id: $blockId \n";
```

3) Update the block with the notes

```
// it is time to update the block with the new notes.
$notes = "$colo,$type,$host";
$params = array();
$params['id'] = $blockId;
$params['notes'] = $notes;
// make the call to the IPAM-UPDATE endpoint
$apiResponse = $apiClient->sendRequest('ipam', 'update', $params);

// and done!
echo $apiResponse->message . "\n";
```

IP Blocks - Assign / Subassign

Context: I unassigned an IP address and now it's in the Holding Tank. Now I want to assign an IP from the Holding Tank. I don't want to unassign an IP randomly, in case it is allocated to a Resource. What are my options?

There are 3 options:

1) If you know the specific IP, you can use use the ipam-get api call to determine if it is in Holding:

```
/api/v1/api.php?target=ipam&action=get&cidr=1.2.3.4/32

{
  id:1234,
  cidr:"1.2.3.4",
  ...
  resource_name:"Holding"
}
```

2) If you want to show all blocks/IPs in Holding, you can use the following ipam-get API call:

```
/api/v1/api.php?target=ipam&action=get&resourceQuery={"name":"Holding"}
```

3) If you know the block is in Holding, you can issue another ipam-unassign API call to move it from Holding to Available:

```
/api/v1/api.php?target=ipam&action=unassign&block=1.2.3.4/32
```

Context: I need to create a Resource Holder, assign them an IP block, then subassign some IPs out of that block to two new Resource Holders. What does this look like in Python?

We broke this up in a few steps so it's easier to link together.

1) Let's create a Resource Holder called "Ned"

```
query_string    = 'target=resource&action=add&meta[type]=entry&meta[section]=resource-holder&meta[name]=Ned'
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Create Ned resource holder'
print url, "\n"
data = json.load(urllib2.urlopen(url))
ned_resource_id = data['data']['id']
```

2) Now let's add the 213.29.27.0/24 IP block

```
query_string =    'target=ipam&action=add&rir=RIPE&block=213.29.27.0/24'
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
```

```
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Create 213.29.27.0/24 block'
print url, "\n"
data = json.load(urllib2.urlopen(url))
```

3) With the block in the system, we can assign 213.29.27.0/24 to "Ned" the Resource Holder

```
query_string =    "target=ipam&action=directAssign&block=213.29.27.0/24&resourceId=%d" % (ned_resource_id)
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Assign 213.29.27.0/24 block to Ned'
print url, "\n"
data = json.load(urllib2.urlopen(url))
```

4) Since we plan on assigning IPs out of this block, we should enable subassignments for 213.29.27.0/24

```
query_string =    'target=ipam&action=update&block=213.29.27.0/24&allowSubAssignments=true'
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Update 213.29.27.0/24 to allow sub assignments'
print url, "\n"
data = json.load(urllib2.urlopen(url))
```

5) Now let's create a Resource Holder "Tara"

```
query_string =    "target=resource&action=add&meta[type]=entry&meta[section]=resource-holder&meta[name]
=Tara&meta[parent_id]=%d" % (ned_resource_id)
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Create Tara resource holder'
print url, "\n"
data = json.load(urllib2.urlopen(url))
tara_resource_id = data['data']['id']
```

6) To keep it interesting, let's create another Resource Holder "Una"

```
query_string =    "target=resource&action=add&meta[type]=entry&meta[section]=resource-holder&meta[name]
=Una&meta[parent_id]=%d" % (ned_resource_id)
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Create Una resource holder'
print url, "\n"
data = json.load(urllib2.urlopen(url))
una_resource_id = data['data']['id']
```

7) Assign a /28 block from Ned's 213.29.27.0/24 to Tara

```
query_string =    "target=ipam&action=smartAssign&type=ipv4&rir=RIPE&mask=28&&resourceId=%
d&assignedResourceId=%d" % (tara_resource_id, ned_resource_id)
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Assign block from Ned\'s 213.29.27.0/24 to Tara'
print url, "\n"
data = json.load(urllib2.urlopen(url))
```

8) Then assign another /28 block from Ned's 213.29.27.0/24 to Una

```
query_string =    "target=ipam&action=smartAssign&type=ipv4&rir=RIPE&mask=28&&resourceId=%
d&assignedResourceId=%d" % (una_resource_id, ned_resource_id)
query_string    += '&apiKey=' + api_key
hash            = base64.b64encode( hmac.new(api_secret_key, query_string, hashlib.sha256).digest() )
url               = base_url + '?' + query_string + '&hash=' + hash
print 'Assign block from Ned\'s 213.29.27.0/24 to Una'
print url, "\n"
data = json.load(urllib2.urlopen(url))
```

DNS

Context: I need to set up a DNS server using ProVision's API in PHP, create a zone with a few simple records, and push it to the server.

1) Start with providing instance information, API key, Secret Key, and DNS Server IP

```
<?php
//
//
// supply the URL of your ProVision instance, your API key and your Secret key.
$proVisionURL = "https://ops.6connect.com/qa-4.2.2";
$apiKey = "Nnvz8xKZDQUWke6gDxb";
$apiSecretKey = "2YojRbrHnToPZ7cDeFBzcTAvcfMbPVmX";
// this example uses 6connect's PHP APIClient
require_once("APIClient.php");
// set up the connection
$apiClient = new APIClient($proVisionURL, $apiKey, $apiSecretKey);

// save this.  IP of the DNS Server we're creating.
$serverIp = "208.39.106.184";
```

2) Add a DNS server

```
// begin making api calls.  We begin by adding a simple DNS server.
$params = array();
$params['displayName'] = "Example Server";                                                    // the
pretty name of the DNS server
$params['server'] = "208.39.106.184";                                                           // the
IP of the DNS Server
$params['active'] =
1;                                                                                            // whether
or not this server is currently enabled
$params['transferType'] = "SCP";                                      // we are using an ISC Bind server which
we will communicate with via SCP
$params['username'] = "6connect";                                                                //
the username used to SCP zones to this server
$params['password'] = "password";                                                                //
the password used to SCP zones to this server
$params['port'] = 22;                                                 // the port used to SCP zones to this
server
$params['serverType'] = "master";                                                                //
whether this server is a master or a slave
$params['SOA'] = "ns1.dns.6connect.net. hostmaster.6connect.net.";        // the default SOA
$params['remoteDirectory'] = "/tmp/";                                                          //
where to place the zone files on the server
$params['namedConfPath'] = "/tmp/";
// the path to the zones within the configuration file.  Usually the same as 'remoteDirectory'
$params['postCommand'] = "touch /tmp/allFinished";                                        // the command to
execute on the server after the transfer is complete.
// add the server
$apiResponse = $apiClient->sendRequest('dnsServer', 'add', $params);
if ($apiResponse->status == 1) {
        echo "Successfully added DNS Server '" . $params['displayName'] . "'\n";
} else {
        echo "Could not add DNS Server '" . $params['displayName'] . "' !\n";
        die();
}

// now we fetch the id of our newly created server
$params = array();
$apiResponse = $apiClient->sendRequest('dnsServer', 'get', $params);
$data = $apiResponse->data;
for ($i = 0; $i < count($data); $i++) {
        if ($data[$i]['server'] == $serverIp) {
                        // we save the id for later.
                        $serverId = $data[$i]['id'];
                        break;
        }
}
echo "Server Id is: $serverId \n";
```

3) Create a zone

```
// okay, DNS server is set up -- time to create a zone.
$params = array();
$params['zoneName'] = "atestzone.com";                                  // zone name
$params['zoneResourceId'] = 1;                                                  // the owner of the zone; 1 is
default
$apiResponse = $apiClient->sendRequest('zone', 'add', $params);
if ($apiResponse->status == 1) {
    echo "Successfully added DNS Zone '" . $params['zoneName'] . "'\n";
} else {
    echo "Could not add DNS Zone '" . $params['zoneName'] . "' !\n";
    die();
}
// snag the zoneId for later.
$zoneId = $apiResponse->data;
```

4) Add Zone records

```
// Lets add some records to our new zone!
$params = array();
$params['newRecordZoneId'] = $zoneId;                           // parent zone id
$params['newRecordType'] = 'A';                                         // record type
$params['newRecordHost'] = "www";                       // the host field of the record
$params['newRecordValue'] = "1.2.3.4";                  // the value field of the record
$params['newRecordTTL'] = "3600";                       // the value of the TTL field
$apiResponse = $apiClient->sendRequest('record', 'add', $params);
if ($apiResponse->status == 1) {
    echo "Successfully added Record to zone #$zoneId\n";
} else {
    echo "Could not add Record to zone #$zoneId!\n";
    die();
}

$params = array();
$params['newRecordZoneId'] = $zoneId;                   // parent zone id
$params['newRecordType'] = 'A';                         // record type
$params['newRecordHost'] = "dev";                       // the host field of the record
$params['newRecordValue'] = "2.3.4.5";                      // the value field of the record
$params['newRecordTTL'] = "3600";                                       // the value of the TTL field
$apiResponse = $apiClient->sendRequest('record', 'add', $params);
if ($apiResponse->status == 1) {
    echo "Successfully added Record to zone #$zoneId\n";
} else {
    echo "Could not add Record to zone #$zoneId!\n";
    die();
}

$params = array();
$params['newRecordZoneId'] = $zoneId;                   // parent zone id
$params['newRecordType'] = 'A';                         // record type
$params['newRecordHost'] = "cloud";                     // the host field of the record
$params['newRecordValue'] = "3.4.5.6";                  // the value field of the record
$params['newRecordTTL'] = "3600";                       // the value of the TTL field
$apiResponse = $apiClient->sendRequest('record', 'add', $params);
if ($apiResponse->status == 1) {
    echo "Successfully added Record to zone #$zoneId\n";
} else {
    echo "Could not add Record to zone #$zoneId!\n";
    die();
}
```

4) Link the Zone to the new DNS server and push

```
// Okay, we have some zones with records.  Time to link this zone to the new DNS Server
$params = array();
$params['serverId'] = $serverId;                                                 // the server id
$params['zoneId'] = $zoneId;                                                        // the zone id
$params['serverSlave'] = 0;                                                                 // not a slave
zone
```

```
$apiResponse = $apiClient->sendRequest('zoneLinkage', 'add', $params);
if ($apiResponse->status == 1) {
    echo "Successfully linked Zone #$zoneId to server #serverId\n";
} else {
    echo "Could not link Zone #$zoneId to server #serverId!\n";
    die();
}
// now we can push the zone to the server
$params = array();
$params['zoneId'] = $zoneId;                          // the zone id to push
$apiResponse = $apiClient->sendRequest('dnsServer', 'transferSingle', $params);
if ($apiResponse->status == 1) {
    echo "Zone pushed!\n";
} else {
    echo "Could not push zone!\n";
    die();
}
?>
```

DHCP

Context: I need to attach the DHCP module as a child

DHCPv2 functionality is enabled on a particular resource by attaching a DHCP Module as a child. A command to do this is as follows:

```
            [ProVision root]/api/v1/api.php?target=resource&action=add

            data:
meta[type]: dhcp_module
meta[name]: [parent resource id] DHCP Module
meta[parent_id]: [parent resource id]
```

The special resource type “dhcp_module” indicates to ProVision that the DHCP system is enabled for the parent object. The attributes associated with the “dhcp_module” resource govern the DHCP system's behavior.

Updating the attributes of a DHCP Server uses a Resource Update command:

```
[ProVision root]/api/v1/api.php?target=resource&action=update&meta[id]=2178 &meta[type]=dhcp_module&fields
[_dhcp_attributes][]={"type":"ISC","notes":"notes go here","username":"username","port":"port","
config_test":"/etc/init.d/dhcpd configtest","server_stop":"/etc/init.d/dhcpd stop","server_start":"/etc/init.
d/dhcpd start","config_path":"/tmp/dhcpd.conf","option_routers":"192.168.0.0","option_domain_name_servers":"
ns1.6connect.com","option_domain_name":"6connect.com","authoritative":"1","default_lease_time":"600","
max_lease_time":"7200","local_port":"67","log_facility":"local7","password":"password","server_ip":"
192.168.0.1","freeLines":3,"freeLine1":"free line 1","freeLine2":"free line 2","freeLine3":"free line 3"}
```

This command appears rather complicated, but can be broken apart into reasonable pieces. The first section:

```
target=resource&action=update&meta[id]=2178&meta[type]=dhcp_module
```

is familiar from other parts of ProVision. We are updating a resource of type “dhcp_module” whose resource id is 2178. The second section of the command details the update values, starting with

```
 fields[_dhcp_attributes][]=
```

which contains a JSON-encoded string of all the fields specific to a DHCP server's function. When expanded into its full object form it is substantially easier to digest:

```
{
            "type":"ISC",
            "notes":"notes go here",
            "username":"username",
            "port":"port",
            "config_test":"/etc/init.d/dhcpd configtest",
            "server_stop":"/etc/init.d/dhcpd stop",
            "server_start":"/etc/init.d/dhcpd start",
            "config_path":"/tmp/dhcpd.conf",
            "option_routers":"192.168.0.0",
            "option_domain_name_servers":"ns1.6connect.com",
            "option_domain_name":"6connect.com",
            "authoritative":"1",
            "default_lease_time":"600",
            "max_lease_time":"7200",
            "local_port":"67",
            "log_facility":"local7",
            "password":"password",
            "server_ip":"192.168.0.1",
            "freeLines":3,
            "freeLine1":"free line 1",
            "freeLine2":"free line 2",
            "freeLine3":"free line 3"
}
```

This object describes all the most common DHCP server configuration options. For a full explanation of each of the fields, see the Detailed API Specification later in this document.

Please note that the object above must be passed to the DHCP system as a JSON-encoded string. It must be passed into the special "_dhcp_attributes" attribute for it to be functional, as in the example URL.

Context: I need to add a DHCP aggregate

An example command to add a DHCP Aggregate is:

```
[ProVision root]/api/v1/api.php?target=ipam&action=add&block=192.168.0.0/24&rir=
1918&vlan=&tags=&region=&resourceId=1282&allowSubAssignments=true
```

The important part to note is that the IP block is being assigned to resourceId 1282, which corresponds to the DHCP Available resource. The DHCP Available resource is a system-level resource which is used to hold all unassigned DHCP IP addresses. Every instance has its own DHCP Available resource, whose id can be found with the following command:

```
[ProVision root]/api/v1/api.php?target=resource&action=get&slug=dhcp-available
```

New DHCP subnets and hosts draw their IPs from this pool. If there are no IPs in the DHCP Available pool new subnets and hosts will not be able to be created.

DHCP IP aggregates are fetched, updated, split, and deleted using the standard IPAM management API endpoints. Please see the IPAM API Documentation. for details.

Context: I need to add a DHCP Pool

Similar to how the "dhcp_module" resource was created above, the command to create a DHCP Pool is as follows:

```
[ProVision root]/api/v1/api.php?target=resource&action=add&meta[type]=dhcp_pool &meta[name]=New Subnet&fields
[_dhcp_type][]=subnet&fields[_dhcp_pool_attributes][]={"mac":"","rangeStart":"","rangeEnd":"","freeLines":3,"
freeLine1":"Free Line 1","freeLine2":"Free Line 2","freeLine3":"Free Line 3"}
```

The first half of this command is relatively straightforward:

```
target=resource&action=add&meta[type]=dhcp_pool&meta[name]=New Subnet
```

This section informs the API that we wish to create a new, empty “dhcp_pool” resource whose name is “New Subnet.”

```
fields[_dhcp_type][]=subnet&fields[_dhcp_pool_attributes][]={"mac":"","rangeStart":"", "rangeEnd":"","
freeLines":3,"freeLine1":"Free Line 1","freeLine2":"Free Line 2","freeLine3":"Free Line 3"}
```

The second half of the command behaves in a similar manner to the “dhcp_module.” The “_dhcp_pool_attributes” field holds a JSON-encoded string which describes the dhcp_pool resource. When expanded, the JSON string becomes the following object:

```
{
            "mac":"",
            "rangeStart":"",
            "rangeEnd":"",
            "freeLines":3,
            "freeLine1":"Free Line 1",
            "freeLine2":"Free Line 2",
            "freeLine3":"Free Line 3"
}
```

For a full explanation of each of the fields, see the Detailed API Specification.

Please note that the object above must be passed to the DHCP system as a JSON-encoded string. It must be passed into the “_dhcp_pool_attributes” attribute for it to be functional, as in the example URL.

Once a dhcp_pool resource is in the system it can be updated with IP data obtained from the IP Management system. Under DHCPv2, the DHCP system uses all the standard IPAM API endpoints and can make use of both the smartAssign and the directAssign methods. Please see the IPAM API documentation for details.

Context: I need to link a DHCP pool to a DHCP server

An example of building a link between a dhcp_pool and a DHCP Server is:

```
[ProVision root]/api/v1/api.php?target=resource&action=addLink&resource_id1=2178&
resource_id2=1452&relation=dhcpPoolLink
```

The Resource Linkage system controls which DHCP Pools are associated with a given DHCP Server. In the case of linking a DHCP Pool to a DHCP Server, the relation used is “dhcpPoolLink”. This is a directional link, so it is important that resource_id1 and resource_id2 do not get confused.

```
relation:  "dhcpPoolLink"
resource_id1:  the id of the dhcp_module this pool is being linked to
resource_id2:  the id of the dhcp_pool being linked
```

It is very important that resource_id1 not be confused with resource_id2. The link will not function with the values reversed.

To undo the above and break a DHCP Pool link, use the same command but substitute “deleteLink” for the action “addLink”.

```
[ProVision root]/api/v1/api.php?target=resource&action=deleteLink&resource_id1=2178&
resource_id2=2179&relation=dhcpPoolLink
```

Context: I need to push a DHCP config file

Once the server has been configured according to the previous sections, hitting the following API endpoint will trigger a DHCP push:

```
[ProVision root]/api/v1/api.php?target=dhcp&action=push&id=2178
```

The “id” in the above string is the id of the dhcp_module resource attached to the server you whose configuration is to be pushed. The API return payload will contain success or failure codes, as well as a description of any errors which might have occurred.

When a DHCP configuration file is pushed an SSH connection is opened to the configured server using the user, password, and port supplied to the '_dhcp_attributes' attribute on the dhcp_module resource. If the system successfully connects, it will assemble a DHCP configuration from the information given to the dhcp_module's '_dhcp_attribute' attribute and then parse and add in all linked dhcp_pool resources.

After the assembled file has been transferred to the DHCP server it will be placed in the location given by 'config_path' on the dhcp_module, and then the command described in 'config_test' will be run to determine whether or not this new file parses correctly. If 'config_test' is blank or omitted, this step is skipped.

If the file parses correctly the DHCP will be stopped and restarted according to the 'server_stop' and 'server_start' commands on the DHCP module. If there are errors at any point the system backs out, replaces old config files, and reports the errors via the 'message' return field of the API call.

Python SDK:

IP Blocks

Context: How do I create aggregates, get block information, and delete aggregates using the API / python SDK?

```
#!/usr/bin/python
from apiclient import APIClient, APIResponse

# REPLACE WITH CORRECT VALUES FOR YOUR INSTANCE

base_url                = 'https://<ProVision Instance URL>'

api_key                         = '00-ABCDEFGHIJ123456'

api_secret_key        = '0123456789abcdef0123456789abcdef'


# create the APIClient

client = APIClient(base_url, api_key, api_secret_key)



# create aggregate 1.2.3.0/24

target = 'ipam'

action = 'add'
```

```
params = {'block': '1.2.3.0/24', 'rir':'ARIN'}

url = client.get_request_url(target, action, params)

print url

response = client.make_api_call(target, action, params)

print response


# get block 1.2.3.0/24

target = 'ipam'

action = 'get'

params = {'block': '1.2.3.0/24'}

url = client.get_request_url(target, action, params)

print url

response = client.make_api_call(target, action, params)

print response



# delete aggregate 1.2.3.0/24

target = 'ipam'

action = 'delete'

params = {'block': '1.2.3.0/24'}

url = client.get_request_url(target, action, params)

print url

response = client.make_api_call(target, action, params)

print response
```

Portable Gadgets

Portable Gadgets

- Portable Gadgets
  - Overview
    - Global Search:
      - Global Search Option Types:
    - IPAM Search:
      - IPAM Option Types:
    - DHCP Search:
      - DHCP Option Types:
    - Log:
      - More Options:
  - Additional Information:


Overview

ProVision's Portable Gadgets are drop-in code snippets that use the ProVision API to bring in data to other systems or web pages. Portable Gadgets allow for quick data access and increased integration.

Currently, four Gadgets are available: Global Search, IPAM Search, DHCP Search, and Log. Each Gadget comes in various default option types for display style, number of records return, or behavior. Additional client-side style customizations may be made to further integrate the gadget with company styles.


Global Search:

The Global Search Gadget utilizes ProVision's global search API to searching by name string and return ID, Type, and the Name. The search may be limited to specific types (IPAM, Resources, Zones, Records, Contacts, or All Types) if desired.




Global Search Option Types:

Type I.




- Returns 5 records per Type
- Auto Width, height set to 300px

Type II.




- Returns 5 records per Type
- No search input provided
- Fixed size (400px wide x 300px high)

Type III.




- Returns 3 records per Type
- Auto Width, height set to 200px

Type IV.



- No search on load
- Links stay in current window
- Fixed size (400px wide x 200px high)


Type V.



- Type I functionality restyled with CSS


IPAM Search:

The IPAM Search Gadget utilizes ProVision's IPAM API to return ID, CIDR, and Resource Name results searching by an IPAM Resource name string.




IPAM Option Types:

Type I.



- Returns 5 records per Type
- Auto Width, height set to 200px

Type II.




- Returns 3 records per Type
- No search input provided
- Fixed size (400px wide x 200px high)

Type III.




- No search on load
- Links stay in current window
- Auto Width, height set to 300px

Type IV.



- Type I functionality restyled with CSS
- Auto Width, height set to 400px


Type V.



- Customizable Fields
- Auto Width, height set to 300px


DHCP Search:

The DHCP Search Gadget utilizes ProVision's DHCP API to return results of varying types when searching for a name string. The search may be limited to specific types if desired.



DHCP Option Types:

Type I.



- Returns 5 records per Type
- Auto Width, height set to 300px

Type II.




- Returns 3 records per Type
- No search input provided
- Fixed size (400px wide x 200px high)

Type III.



- No search on load
- Links stay in current window
- Returns 5 records per Type
- Auto Width, height set to 300px

Type IV.




- Type I functionality restyled with CSS
- Returns 5 records per Type
- Auto Width, height set to 300px

Log:

The Log Gadget provides detailed information on actions performed in ProVision. Actions may be filtered by Level, Category, Log ID, User, and Time (specific or a range), as well as results-per-page option set. Additional filtering options allow targeting of specific log entries.

Clicking on the blue arrow at the beginning of each log entry shows additional details about that log item.



The following filters and options are available:

Level: Under the "Level" dropdown box, select "All Levels", "Emergency", "Alert", "Critical", "Error", "Warning", "Notice", "Info", or "Debug".

Category: Under the "Category" dropdown box, select "All Categories", "User", "IPAM", "Resource", "Resource Holder", "DNS", "Peering", "Assistant", "API", "NTP", "Device", or "Reporting".

Results per page: In the "Results per page" text box, type the desired number of log entries to see per page. By default, this value is set to 100.

Search: Type a search string, such as the name of a resource, then click the "Search" button.

More Options:

Additional detailed filter and search options are available under the "More Options" link.

Log ID: Retrieve a specific log entry from its log_id parameter.

IP: Search by IP of the machine that created the event in the log.

Username: Filter logs by ProVision username, or by "Unknown" user.

Time: Filter log entries by exact time created. Must be in datetime format (2016-08-14 16:41:18).

Time Minimum: The earliest day and time of log entries to show in results. Must be in datetime format (2016-08-14 16:41:18).

Time Maximum: The latest day and time of log entries to show in results. Must be in datetime format (2016-08-14 16:41:18).

Additional Information:

- Getting Started With Portable Gadgets
- Portable Gadget Customization

Getting Started With Portable Gadgets

Getting Started

- Getting Started
  - Adding a Portable Gadget to a Web Page
    - Requirements
    - Before You Begin
    - Step 1: Reference dependency files
    - Step 2: Create Gadget
    - Step 3: Initialize the Gadget
      - a) Preparing the settings
      - b) Initialize the gadget HTML element
    - Basic Page Example

Adding a Portable Gadget to a Web Page

Requirements

Setting up Portable Gadgets requires a ProVision instance URL and valid API credentials (API key and secret key), as well as some familiarity with HTML, CSS, and Javascript.

Before You Begin

Before you begin, make sure you have access to the source code for the web page on which you want the portable gadget to appear, or create a simple new web page for testing purposes with minimal tags like this (with the location of steps included as comments):

```
<html>
        <head>
                <!-- STEP 1 WILL GO HERE -->

                <!-- STEP 3a WILL GO HERE -->
                <!-- STEP 3b WILL GO HERE -->
        </head>
        <body>
                <!-- STEP 2 WILL GO HERE -->
        </body>
</html>
```

Step 1: Reference dependency files

Include the following two scripts the <HEAD> block. They should reference your provision installation.

In this example, "https://cloud.6connect.com/6c_123" is the root folder of a 6connect installation, so replace that with your own 6connect instance URL.

```
<script type='text/javascript' src="https://cloud.6connect.com/6c_123/portable/init.js"></script>
<link rel="stylesheet" type="text/css" href="https://cloud.6connect.com/6c_123/portable/css/provision-
portable.css">
```

Step 2: Create Gadget

Place the html tag for your gadget where you want it to appear in the page <body>, and give it a unique id.

Your gadget should be an html element in your page body (any contents inside the element will be removed). This example has a div referred to as "gadget" (as the ID).

```
<!-- provision gadget -->
<div id="gadget"></div>
```

Step 3: Initialize the Gadget

a) Preparing the settings

First, a settings variable must be prepared with the details of the gadget.

It must have the following keys for the provision url and api keys:

- provision_location
- provision_api_key
- provision_secret_key

...as well as the name of one of the gadget to load:

- search -- does a search with the global search API
- dhcp -- does a search with the DHCP API
- ipam -- does a search with the IPAM API
- pv-logs – details actions taken in ProVision.

Here is an example for a search gadget, loading with the search term "6connect". By default it will load up to five results per type.

```
<script type='text/javascript'>
var settings = {
provision_location: "https://cloud.6connect.com/6c_123",
provision_api_key: "00-ABCDEFGHIJKLMN00",
provision_secret_key: "00abcd11ef22ghij3300klmno123",

search: "6connect",
};
</script>
```

Here is an example to load as an IPAM gadget, with an option to limit results to 10 records:

```
<script type='text/javascript'>
var settings = {
provision_location: "https://cloud.6connect.com/6c_123",
provision_api_key: "00-ABCDEFGHIJKLMN00",
provision_secret_key: "00abcd11ef22ghij3300klmno123",

ipam: "6connect",
limit: 10
};
</script>
```

An example with the DHCP gadget:

```
<script type='text/javascript'>
var settings = {
provision_location: "https://cloud.6connect.com/6c_123",
provision_api_key: "00-ABCDEFGHIJKLMN00",
provision_secret_key: "00abcd11ef22ghij3300klmno123",

dhcp: "Test",
};
</script>
```

b) Initialize the gadget HTML element

The gadget will initialize when scripted to do so with the provision() command. For the example html in section II, we can instantiate this gadget by running the following (as long as settings was prepared):

```
<script type='text/javascript'>
provision('#gadget', settings)
</script>
```

The first parameter targets the html element that is the gadget, using jQuery's selector format. In this case, it is an element with the ID "gadget".

Basic Page Example

Here is a simple example html page with a search gadget. In this example, a default search term of "6connect" is included, and the return limited 10 records.

```
<html>
        <head>
                <script type='text/javascript' src="https://cloud.6connect.com/6c_123/portable/init.js"><
/script>
                <link rel="stylesheet" type="text/css" href="https://cloud.6connect.com/6c_123/portable/css
/provision-portable.css">
                <script type='text/javascript'>
                        var settings = {
                                provision_location: "https://cloud.6connect.com/6c_123",
                                provision_api_key: "00-ABCDEFGHIJKLMN00",
                                provision_secret_key: "00abcd11ef22ghij3300klmno123",

                                search: "6connect",
                                limit: 10
                        };
                        provision('#search_gadget', settings);
                </script>
        </head>
        <body>
                <div id="search_gadget"></div>
        </body>
</html>
```

Portable Gadget Customization

Customizing Portable Gadgets

- Customizing Portable Gadgets
- Customization Options
    - Required Settings:
    - Optional Settings:
- Sample CSS Customization
    - Alternating Row Formatting:

Customization Options

Portable Gadgets come with both built-in customization options as well as the ability to edit styles locally through CSS.

Required Settings:

The required fields are:

provision_location: the location of the provision installation
provision_api_key: available from the Admin API Tab in ProVision
provision_secret_key: available from the Admin API Tab in ProVision

Other required fields (by gadget)

```
Search:
    search: "string"
IPAM:
   ipam:  "string"
DHCP:
   dhcp:  "string"
```

Where, in each case, "string" is the search term used on the initial loading of the gadget. If it is an empty string (literally, ""), then gadget will load without a pre-defined search.

Optional Settings:

These settings must be included as parameters when initializing the gadget. See Getting Started With Portable Gadgets.

limit: positive integer, or -1

The record return limit of the gadget. In some gadgets (search and DHCP) there are multiple types, so it limits per type. The default limit, if this option is not provided, is 5. If you specify limit a -1 (or basically any negative number), it will not enforce a limit.

links_change_window: true


setting this to true (not string "true" but actual true type in javascript) will make links change the current window. The default behavior (not having this option or false), would have links open a new tab.

interact: false

By default, there will be a search box on all these gadgets. But with this option set to false (again, using false not string "false") will remove that box so search cannot be changed.

Sample CSS Customization

Alternating Row Formatting:




```
<style>
.pg-subtitle {
    color: lightslategrey;
    font-size:1.4em;
    font-weight: bold;
}

.pg-field-name a:hover {
    text-decoration: none;
    color: white;
    background-color: gray;
}

.pg-results tr:nth-child(2n+1) {
    background: white;
}
.pg-results tr:nth-child(2n+0) {
    background: lightgray;
}
</style>
```

Reverse API


Reverse API

- Reverse API
  - Overview
  - API Call Formatting
  - Reverse API Detail:

Overview

Reverse API Tools - Beta

ProVision's Reverse API calls and UI elements allow for integration with outside APIs to improve workflow and create custom display content. In the ProVision user interface, the Reverse API page allows for endpoints to be built and provides a text editor to create presentation JavaScript commands. This JavaScript presentation code is then displayed in the Reverse API Gadget.



Using the ProVision Reverse API (rAPI), you can perform these same actions and customize to meet your specific needs outside of the ProVision UI.

API Call Formatting

Reverse API (rAPI) calls are made to hit a user-defined URL or command line program. If the rAPI type is set to 'external,' the system makes a HTTP request. If the rAPI type is set to 'local', it executes the call on the command line of the local machine. In both cases the call is first customized with the attributes of the resource supplied to the execute function. This allows a single rAPI endpoint to serve a wide array of individual resources, fetching only information relevant to that particular resource without having to store anything locally.

rAPI calls are formatted thusly:

```
http://observium.tcp0.com/graph.php?
height=200&width=265&type=device_bits&legend=no&username=api&password=password&device={observium-id}
```

The interesting part about this URL is the bit in curly-braces: {observium-id}. When this call is made, the system decodes the URL by searching for everything within curly-braces and replaces it with data pulled from a resource. A rAPI call may have as many or as a few curly-brace replacement targets as is needed. Each curly-brace target will be replaced with exactly one resource attribute. All targets must be successfully replace for the command to succeed.

For example, when this rAPI call is decoded with information from the 1-dev resource, the decoded call is as follows:

```
http://observium.tcp0.com/graph.php?
height=200&width=265&type=device_bits&legend=no&username=api&password=password&device=21
```

The rAPI service then pulls the data from that URL, pairs it with its presentation code, and returns it via the execute endpoint. If a user attempted to execute the above call on a resource which did not have the “observium-id” property, the execute endpoint would return the following error: "Reverse API Call references token 'observium-id', which does not exist in resource."

All curly-brace calls reference a resource attribute by their unique resource slugs. The list of available resource attributes can be customized using the existing resource system endpoints.
Curly-brace targets may take the form {parent.observium-id}. The “parent.” prefix indicates that in decoding this particular brace, the attributes of the resource's parent are to be used.

Reverse API Detail:

For detail on the Reverse API calls and parameters, proceed to Reverse API - Detail.

Reverse API - Detail

- Reverse API Module
  - reverseAPI_add
  - reverseAPI_get
  - reverseAPI_delete
  - reverseAPI_update
  - reverseAPI_execute

Reverse API Module

reverseAPI_add

URL	/api/v1/api.php?target=reverseAPI&action=add
Description	Add a Reverse API Endpoint
Returns	**Examples:** SUCCESSFUL: performs ResourceAPI->Get operation to return the newly-created entry, thus will appear similar to a "Get" return: {"success":1,"message":"Reverse API endpoint added","data":{"id":"1","name":"TestPoint2","type":"local","created_by":"user","last_modified":"2015-04-01 12:24:57","call":"http:\/\/www.test.com?api.php","presentation":null}} ERROR: {"success":0, "message":"error message"}

Required Parameters

Name	Type	Example	Description
name	STRING	TestPoint2	The name of the rAPI object
type	STRING	local	The type of the rAPI object. Valid settings are 'local' and 'external'.
call	STRING	http://www.test.com?api.php&server={serverId}	The URL or the system path which is first decoded against a resource and then hit when this rAPI endpoint is invoked.

Optional Parameters

Name	Type	Example	Description
presentation	STRING	endpoint = function(data, outputDiv) {console.log(outputDiv);};	The Javascript code used to display this endpoint on a resource page.

Example URL	/api/v1/api.php?target=reverseAPI&action=add&name=TestPoint2&type=local&call=http://www.test.com?api.php&server={serverId}

reverseAPI_get

URL	/api/v1/api.php?target=reverseAPI&action=get
Description	Fetches one or more Reverse API endpoints
Returns	**Examples:**

SUCCESSFUL	An array of ReverseAPI objects: {"id":"535","name":"Observium RAM Graph","type":"external","created_by":"user","last_modified":"2015-03-18 09:16:49","call":"http:\/\/observium.tcp0.com\/graph.php?height=200&width=265&type=device_ucd_memory&legend=no&username=api&password=password&device={observium-id}","presentation":"endpoint = function(data, outputDiv) {\n\n outputDiv.css('font-family','Helvetica, Arial, sans-serif;');\n\n\toutputDiv.append(\" RAM Usage<\/div>\");\n\n\tif (data == \"\") {\n\t\toutputDiv.append(\" No data returned<\/div>\");\n\t\treturn;\n\t}\n\n\toutputDiv.append('<div style=\"margin-left:-18px;margin-top:-3px;\"><\/div>');\n};"}
ERROR	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
id	INTEGER	The id of the rAPI objectSt
name	STRING	The name of the rAPI object
type	STRING	The type of the rAPI object
created_by	STRING	What user created the rAPI object
last_modified	DATETIME	When this rAPI object was last changed
call	STRING	The URL or the system path which is first decoded against a resource and then hit when this rAPI endpoint is invoked.
presentation	STRING	The Javascript code used to display this endpoint on a resource page.

Required Parameters: None

Optional Parameters:

Name	Type	Example	Description
id	INTEGER	535	The id of the rAPI objectSt
name	STRING	TestPoint2	The name of the rAPI object
type	STRING	external	The type of the rAPI object. Valid settings are 'local' and 'external'.
created_by	STRING	user	The user who created the rAPI object

Example URL: /api/v1/api.php?target=reverseAPI&action=get&name=TestPoint2

reverseAPI_delete

URL: /api/v1/api.php?target=reverseAPI&action=delete

Description: Delete a rAPI endpoint

Returns:

Examples:

SUCCESSFUL	{"success":1,"message":"Reverse API endpoint deleted"}
ERROR	{"success":0, "message":"error message"}

Required Parameters:

Name	Type	Example	Description
id	INTEGER	535	The id of the rAPI objectSt

	name | STRING | TestPoint2 | The name of the rAPI object
Optional Parameters	None
Example URL	/api/v1/api.php?target=reverseAPI&action=delete&id=535&name=TestPoint2

reverseAPI_update

URL	/api/v1/api.php?target=reverseAPI&action=update
Description	Update an existing rAPI endpoint
Returns	**Examples:** SUCCESSFUL: ResourceAPI->Get updated object, thus will appear the same as a "Get" return: {"id":"535","name":"Observium RAM Graph","type":"external","created_by":"user","last_modified":"2015-03-18 09:16:49","call":"http:\/\/observium.tcp0.com\/graph.php?height=200&width=265&type=device_ucd_memory&legend=no&username=api&password=password&device={observium-id}","presentation":"endpoint = function(data, outputDiv) {\n\n outputDiv.css('font-family','Helvetica, Arial, sans-serif;');\n\n\toutputDiv.append(\" RAM Usage<\/div>\");\n\n\tif (data == \"\") {\n\t\toutputDiv.append(\" No data returned<\/div>\");\n\t\treturn;\n\t}\n\n\toutputDiv.append('<div style=\"margin-left:-18px;margin-top:-3px;\"><\/div>');\n};"} ERROR: {"success":0, "message":"error message"}
Required Parameters	**Name** | **Type** | **Example** | **Description** id | INTEGER | 535 | The id of the rAPI objectSt
Optional Parameters	**Name** | **Type** | **Example** | **Description** name | STRING | TestPoint2 | The name of the rAPI object type | STRING | external | The type of the rAPI object. Valid settings are 'local' and 'external'. call | STRING | http://www.test.com?api.php&server={serverId}&action=12 | The URL or the system path which is first decoded against a resource and then hit when this rAPI endpoint is invoked. presentation | STRING | endpoint = function(data, outputDiv) {console.log (outputDiv);}; | The Javascript code used to display this endpoint on a resource page.
Example URL	/api/v1/api.php?target=reverseAPI&action=update&id=535&name=TestPoint2

reverseAPI_execute

URL	/api/v1/api.php?target=reverseAPI&action=execute
Description	Decodes a rAPI call against a Resource, executes the resulting string, returns the result along with the presentation code
Returns	**Examples:** SUCCESSFUL: The result of a rAPI call customized for the supplied resource

	{“data”:”\u0017\u00fbD","presentation":"endpoint = function(data, outputDiv) {\n\n\toutputDiv.css('font-family','Helvetica, Arial, sans-serif;');\n\n\toutputDiv.append(\" Port Traffic<\/div>\");\n\n\tif (data == \"\") {\n\t\toutputDiv.append(\" No data returned<\/div>\");\n\t\treturn;\n\t}\n\n\toutputDiv.append('<div style=\"margin-left:-15px;margin-top:-3px;\"><\/div>');\n};"}}
ERROR	{"success":0, "message":"error message"}

Return Detail:

Name	Type	Description
data	MIXED	The result of the reverse API call. Could be binary data, could be JSON.
presentation	STRING	The presentation javascript which pairs with this rAPI call

Required Parameters

Name	Type	Example	Description
id	INTEGER	537	The id of the rAPI objectSt
resource_id	INTEGER	2245	ID of the resource

Optional Parameters: None

Example URL: /api/v1/api.php?target=reverseAPI&action=execute&id=537&resource_id=2245

Toolkit

Toolkit Modules

6connect provides customers with additional CLI modules for ProVision power users in the /tools directory. These tools are outlined below.

- Toolkit Modules
  - Users / Permissions
    - Add User
    - Rebuild Permissions
  - DNS
    - Audit Forward DNS
    - Audit Reverse DNS
  - Database
    - Database Analyzer
    - Database Reset
  - Import
    - IPPlan Importer:
    - PHPIPAM Importer:
  - Internal 6connect Tools
  - Additional Information:

Users / Permissions

Add User

File: add-user.php

Description: Adds a new user to 6connect Provision. Especially useful if an admin has locked themselves out and has access to the local server, or for adding additional credentials to a new local installation. The tool walks through the required information.

Command: “php add-user.php"

Rebuild Permissions

File: rebuild-permissions.php

Description: Will rebuild the cached permissions for the specified resource id. Should not be used outside of a db reset, or a corruption of the permissions cache.

Command: “php rebuild-permissions.php"

DNS

Audit Forward DNS

File: audit_forward_dns.php

Description: Audits the forward DNS for a specified IP block, comparing the DNS records in 6connect to a publicly facing server. Will provide detail output showing resolved records, if records conflict and why.

Command: “php audit_forward_dns.php”

Options:

-v Sets verbose mode to print debug information

-a <message key> run as asycronous request (note: you should not use this, it is for the GUI)

-b <ip block> IP block in cird notation to audit dns for.

-n <name server> FQDN or IP address of specific name server to resolve records against. Defaults to 8.8.8.8.

-h print help

Audit Reverse DNS

File: audit_reverse_dns.php

Description: Audits the reverse DNS for a specified IP block, comparing the DNS records in 6connect to a publicly facing server. Will provide detail output showing resolved records, if records conflict and why.

Command: "php audit_reverse_dns.php"

Options:

-v Sets verbose mode to print debug information

-a <message key> run as asycronous request (note: you should not use this, it is for the GUI)

-b <ip block> IP block in cird notation to audit dns for.

-n <name server> FQDN or IP address of specific name server to resolve records against. Defaults to 8.8.8.8.

-h print help

Database

Database Analyzer

File: databaseAnalyzer.php

Description: Takes two MySQL dump files for input, one thought to be the “good” database, and one the “bad” to compare against each other for differences. Is used internally to audit database changes after an upgrade to ensure all changes for the upgrade were committed by comparing against the template database for that release. Can be useful for diagnosing missed upgrades, or other database issues. Could be used on any set of databases, and is not 6connect specific.

Command: "php databaseAnalyzer.php"

Options:

-v Sets verbose mode to print debug information

-a <database name> Required - the 'good' database to comapre against.

-b <database name> Required - the 'bad' database to check for incorrect information.

-g <globals file> Optional - The script will automatically look to the globals.php file for database connection information. This option can be used to specify and alternate file, or file location.

-h print help

Database Reset

File: dbReset.php

Description: This tool resets portions or all of the database to factory defaults. Can reset only IP, DNS, or Resource information or all all three. If erasing resource information, you need to enter a user to assume global admin permission to log back in with. Even if this isn’t specified, the add-user tool can be used to add a user back after. We recommend creating a backup prior to using this tool, and only use if you are sure you know what you are doing!

Command:"php dbReset.php"

Options:

-v Sets verbose mode to print debug information

-i Erases any and all IP information. Tags, regions, and other IPAM preference settings are not changed.

-d Erases any and all DNS information including zones, records, and archive data. Does not affect DNS perference settings, or configured DNS servers.

-r Resets all resource information back to the factory defaults, and removes all associated information (user groups, files, etc).

-u <user name> User name that will have Global Admin permissions restored on the default resources

-h print help

Import

IPPlan Importer:

File: ipplan_import.php

Description: The IPPlan Importer is a command-line tool to import IPs from an IPPlan database into ProVision. Details on how to use this tool are available at IPPlan Importer.

Command: "php ipplan_import.php"

Options:

For options, refer to IPPlan Importer.

PHPIPAM Importer:

File: phpipam_import.php

Description: Generates a CSV or imports data from a phpipam instance

Command: "php phpipam_import.php"

Options: Contact 6connect Support if you have any questions

Internal 6connect Tools

The following tools contained in the /tools folder are for 6connect internal use only:

File: scp_wrapper.php - Internal 6connect tool, not meant for command line use.

File: s64_restart_master - Internal 6connect tool, not meant for command line use.

File: s64_restart_slave - Internal 6connect tool, not meant for command line use.

File: async_import.php - Internal 6connect tool, not meant for command line use.

File: importBigDump.php - Internal 6connect tool supporting IPPlan Importer, not meant for command line use.

File: ipplan_functions.php - Internal 6connect tool supporting IPPlan Importer, not meant for command line use.

File: dns_transfer_server.php - Internal 6connect tool, not meant for command line use.

File: observium_import.php - Internal 6connect tool, not meant for command line use.

File: digAndLookup.php

File: pullLAMPInfo.php

Additional Information:

- IPPlan Importer

IPPlan Importer

IPPlan Importer

- IPPlan Importer
  - Overview
  - Before you begin:
  - Connector Method (Results in .csv files only):
  - Importer Method (Results in full import):
    - Run & Set the RIR:
  - Additional Run Options:
    - Load SQL Without Importing
    - Generate CSV Without Loading SQL
    - Generate CSV No Overwrite
    - Generate CSV With RIR
    - Run Only Import
    - Run Import No Overwrite

Overview

The IPPlan Importer is a command-line tool to import IPs from an IPPlan database into ProVision. This tool can be used via two approaches: generating .csv files via the tool only, then using the ProVision IP Import UI to import the csv files (Connector), or as a full command-line import solution, bypassing the ProVision UI entirely (Importer).

Options:

1) Generate .csv files to use with the IP Import - Upload/Import from CSV tool through the ProVision UI.

2) Import IPs directly into ProVision without accessing the UI.

Before you begin:

You will need:

- A MySQL export of IPPlan created from mysqldump, located on the same server / accessible from the IPPlan Importer tool.
- Administrative access to your ProVision instance folder

Accessing the Tool and Showing Help Instructions:

The tool is located in tools/ipplan_import.php. A help document is provided listing example commands and detailed situation-specific options.

To execute it, you must preface it with "php" program. From from your instance's root folder, the command would be:

"php tools/ipplan_import.php --help"

If you are in the tools folder, the command would be:

"php ipplan_import.php --help"

This will bring up the help / instruction document. It is also provided below.

Help File Text

```
usage: php ipplan_import.php [options] <SQL dump file>

Examples:

For creating CSV's for use in ProVision IP importer:
    php ipplan_import.php filename.SQL --csv

For creating CSV's, but do not load SQL file if one already has been:

    php ipplan_import.php filename.SQL --csv --no-overwrite
```

```
For importing data from SQL dump. Note that you must specify RIR:
    php ipplan_import.php filename.SQL --rir=1918

For importing data from SQL dump, if one hasn't been loaded already:
    php ipplan_import.php filename.SQL --rir=1918 --no-overwrite

Caution: By default, SQL dump will be loaded into database 'provision_import_ipplan'. If database already
exists it will be dropped, unless --no-overwrite option is specified.

options:

  --only-import - Skip loading SQL file. Instead, import existing data in database 'provision_import_ipplan'.

  --only-sql - Load SQL dump into database 'provision_import_ipplan'. --only-import can be run at a later
time to use loaded database.

  --rir=RIR - (required for import) RIR for IP's

  OPTIONS IF LOADING SQL FILE:

  --no-overwrite - Load SQL dump only if database 'provision_import_ipplan' is currently non-existent.
Otherwise, drop existing database.

  OPTIONS IF IMPORTING DATA:

  --csv - generate CSV's instead of importing directly to ProVision.
```

Connector Method (Results in .csv files only):

This method creates .csv files that you can use with the IP Import - Upload/Import from CSV tool through the ProVision UI.

1. From the tools/ folder, run the tool with the --csv option. Be sure to reference your sql export file name and location:

   "php ipplan_import.php ../ipplanv6.sql --csv"

   (where '../ipplanv6.sql' is the path to your SQL file)
   This will generate two files: ipplan_aggregates.csv and ipplan_hosts.csv. Both can be used to import in the IP import section of ProVision.
2. Copy / Download the generated .csv files to a browsable directory on your local machine, to be accessed by the ProVision UI.
3. Through the ProVision UI, import the ipplan_aggregates.csv file as described in IP Import - Upload/Import from CSV.
4. Through the ProVision UI, import the ipplan_hosts.csv file as described in IP Import - Upload/Import from CSV.

Note that you must import ipplan_aggregates first. into IP Import - Upload/Import from CSV to create the aggregates ipplan_hosts.csv will use.
Then, import ipplan_hosts.csv as described in IP Import - Upload/Import from CSV.

Importer Method (Results in full import):

This method has the tool process the import task. Using this case, you must set the RIR in the command line for all of the IP's.

Run & Set the RIR:

1. From the tools/ folder, run the tool with the --rir option, referencing your SQL file location:

   "php ipplan_import.php ../ipplanv6.sql --rir=1918"
   (where '../ipplanv6.sql' is the path to your SQL file)

This will load your IPPlan database file into your mysql server and then import the hosts into ProVision. They will each be given the RIR you specified, as well as this text in the Notes field: 'IPPlan import'

The import may need to run for a number of minutes, depending on the size of your data. For reference, an import of 2100 hosts inside of 150 aggregates took approximately 10 minutes to complete during our testing.

Additional Run Options:

Additional run options for various combination of conditions are detailed below. The command is the text within the quotes only.

Load SQL Without Importing

You can load the SQL file, but NOT run an import, with the --only-sql option (feel free to include --no-overwrite option as well in case you don't want to overwrite a prior loaded SQL file):

"ipplan_import.php ../ipplanv6.sql --only-sql"

"ipplan_import.php ../ipplanv6.sql --only-sql --no-overwrite"

Generate CSV Without Loading SQL

If you have already loaded the sql file previously, you can generate CSV files without having to load the SQL file:

"ipplan_import.php --only-import --csv"

Generate CSV No Overwrite

If you want to just generate CSV files without re-loading the database file, you can as well:

"ipplan_import.php ../ipplanv6.sql --no-overwrite --csv"

Generate CSV With RIR

You can also generate csv files with the rir option:

"ipplan_import.php ../ipplanv6.sql --no-overwrite --csv --rir=1918"

Run Only Import

If you have already loaded your IPPlan database with the tool before, you can do --only-import:

"php ipplan_import.php --rir=1918 --only-import"

Run Import No Overwrite

If you are not sure whether you have already loaded your IPPlan database with the tool before, you can specify --no-overwrite to NOT load the sql file if it was loaded already, or do load if it wasn't:

"ipplan_import.php ../ipplanv6.sql --rir=1918 --no-overwrite"

CLI (Alpha)

Command Line Interface - ALPHA

- Command Line Interface - ALPHA
  - Overview
  - CLI Commands (ALPHA)

Overview

The command line interface for ProVision is a beta feature that has been release for feedback.

How to Access the CLI from your browser

When logged into ProVision via a web browser, use the key combination "**Control+Shift+S**" or "**Control+Shift+~**" to access/close the CLI

CLI Commands (ALPHA)

CLI Help

When in the CLI, type:

```
ipam man
```

for sample commands and syntax

Currently, the CLI supports the following commands:

```
ipam <command> [-t] [<cidr>] [<resource name>] [<args>]

    show:     show details for a block. Examples:

                  - "ipam show 10.0.0.0/8" will show details for the block 10.0.0.0/8

                  - "ipam show holding" will show details for all blocks in the Holding Tank

                  - "ipam show "<resource name>"" will show details for all blocks assigned to <resource
name>


    add:      add a block. ex: "ipam add 192.168.0.0/24"


    update:   update attributes for a block. ex: ipam update 192.168.0.0/24 --vlan=100 tags=VM,Dev


    assign:   assign a block to a resource. ex: ipam assign 192.168.0.0/24 "<resource name>"



    assign:   smart assign a block to a resource. ex: ipam assign --mask=24 --rir=ARIN --type=ipv4
"<resource name>"


    unassign: reclaims a block from a resource and places it in the Holding Tank. If the block is already in
the holding tank, reclaims it an makes it available.
```

Resource Concepts 1

Overview

In Provision, the Resource System (RS) is an expression of object-oriented programming. In this context, the term “resource” is equivalent to the term “object”, where an object is an instance of a class. Traditionally in OOP, there is an Object class that is the root of the class hierarchy. In the RS, the Resource class is the root class. Every class in the system has Resource as a superclass and all resource objects implement the methods of that class.



The diagram above shows examples of resource sub-types. The items on a green or blue background are types of resources; they each have their own corresponding Class. An item on a yellow background is an example of an object that could have been instantiated from the class (resource type) that it's part of.

Additional Information:

- Resource Classes
- The Database Layout
- Asset System

Resource Classes Doc

Classes

> "A class--the basic building block of an object-oriented language such as Java--is a template that describes the data and behavior associated with instances of that class. When you instantiate a class you create an object that looks and feels like other instances of the same class."
>
> *Mary Campione and Kathy Walrath, The Java Tutorial: Object-Oriented Programming for the Internet, The Java Series (Reading, Mass.: Addison Wesley, 1996)*

- Classes
  - Class Resource
    - Properties
  - Examples
    - 1 - PHP
    - 2 - API request

Class Resource

```
class Resource {
    public int    $id;
    public string $name;
    public string $slug;
    public string $type;
    public int    $parent_id;
    public int    $category_id;

    protected array $attr   = array();
    protected bool  $loaded = FALSE;

    public object get_attr( string $key );
    public void   set_attr( string $key, object $value );
    public bool   loaded();
}
```

Properties

As you can see from the database layout, the public properties of the Resource class are all part of the main **resource** table. The two protected properties **attr** and **loaded** are created at runtime. There are many situations where only the core information is required. To improve performance, attribute data is ignored when it is not required. Attributes are stored in the database as longtext; non-primitive types (such as arrays) are serialized and stored as a string.

```
$attr
A key-value store of the attributes that exist in the resource_attr table.

$loaded
A boolean value which is used to indicate whether or not the attributes have been loaded.
```

Why do some attributes have names that start with an underscore?

This is the convention for storing metadata. Most attributes are for storing data that is created by the user and is available to be directly edited by the user. When we want to store system data, configuration options, or just data that isn't meant for human consumption - we store it as metadata. An attribute is identified as being metadata by the convention of starting the name/key of the attribute with an underscore character (e. g. _meta). If you are interfacing with the API, you will frequently come across metadata. You're welcome to modify the metadata of a resource (if you know what you're doing) or add metadata attributes for known metadata keys, but you shouldn't create your own attributes with keys that begin with an underscore. Future versions of ProVision will use new metadata keys without warning, and if there is a naming conflict, your data could be lost.

Examples

These examples show the different methods that can be used to find and load a Resource object. They also show different data structures that are used to represent the object.

1 - PHP

Internal code example

⚠

To help users better understand how ProVision works, some of the examples in this documentation are of internal processes. They can contain code that only works when used as part of the core system and thus is not applicable to 3rd party development. The API is currently the only way for external tools to integrate with ProVision. Any example that contains internal code should be clearly labeled. Some common characteristics of these examples are code that doesn't use the API and code written in PHP (most example code will be in JavaScript).

This example uses the ResourceQuery class to find a resource object and then prints the result. It is included to show the similarity between finding a resource via the API and what happens under the hood.

```
$params = array(
    'slug' => 'tlr'
);
$resourceQuery = new ResourceQuery();
$resource = $resourceQuery->query($params);

var_dump($resource);
/*
array (size=1)
  0 =>
    object(Resource)[27]
      protected 'id' => string '1' (length=1)
      protected 'name' => string 'TLR' (length=3)
      protected 'slug' => string 'tlr' (length=3)
      protected 'type' => string 'resource' (length=8)
      protected 'parent_id' => null
      protected 'category_id' => null
      protected 'attr' =>
        array (size=0)
          empty
      protected 'loaded' => boolean true
*/
```

2 - API request

This is a standard API request, the request data is urlencoded and the result is JSON

/api/v1/api.php?target=resource&action=get&slug=TLR

```
{
  "success": 1,
  "message": "Search successful",
  "data": [
    {
      "id": "1",
      "name": "TLR",
      "slug": "tlr",
      "type": "resource",
      "parent_id": null,
      "category_id": null,
      "attr": {}
    }
  ]
}
```


Database Layout 1

Database Layout

Details of the database and tables used by the RS are not necessary and should have no bearing on usage or API based development. However, a visualization of these tables may help some users better understand how the RS works, so they are provided below.

- Database Layout
  - Figure
  - Relations
  - Structure in SQL

Figure



Relations

`resource`.`category_id` -> `resource`.`id`

`resource`.`parent_id` -> `resource`.`id`

`resource_attr`.`resource_id` -> `resource`.`id`

Structure in SQL

resource

```
--
-- Table structure for table `resource`
--
CREATE TABLE IF NOT EXISTS `resource` (
`id` int(11) NOT NULL,
  `name` text NOT NULL,
  `slug` varchar(100) NOT NULL,
  `type` varchar(20) NOT NULL,
  `parent_id` int(11) DEFAULT NULL,
  `category_id` int(11) DEFAULT NULL,
  `date` timestamp NOT NULL DEFAULT CURRENT_TIMESTAMP
) ENGINE=InnoDB  DEFAULT CHARSET=utf8 AUTO_INCREMENT=1115 ;
--
-- RELATIONS FOR TABLE `resource`:
--   `category_id`
--       `resource` -> `id`
--   `parent_id`
```

```
--       `resource` -> `id`
--
--
-- Indexes for dumped tables
--
--
-- Indexes for table `resource`
--
ALTER TABLE `resource`
 ADD PRIMARY KEY (`id`), ADD UNIQUE KEY `slug` (`slug`), ADD KEY `category_id` (`category_id`), ADD KEY
`parent_id` (`parent_id`);
--
-- AUTO_INCREMENT for dumped tables
--
--
-- AUTO_INCREMENT for table `resource`
--
ALTER TABLE `resource`
MODIFY `id` int(11) NOT NULL AUTO_INCREMENT,AUTO_INCREMENT=1115;
--
-- Constraints for dumped tables
--
--
-- Constraints for table `resource`
--
ALTER TABLE `resource`
ADD CONSTRAINT `resource_ibfk_1` FOREIGN KEY (`category_id`) REFERENCES `resource` (`id`) ON DELETE SET NULL
ON UPDATE CASCADE,
ADD CONSTRAINT `resource_ibfk_2` FOREIGN KEY (`parent_id`) REFERENCES `resource` (`id`) ON DELETE SET NULL
ON UPDATE CASCADE;
```

resource_attr

```
--
-- Table structure for table `resource_attr`
--
CREATE TABLE IF NOT EXISTS `resource_attr` (
`attr_id` int(11) NOT NULL,
  `resource_id` int(11) NOT NULL,
  `attr_key` varchar(255) NOT NULL,
  `attr_value` longtext NOT NULL
) ENGINE=InnoDB  DEFAULT CHARSET=utf8 AUTO_INCREMENT=6744 ;
--
-- RELATIONS FOR TABLE `resource_attr`:
--   `resource_id`
--       `resource` -> `id`
--
--
-- Indexes for dumped tables
--
--
-- Indexes for table `resource_attr`
--
ALTER TABLE `resource_attr`
 ADD PRIMARY KEY (`attr_id`), ADD KEY `item_id` (`resource_id`);
--
-- AUTO_INCREMENT for dumped tables
--
--
-- AUTO_INCREMENT for table `resource_attr`
--
ALTER TABLE `resource_attr`
MODIFY `attr_id` int(11) NOT NULL AUTO_INCREMENT,AUTO_INCREMENT=6744;
--
-- Constraints for dumped tables
--
--
-- Constraints for table `resource_attr`
--
ALTER TABLE `resource_attr`
ADD CONSTRAINT `resource_attr_ibfk_1` FOREIGN KEY (`resource_id`) REFERENCES `resource` (`id`) ON DELETE
CASCADE ON UPDATE CASCADE;
```

Asset System

The Asset System


- The Asset System
  - Prerequisites
  - Overview
  - Introduction
  - Components
    - Section
    - Entry
    - Field
    - Category
    - Gadgets

Prerequisites

Some knowledge of object orientated programming (OOP) is recommend to understand the following description of the Asset System. If you are unfamiliar with OOP concepts, I would recommend reading a tutorial such as this one (http://docs.oracle.com/javase/tutorial/java/concepts/index.html) provided by Oracle or this one (http://msdn.microsoft.com/en-us/library/ca22fyhc(v=vs.90).aspx) provided by Microsoft, to help you understand terms like class, object, instantiate, property, method, and others.

Overview

The asset system is a content management system (CMS) that is built as an extension to the resource system. It's the main use of the resource system, and to many, the terms "asset system" and "resource system" can seem synonymous. In the diagram below, the Resource class is at the top in red. The child-classes that make up the asset system are in green. Yellow is used for examples of objects (not classes) that could/would have been instantiated from their Class. And the items in blue are examples of resource child-classes (resource types) that exist outside of the asset system.



Introduction

When writing software, the developer creates classes. A class is like a blueprint for objects. The class defines the properties and methods that the future objects will have, and like blueprints, multiple objects can be created from a single class. The Resource Class is a class, and each resource "type" (e.g. Section, Field, Contact, ect.) has a class, something which has been written in core code and cannot be changed by the user. The purpose of the asset system is to reproduce this fundamental low-level class-object system in such a way that the user can create their own classes, properties, methods, and objects without needing to dive into the code.

Components

Section

Sections are like classes, they are the templates/blueprints of the asset system. To create the structure of the blueprint, the user assigns fields (i. e. properties) and sometimes gadgets (i.e. methods) to the section.

Entry

Entries are the objects of the asset system. An entry cannot be created without a section to use as its blueprint. Creating an entry from a section is like instantiating an object from a class.

Field

Fields are the properties of the class. Field has its own child-classes; this is to accommodate the different types of fields. For example, when creating a class *Car*, the developer might give the *Car* class the property *String color*. In a similar fashion, a user of the Asset System could create a Section called *Truck*, a TextField called *color*, and then assign that textfield to the section. When the user goes to create an entry from the section *Truck*, they'll be given the option to include a text value for the field *color*.

Fields also have a use beyond acting as properties for classes. The field object (in this case *color*) is a resource object in it's own right. This means it can be modified independently of the sections that have assigned it and the entries that are using it. For example, a field which shows a dropdown box of several options could be modified to include more options; any entry which is using that field would automatically receive those new changes. Or consider a simple textfield object called "MAC Address" that is used by several sections and entries. If that field was modified to include a filter that checks the input for a valid MAC string, any entry using that field would get those improved validation checks.

Also, because the same field object can be assigned to multiple sections, it's easier to find entries by their values because they're all using the exact same field object. The alternative would have to be a blind text search to try and find different objects but with contextually similar values, and that method is notoriously unreliable.**This is why it's encouraged to assign the same field object to different sections as opposed to just making new fields each time.**

Fields are like what you might call class properties or class variables, but they've also got a lot more functionality available for when you need it.

Category

Categories are just an organizational tool. There is a clearly defined relationship between Sections, Entries, and Fields, but Categories exist on their own. If you look on the Classes page, you'll see that every Resource has the same 6 fundamental properties and 3 of them are ID values. The first is the ID that belongs to the resource itself, the second is the ID of the resource's parent, and the third is the ID of the Category that the resource belongs to (if any). There isn't a strict hierarchy here, how you use categories is entirely up to you. You can create categories, child categories, and careful plan exactly how you want the resources in your system to be organized. Or you can ignore the whole thing completely and just let every resource have the default category of "uncategorized." Many user find that the ability to create hierarchal parent-child relationships with entries, and then filter down results even further by Section, leaves the use of Categories unnecessary. But if you want to use them, it's there.

Gadgets

Gadgets are not resources, which is why they're not included in the chart at the top of the page. Gadgets are self contained applications and are limited to only using HTML, CSS, and JavaScript. All they know about the page that they're loaded on is the ID of the resource. However, because gadgets can interact with the API via JavaScript/AJAX, they're the perfect way to add new features to the asset system in a maintainable and modular way. At it's core, the asset system just allows users to create entries and then modify their text based attributes through a simple form. The ability for gadgets (such as the IPAM-Gadget) to interact with the API, is what makes the asset system so powerful.

Currently, the only gadgets that can be assigned to sections are gadgets that have been created by 6Connect. However our API is robust enough that almost anything you can do through ProVision could be recreated in the form of an isolated gadget. And because they're just made from html and javascript, it shouldn't be too strenuous for anyone to write a gadget of their own. If you want to create your own gadgets, it would be recommended to email us first with an outline of what you're trying to do. Then the recommended procedure would be to first create it as a standalone HTML/Javascript webpage that connects to our API (you may need to disable cross domain request security in your browser to make the AJAX connections work). Once you have your standalone page working, the process to turn that into an embeddable gadget is trivial.

Note: Gadgets are initialized as AngularJS applications. Both the AngularJS and jQuery libraries will be loaded on the page and available to use, but it is highly recommend to make the entire gadget in the form of an AngularJS app. But as noted above, it's best to contact us first so we can help you in the right direction.

Help & Support

Help & Support

For setup assistance or additional information, you can contact our support team at support@6connect.com.

For tutorials, frequently asked questions, feedback, or additional resources such as import templates and previous documentation versions, please follow the links listed below.

Table of Contents

- Tutorials
- FAQ
- Additional Resources
- Feedback and Feature Requests

Tutorials

Tutorials

Here we have grouped together video tutorials for various tasks and UI components. We link to these in the Getting Started area in the documentation, but you can also browse them individually depending on your needs. If you have suggestions for content - please send them to support@6connect.com.

Table of Contents

- Common Tasks
- UI Tours

Common Tasks

Here is a list of shortcuts to walkthroughs and information on performing common tasks in ProVision:

IPAM

IP Blocks

Adding/Editing blocks

Aggregating/Splitting blocks

SWIP configuration and use

RPSL configuration and use

IP Import

Import Aggregate Blocks

IP Import from CSV

DNS

Importing DNS Data

Import DNS Zones:

BIND DNS Zone Upload / Import

PowerDNS Zone Import

Peering

Peering Common Tasks

Adding routers

Adding sessions

Importing sessions

Resources

Importing Resource Data

Resource Import from CSV

Resource Importer Walkthrough

UI Tours

- General
  - Getting to know ProVision: First Steps - Part1
    - ProVision v5.1.x
  - Getting to know ProVision: First Steps - Part2
    - ProVision v5.1.x
- Administration
  - Admin Preferences Page Overview
    - ProVision v6.0.x
    - Previous Versions:
    - ProVision v5.1.x
  - Managing Group and User Permissions
    - ProVision v5.1.x
  - DNS BIND Zone Importing
    - ProVision v5.1.x

General

Getting to know ProVision: First Steps - Part1

ProVision v5.1.x

Getting to know ProVision: First Steps - Part2

ProVision v5.1.x

Administration

Admin Preferences Page Overview

ProVision v6.0.x

Previous Versions:

ProVision v5.1.x

Managing Group and User Permissions

ProVision v5.1.x

DNS BIND Zone Importing

ProVision v5.1.x

FAQ

FAQ

From the command line in your ProVision instance, you can get a manual SQL backup using the following way:

```
mysqldump -uUSER -pPASSWORD DATABASE > bkup.sql
```


You can get the values for USER, PASSWORD, and DATABASE by reading them from the following file:

```
[ProVision Root]/data/globals.php
```


An example of a completed command:

```
mysqldump -uroot -p6connect_DBPSWD qa_5_1_5 > bkup.sql
```

You can then use this .sql file to restore the old version should you need to revert the installation.
When managing duplicate/overlapping IP ranges withing ProVision, there are several methods you can use to ensure that blocks are "unique" and still leverage functions like Smart Assign. The easiest approach is to use metadata for the aggregate (LIR, Region, Resource, etc.). From the ProVision GUI, you can use the "Add Aggregate" function on the IPAM tab (image below) to add a duplicate aggregate. By assigning the new Aggregate to a Resource (#1) you will tie the block and a Resource together. You most likely wish to make assignments out of this new aggregate, so you can enable subassignments (#2) before adding the aggregate (#3).



Now the block will be assigned to a Resource, and you can still provision smaller blocks out of these duplicate parent blocks. When using the IPAM gadget from the Resource screen, just go the Advanced section and you will have more options available for assigning IP data. If you have "strict" enabled, your Smart Assign function should work as expected when you use the LIR or Assigned Resource fields for blocks.



Yes - in DNS Admin, simple specify the DNS Servers like normal and then attach the zones as needed with the desired SOA.
The users list includes a "system user" that is only used by ProVision internally in the application.
In the case when a user already has SWIPped blocks to ARIN, 6connect checks prior to actually performing a SWIP. In the process, if the IP block is already SWIPped, it will check for existing ARIN customer data and update the 6connect data to reflect what ARIN has on file. Once that is complete, the user can then perform a de-SWIP function using ProVision.
When you make an API request to assign a block, if the block is already assigned to another resource, you will receive an error. If your process is to search for and then assign blocks, the Smart Assign API call may be very helpful. That call combines the search and assignment into one action.
Please make sure that URL rewriting is enabled in your instance (apache mod_rewrite)
In some legacy instances we have seen zone record-view linkages come out of alignment and result in unexpected behavior.

BACKUP YOUR DATABASE

⚠

Please note that the following mysql commands modify your database! Please take a backup copy of your database before performance any database modifications.

First, verify the error with the following mysql commands:

```
SELECT count(*) FROM `zone_server_linkage` as t1
INNER JOIN `records` as t2 ON t1.`zoneid` = t2.`zone_id`
INNER JOIN `dns_views` as t3 ON t1.`serverid` = t3.`server_id` AND
`name` = '_6connectDefault'
LEFT JOIN `dns_view_record_linkage` as t4 ON t2.`id` = t4.`record_id`
AND t3.`id` = t4.`view_id`
WHERE t4.`id` IS NULL;
```

If the reply comes back non-zero, then your database is most likely exhibiting unexpected behavior.

The following mysql commands will re-align all the record-view linkages:

```
INSERT INTO `dns_view_record_linkage` SELECT '', t2.`id` as `record_id`,
t3.`id` as `view_id` FROM `zone_server_linkage` as t1
INNER JOIN `records` as t2 ON t1.`zoneid` = t2.`zone_id`
INNER JOIN `dns_views` as t3 ON t1.`serverid` = t3.`server_id` AND
`name` = '_6connectDefault'
LEFT JOIN `dns_view_record_linkage` as t4 ON t2.`id` = t4.`record_id`
AND t3.`id` = t4.`view_id`
WHERE t4.`id` IS NULL;
```

Contact support(support@6connect.com) if you have any additional questions or this does not resolve the issue.

To create a reserved pool of IP space, you can create a Section called "Reserved", add the IPAM gadget to it, then create an Entry with that Section to be the address group. From there, use the IPAM gadget and the IPAM Manage page to assign and unassign IP space from that pool.

The workflow for this would be:

1. Assign IP space to the "Reserved" Section.
2. When you are ready to pull space from "Reserved", unassign the desired block. This moves it to the holding tank.
3. Override the holding tank to make the space "available". This can be done in the IPAM manager via the "Override Holding" wrench option, or a manual 'pull out of holding' API call.
4. Assign the block to the desired Resource.

Depending on your version of ProVision, you may need both steps. Edit the file <6connect web root>/data/globals.php and:

1) Change the $hostname variable to the new value

2) Change the $base_url to the new value

Please note that you may also need to update the SSL certs, httpd settings, etc.

Additional Resources

- Import Templates
- List of Abbreviations

Import Templates

Import Templates

Downloadable Import Templates

Below you can find CSV templates for uploading Resource, Contact and IP data.

For DNS Import examples and a walkthrough, visit the DNS Import page.

	File	Modified
	File contact-import-sample_v1.csv	May 06, 2020 by The Force
	Text File customer-import-sample.csv	May 06, 2020 by The Force
	File import-zone-assign.csv	May 06, 2020 by The Force
	File IP-import-sample_v1.csv	May 06, 2020 by The Force

Drag and drop to upload or browse for files
Download All

List of Abbreviations

List of Abbreviations:


API	Application Program Interface
CLI	Command-line interface
DHCP	Dynamic Host Configuration Protocol
DNS	Domain Name System
DNSSec	Domain Name System Security Extensions
IP address	Internet Protocol address
IPAM	Internet Protocol address management
LDAP	Lightweight Directory Access Protocol)
SDK	software development kit
SSH	Secure Shell

Abbreviation List.xlsx

Feedback and Feature Requests


Upcoming Features

For information on future releases, click on the "Coming Soon" link on the Dashboard Status Widget - it will direct you to the "Coming Soon" feature Roadmap (subject to change).



Support or Feedback

From the dashboard "Contact Us" Widget, you may click the support link to email a support request to support@6connect.com, or click "show feedback form" to open a form to send a short feedback message to feedback@6connect.com.



Of course, you may aways email support@6connect.com or feedback@6connect.com directly.

6connect Scanlet (Beta)

Scanlet (Beta)

Download Information

Download the latest version here

System Requirements

Java: Download Here

Known Issues

- In some cases, the application may appear to hang before it finishes. This is usually related to timeouts not being addressed quickly. We erred on the side of caution to ensure that devices were located, but the result is that sometimes unresponsive devices can make the scan take longer than expected.

Documentation

This software is currently in Beta - please forward all feedback to gary@6connect.com

Starting Scanlet

When you open the download URL, you should see the Java plugin activate and should be prompted with a security warning to confirm that you are knowingly running the application.





Upon checking the box and clicking the "Run" button, it should automatically bring up the UI in your browser.

If this does not work, try to click the link at the bottom left of the webpage to manually open the application.


Using Scanlet

Running a Scan







STEP 1: Set the IP range that you would like to scan. If you click on the "IP Range" square, you will have a window open to set the parameters.



STEP 2: Select the additional parameters for your scan (ping selector, Ports, thresholds, etc.)



STEP 3: Run the scan!




STEP 4: View the scan results. You can expand the arrows per IP address, view Port information or MAC address data.

Uploading/Saving scan results

Option 1: If you have a 6connect ProVision instance to test with, you can upload your scan results into the platform using the API with the "UPLOAD" selection.



When you click on the "SAVE" button, you will be directed to enter the API information for your particular instance. Discovered devices will be imported as type "Scanlet". We will be pushing out an update that will allow you to modify different types and even allow some more detailed heirarchies from the initial discovery model.



Option 2: If you would like to save an XML/CSV version locally to your computer, simply select the format you prefer. When you click on the Save button, it will prompt you for a location to save the file.

Release Notes

Release Notes

- ProVision 7.4.0
- ProVision 7.3.0
  - ProVision 7.3.1
- ProVision 7.2.0
  - ProVision 7.2.1
- ProVision 7.1.0
  - ProVision 7.1.1
- ProVision 7.0.0
  - ProVision 7.0.2
  - ProVision 7.0.1
- ProVision 6.1.1
  - ProVision 6.1.2
- ProVision 6.0.0
  - ProVision 6.0.2
  - ProVision 6.0.1
- ProVision 5.3.0
  - ProVision 5.3.2
  - ProVision 5.3.1
- ProVision 5.2.0
  - ProVision 5.2.2
  - ProVision 5.2.1
- ProVision 5.1.0
  - ProVision 5.1.4
  - ProVision 5.1.3
  - ProVision 5.1.2
  - ProVision 5.1.1
- ProVision 5.0.0
  - ProVision 5.0.4
  - ProVision 5.0.3
  - ProVision 5.0.2
  - ProVision 5.0.1
- ProVision 4.2.0
  - ProVision 4.2.1
- ProVision 4.1.0
  - ProVision 4.1.23
  - ProVision 4.1.22
  - ProVision 4.1.21
  - ProVision 4.1.20
  - ProVision 4.1.19
  - ProVision 4.1.18
  - ProVision 4.1.17
  - ProVision 4.1.16
  - ProVision 4.1.15
  - ProVision 4.1.14
  - ProVision 4.1.13
  - ProVision 4.1.12
  - ProVision 4.1.11
  - ProVision 4.1.10
  - ProVision 4.1.9
  - ProVision 4.1.8
  - ProVision 4.1.7
  - ProVision 4.1.6
  - ProVision 4.1.5
  - ProVision 4.1.4
  - ProVision 4.1.3
  - ProVision 4.1.2
  - ProVision 4.1.1
- ProVision 4.0.0
- ProVision 3.9.0
  - ProVision 3.9.3
  - ProVision 3.9.2
  - ProVision 3.9.1
- ProVision 3.8.0
- ProVision 3.7.0
- ProVision 3.6.0
- ProVision 3.5.0
- ProVision 3.4.0

- ProVision 3.3.0
- ProVision 3.2.0
- ProVision 3.0.0
- ProVision 2.5

ProVision 7.4.0

ProVision 7.4.0 is a major release with new features, improvements and bug fixes.

Major Features and Improvements in this release:

- New Features
  - New Admin Settings Interface
  - New Resource Lists Interface
  - Constraints
- Additional Features / Improvements
  - DNS Improvements
    - S64 DNS Server Configuration Rollback
    - Save Import File
    - Import Zone Comments
  - New Report Types
    - IPAM Runout Report
    - DHCP Server Report
    - DHCP Pools Report
  - Additional Improvements
    - ProVision IPAM-As-WHOIS
    - GEO IP Exporter
    - IPAM Auto AS-Resource
    - IPAM IPv6 Sparse Allocation Schemes
    - IPAM Aggregate Notes
    - Chart View Select Top Node
    - Dashboard Log Widget
    - Logging Improvements
- Bug Fixes/Minor Improvements


Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

New Admin Settings Interface

IM - 3723: Update Admin Preferences UI to utilize sub-tabs, improve backend.

The Admin Preferences area has been updated with a new UI and updated backend. Each module area can be accessed by its own sub-tab button, available at the top of the page.



For details, see Admin Preferences.

New Resource Lists Interface

IM - 3481: Updated the Resource Lists UI to support bulk edits, custom columns and other new features

CFR - 32: Bulk Edit for Resources

CFR - 85: User Customization of Resource List Columns

CFR - 98: Mass reassign of resources to a different Parent Resource

CFR - 164: User Customization of # of resource per page / pagination


IM - 1498: Update Add Resource Button(s) to be more consistent with other UI areas

IM - 1908: Multi-Edit of Resource Attributes

IM - 2653: Bulk Resource Assign

IM - 3481: Update Resource List interface

The Resource Lists interface has been updated to better coordinate with the IPAM UI, allowing for a greater variety of customization and new features to be included.



Additional Updates include:


- Bulk resource edit
- Customizable column locations
- Custom columns from resource attributes
- Column sorting
- Additional filter and display options
- Custom resource lists
- Updated Contacts list

For details on using the new Resource List Views, see Resources, Working with Entries, and Customizing Resource Views

Constraints

CFR - 165: Added a Constraints system for setting admin-designated field limitations to ProVision IPAM fields.

Constraints allows Admin users to configure custom field validation and limitations into IPAM fields. Many constraint types are available, such as mathematical comparison operators, length, enumeration, pre-set lists, RegEx, IPv4/IPv6, Phone, email, hostname, FQDN, Mac Address, and URL.



For details, see Constraints.


Additional Features / Improvements

DNS Improvements


S64 DNS Server Configuration Rollback

CFR - 180: S64 DNS Servers now supports configuration rollback

To enable configuration rollback for S64 DNS Servers, go to the Server Settings page for the desired server, then toggle "Enable Configuration Rollback" to "on". Once set, ProVision will create a backup configuration file during push to use for a rollback.



To perform a rollback after a push, click the "Rollback Config" button on the server settings page.




For additional information, see link here.

Save Import File

CFR - 179-a: Added a DNS Admin setting - "Save Import File", which retains original DNS zone import files for download under Zone View page "Backup Files and Attachments"

To enable saving import files, go to Admin Preferences DNS Settings sub-tab. From there, select "Import Settings" in the DNS Global Settings module.

Toggle "Keep Import File" into the ON position, then select "Save Changes".



Proceed with a .zone file import from the zone's View Zone Page.

Once the import has completed, the original zone import file will display in the View Zone page under "Zone Backups and Attached Files".




To download the original file, click "Download" for the import file.


Import Zone Comments

CFR - 179-b: Comments contained in DNS Zone Import files will now be appended into the DNS Zone page "Comments" field.

DNS Zone Import will also import comments contained in the .zone file, such as an internal change log (such as in the image below).



When imported by selecting the "Import Zone" button on the View Zone page, these comments are added to ProVision's zone comments field:



New Report Types


The following default reports have been added to the **Reporting** Tab:

IPAM Runout Report

CFR - 186: Added the IPAM Runout Report type to the Reporting Tab.



The IPAM Runout Report displays available/assigned host statistics and projected runout for the selected block type(s) and region(s).




DHCP Server Report

IM - 3705 a: Added the DHC Servers Report type to the Reporting Tab.




The DHCP Servers Report displays existing DHCP servers in ProVision, associated statistics, and last updated time. The DHCP Servers report can be filtered by Name, Domain, or by last modified date.




DHCP Pools Report

IM - 3705 b: Added the DHC Pools Report type to the Reporting Tab.



The DHCP Pools Report displays existing DHCP Pools in ProVision, type, ranges, IP/MAC, associated groups, and last updated time.

The DHCP Pools Report can be filtered by DHCP Server(s), name, type, or by last modified date.



Additional Improvements

ProVision IPAM-As-WHOIS

CFR - 169: Added support for utilizing ProVision IPAM as a WHOIS server.

ProVision now supports utilization as a WHOIS server via REST API requests.

ProVision supports utilization as a WHOIS server via REST API requests. You can query Resources, Contacts, and IP Blocks, just like a traditional WHOIS server, only ours serves data from the ProVision database.

This feature provides an alternate route to provide ProVision data to legacy workflows on your network. If a team is used to query WHOIS, they can query Provision. If a system needs to talk to WHOIS, it can talk to ProVision-as-WHOIS.

Setup

The ProVision WHOIS Server is a thin client for our REST API that listens on port 43 and accepts WHOIS requests that gets forwarded to our API. It is written in Python 3 using the **socketserver** module, and uses the ProVision endpoint **/api/ipam/whois** to receive all requests from the WHOIS server.

The main business logic is located in **services/WhoisService.php**

Running the Server manually

The server is located at **whois_server/main.py** in the ProVision repository.

Running the server can be done with: **sudo python3 main.py** (We need root because we are binding to port 43)

Quering the WHOIS server

1. install whois if not present (sudo apt-get install whois)
2. whois -h 127.0.0.1 <query>

Installing the WHOIS server as a service

Different Linux distributions might have different ways to setup a service that runs on startup.

systemd

There is a Unit file for systemd in the repository: **whois_server/provision_whois.service** that is used when a service is created in systemd env.

1) Edit the file to setup the proper path to the python server/file

```
ExecStart=/usr/bin/python3 /root/whois_server/main.py
WorkingDirectory=/root/whois_server/
```

2) Copy the file to **/etc/systemd/system** (on CentOS this directory should be: **/lib/systemd/system/**) -

sudo cp whois_server/provision_whois.service /etc/systemd/system/provision_whois.service

3) Start the service with **service provision_whois start**

4) Verify that is working with **service provision_whois status** and making a test query **whois -h 127.0.0.1 <query>**

The systemd services are run as root, so there shouldn't be issues with binding to port 43.

init.d

There is also init.d file located at **whois_server/provision_whois**

1) Edit the file to setup the proper path to the python server/file

```
DAEMON_OPTS="/var/www/projects/whois/app.py"
```

2) Copy the file to **/etc/init.d/**

3) **chmod +x /etc/init.d/provision_whois -v**

4) Verify that is working with **service provision_whois status** and making a test query **whois -h 127.0.0.1 <query>**

GEO IP Exporter

CFR - 192: Added the ability to add GeoIP location information to the Contact Info Gadget for a resource, and export location data for resources with assigned blocks to .csv

ProVision now supports the entering and export of IETF format-compliant GeoIP data for resources which have assigned IP blocks.

The Geo IP Exporter may be enabled as a scheduled task (See: Scheduler Tab) that, at run time, searches the ProVision instance for resources which have IP addresses and an address provided in the Contact Info Gadget, then saves the resulting .csv to the ProVision root directory.

If a resource has an assigned IP address, and either Geo IP location data or a Mailing Address entered in the Contact Info Gadget, then the data will be included in the .csv output. If an IP address is not associated with the resource, or if neither Geo IP / Mailing Address has been provided, the resource will be skipped.


This feature includes updates to the following areas:

- Updates to the Contact Info Gadget to provide Geo IP fields
- A Geo IP Export Scheduler Task
- Writes files to the ProVision root directory


For additional information, expand the walkthrough below:

1) Enter GEO IP data to Resources

Add GEO IP location data to a Resource by selecting "Edit" for the Contact Info Gadget.




Enter a separate address to denote as the GEO IP location, or you may select "Same as Mailing Address":




2) Set up the Geo IP Export Scheduler Task

Create a Scheduler task to export GEO IP data:




3) Run the Scheduler Task / File Access

Run the GEO IP scheduler task, either via "Run Now" or as a scheduled run - the task will search for resources with an assigned IP address, and either Geo IP location data or a Mailing Address entered in the Contact Info Gadget, and add the data to the .csv output.




Once the task has completed, the GEO IP data will be written to the ProVision root directory as "geoip_feed.csv":




IPAM Auto AS-Resource

CFR - 188: Added a new "SystemAS" section to automatically create a resource for ASN's entered in IPAM Manage.

ProVision now automatically creates an AS resource for ASN's entered into IPAM Manage (formatted as "AS1234" or "1234").



An ASN in IPAM Manage will link to the created resource, which will display all IP Blocks in ProVision with that ASN value. SystemAS resources may not be edited, however they may be deleted by an admin if desired.




IPAM IPv6 Sparse Allocation Schemes


CFR - 184: Added scheme options (Leftmost, Rightmost, Center) to IPv6 Sparse Allocation. See: IPAM Configuration

Admins may now denote a system default Sparse Allocation scheme to use for IPv6 Sparse Allocation. Available values are Leftmost, Center, and Rightmost. If not otherwise specified, Leftmost is the ProVision Default.

To edit the Sparse Allocation Scheme, select the desired scheme in IPAM Configuration, then enable sparse allocation for the desired IPv6 aggregate. The Sparse allocation scheme is applied to the aggregate when sparse allocation is enabled for the aggregate, thus, pre-existing sparse allocation schemes will not be altered by later changes.



If you wish to change the scheme for an existing sparse allocated-enabled aggregate, you must disable sparse allocation for the aggregate Edit the selected scheme re-enable sparse allocate for the aggregate. To verify which scheme is applied to aggregates, you may view the aggregate and scheme details in the Numbering Authority Sparse Allocate listings.



IPAM Aggregate Notes

IM - 3809: Added display of IPAM Aggregate notes to the Top - Level Aggregate listing.

IPAM Notes applied to the topmost aggregate block now display in the IPAM sidebar, under the aggregate.





Chart View Select Top Node

IM - 3778: Users can now select a specific resource as the "Top Node" in Resources Chart View.




A specific resource may be selected as the "Top Node" when viewing Resources Chart View, to focus in on a specific sub-tree of the resource hierarchy. Top node selections apply only to that page view session, and are not permanent.

Dashboard Log Widget


IM - 3123: Added a new "Logs" Widget option to the Dashboard.

The Logs Dashboard Widget displays the most recent 'x' number of logs for a specified search term, such as resource name, task, id number, username, and so forth.



Once the Logs Widget has been added to a Dashboard, edit it by clicking the wrench icon in the upper right side of the Widget.

In the Edit menu, you may edit the Logs Widget name, enter a search term, select number of results to display, and select a log level to filter results by.



When complete, click "Apply" to save your changes.

For information on how to add the Logs Widget to the Dashboard, see Customizing the Dashboard.

For additional information on this and other Widgets, see Working with Dashboard Widgets.

Logging Improvements

A number of minor improvements and fixes have been made to logging:

IM - 2617: "Logging" links from tab dropdown menus now automatically filter the Log Tab results to that category.

IM - 3732: Minor UI updates have been made to the Admin Logs page.

IM - 3800: Added log events for updates made to the Field Gadget.

IM - 3801: Overzealous logging of session timeouts have been removed.

IM - 3803: Log events indicating missing field types have been fixed by adding a field repair tool to the upgrade script (tools/verify_fields.php).

IM - 3807: Failed API Authentication attempts now create a log event.

IM - 3808: Added missing values for the "time" attribute in remote Syslog responses.

Bug Fixes/Minor Improvements

CFR - 159: Resource Report now includes filters to show linked resources (checkbox options) and search by attribute.

CFR - 161: Added partial search by phrase / term in field to Reporting resource reports.

IM - 1806: Added Host Count and sort options to IPAM Reporting.

IM - 2491: Updated the UI and page notification that occurs when a user logs in with no group permissions.

IM - 2792: Updated static resource dropdown selectors to a more user-friendly searchable/filterable selector menu.

IM - 3042: Updated IPAM Columns Mask/Host Count fields to correctly display Mask and Host Count, respectively.

IM - 3210: Minor UI adjustments made to the save button style and location in DNS Groups Default Group Parameters and Catalog Zone Settings.

IM - 3262: Updated the permissions handling of all pages to recognize Groups containing Admin access on TLR as having equal permissions to Global Admins.

IM - 3362: Added the ability to clear inputs ("x"s) when using DNS Record List page filters.

IM - 3363: Disabled the "Save Changes" button in DNS Edit ACLs, until savable changes have been entered.

IM - 3374: Scheduler page now correctly displays for TLR Admin users in Groups other than Global Admin.

IM - 3559: Updated information and style of scheduler notification emails to better coordinate with eachother.

IM - 3583: Limited permission users may now view Reporting v2 (but may not perform admin-level report actions)

IM - 3584: Restricted Field Gadget Add/Edit field actions for read-only users.

IM - 3620: Restricted access to VLAN Add/Delete/Update actions for read-only users.

IM - 3628: Updated style of pagination controls in Reporting Resource Reports.

IM - 3646: Relocated the "Loading" image to a more visible location in VLAN Add Domain / Add VLAN.

IM - 3656: Added the ability to remove a single VLAN for a block via an "x" clear-field option.

IM - 3657: Added the ability to remove VLANs for multiple blocks at a time via multiple block edit in IPAM Manage.

IM - 3659: VLAN Sidebar Quicknav now correctly works when navigating from a page other than the first Domain page.

IM - 3661: Resolved an issue preventing VLAN Metadata from being saved if no IP blocks were assigned to the VLAN.

IM - 3663: Removed the automatic display of the VLAN Advanced filter flyout when opening Domain Manage.

IM - 3687: Shortened the filter flyout in IPAM/VLAN Manage so that it can no longer overlap pagination.

IM - 3699: Removed an extra DNS Zone Restore button that would appear in DNS Zone Backup if multiple pages of records existed.

IM - 3707: Resolved a display error that would occur in the "IPAM Stats" dashboard widget Total Available 1918 Hosts field if multiple IPAM Stats widgets existed.

IM - 3708: Added the ability to add a new IPAM region, if all other regions were deleted.

IM - 3711: Clone Resource now correctly handles resource names that contain apostrophes.

IM - 3715: Updated Permissions to better handle caching of group permissions when a user is assigned to more than one Group.

IM - 3717: Resolved an IPAM search error that would load unrelated IP blocks when expanding search results via the "Load More" link.

IM - 3761: Updated user permissions to identify an Admin user as any user in a Group with "Admin" permissions on the TLR resource, instead of only users in the "Global Admin" Group.

IM - 3785: Resolved an issue in IPAM Manage where LIR changes would not propagate to children.

IM - 3788: Updated treeview to limit returned blocks to 8000 IPv4/IPv6 blocks, to prevent browser loading issues.

IM - 3793: The "Email" field once again displays in the Contact Gadget.

IM - 3794: Updated the IPAM gadget to no longer treat in-gadget links as an iframe module.

IM - 3810: IPAM Manage Multi-select Edit now supports bulk enable/disable of the the "Important" flag for blocks.

IM - 3811: All IPAM Column display name changes now correctly update in IPAM Manage filters.

IM - 3812: IPAM Aggregate "Merge" no longer requires a page refresh between consecutive merge attempts.

IM - 3814: Improved search handling of numeric-only search terms.

IM - 3816: Resolved an issue where searching for /32 blocks and following the resulting CIDR link does would not display the block in IPAM Manage.

IM - 3819: Updated error messaging in IPAM Manage when filtering by a single mask.

ProVision 7.3.0

ProVision 7.3.0 is a major release with new features, improvements and bug fixes.

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Major Features and Improvements in this release:

- New Features
  - VLAN v2
    - Included Updates and Features
    - VLAN Updates by Page / Feature:
  - Reporting v2
    - Included Features
    - Available Reports
  - Reporting IPAM Stats Widget
  - DNS Route 53 Connector (Beta)
    - Set Route53 Specific Settings
- Additional Features / Improvements
  - IPAM Improvements
    - Add Aggregate UI Update
    - RIR Filters
  - Holding Tank Improvements: "View Pending Blocks" / Column Sort
  - Peering Improvements
    - Peer Templates
    - Peering File Connectors
    - Improved Peering Import / Peering DB Coordination
    - Peering Cache Check
  - Resource Export to .csv
  - Resource Linkage Gadget Updates
  - Log Rotation (Admin Settings / Scheduler Task)
  - ACP Improvements
    - Admin ACP Settings
    - ACP Workflow Form Gadget Updates
- API Updates
  - APIv2 Updates
- Bug Fixes/Minor Improvements


Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

VLAN v2

IM / CFR - 3471: Fully updated the ProVision VLAN user interface and added new features, pages, and ease of use improvements.

ProVision's VLAN system has been given a shiny new UI to match IPAM and updated with new features, views, and improved access to common tasks.



Included Updates and Features

- Updated UI for all VLAN pages - featuring a cleaner look, collapsible sections, and easy access to management actions
- Supports custom domain ranges and exclusions, using ProVision's Numbering Authority
- Create Domains and add VLANs directly from the VLAN Home page
- Associate Domains with Routers
- VLAN Manage updated to reflect IPAM's interface
- Customizable VLAN Metadata Columns (IPAM Admin VLAN Columns) in lieu of VLAN tags
- Action shortcut panels in VLAN Utilization - Quickview, Assign IP, and Edit VLAN
- New "VLAN Advanced" page provides a global list view of all Domains, VLANs, and their associated metadata
- Improved VLAN workflow by removing the VLAN Admin page, and integrating functions directly into the VLAN Tab.

For more information, see detailed breakdowns of the features, below, or see documentation at IPAM Tab -> VLAN.


VLAN Updates by Page / Feature:

VLAN Home Updates

The VLAN Home page features an updated UI, to better match the style and layout of the IPAM Tab. Navigate between IPAM, VLAN, and Logging by clicking on the sub-tab buttons at the top of the page.


- Navigate between IPAM, VLAN, and Logging by clicking on the sub-tab buttons at the top left of the page

- Open VLAN Advanced (Global View), by clicking the "Advanced" button at the top right of the page
- The VLAN Page Header now contains direct links to add a new domain ("Add Domain") or VLAN ("Add VLAN"), that were previously only accessible from the ProVision Admin area
- The VLAN sidebar list has been updated with new features and options (detailed later)
- The VLAN Utilization area now has domains that are able to be expanded/collapsed and paginated VLAN entries
- The Utilization entry for each VLAN contains an updated UI, gear menu, and new panel options (detailed later)




VLAN Sidebar Updates

The VLAN Sidebar has been updated with a new interface (similar to IPAM's), improved filtering, and new menu options.



Above: VLAN Sidebar - Domain Menu



Above: VLAN Sidebar - VLAN Menu

- The VLAN sidebar has been updated with search, filters, and new right-click menu options
  - Filter the VLAN sidebar to display either "Added" VLANs, "Active" VLANs that have blocks assigned, or "Named" VLANs with user-provided names
  - Search the VLAN sidebar for a particular Domain, VLAN Number, or VLAN name by typing into the search/filter field "Filter VLANs..."
  - Right click to open context menus for both Domains and VLANs
  - The VLAN list under a Domain is now paginated

- Domain Sidebar Actions
  - Click on a Domain name to show/hide the VLANs contained under that Domain
  - Click "manage" next to the Domain name to open VLAN Global for that domain
  - Right click on a domain to open options to:
    - "Edit Domain"- Opens VLAN Advanced Edit Domain Panel for that Domain
    - "Add VLAN" - Opens the Add VLAN page for that Domain

        - "Remove Domain" - Deletes the domain and all VLAN data under it

- VLAN Sidebar Actions
    - Click on a VLAN number/name to QuickNav to its location in the VLAN Utilization area of the page
    - Click on "open" next to a VLAN to open VLAN Manage for that VLAN
    - Right click on a VLAN to open options to:
        - "QuickView" - QuickNavs to the VLAN's Utilization area listing, and opens the VLAN's Quickview Panel
        - "Assign Blocks to VLAN" - QuickNavs to the VLAN's Utilization area listing, and opens the VLAN's "Assign Blocks" Panel
        - "Edit VLAN" - QuickNavs to the VLAN's Utilization area listing, and opens the VLAN's "Edit VLAN" Panel
        - "Remove VLAN" - Deletes the VLAN, removing the VLAN assignment from any blocks assigned to it


VLAN Manage Updates

VLAN Manage has been updated to match the IPAM Manage interface and filtering options, now supports customizable columns / metadata columns, and adds access to common VLAN management areas, and includes four VLAN Panels - Utilization, Quickview, Assign Block, and Edit VLAN.

From any VLAN manage page, you may navigate to VLAN Advanced ("Advanced"), add a new Domain ("Add Domain"), or add a new VLAN ("Add VLAN").

In addition, VLAN Manage has been updated to use the same interface options as IPAM Manage:

- Sort the block list by clicking on column names
- Resize columns by dragging the vertical divider between column names to the left or right
- Edit column order, visibility, names, or add custom metadata columns from IPAM Admin VLAN Columns
- Double-click to open "Edit Block" for any block in the list
- Right-click on a block (or click on the gear icon) to open the IPAM Action Menu
- Shift-click to select multiple blocks, and then right-click for multi-block menu options
- Filter the block view by clicking on "filter >", then selecting filter criteria. When done, click "Apply".
- Open VLAN Action panels from inside VLAN manage to review data or perform standard tasks, including:
    - VLAN Utilization Charts (Pie Icon)
    - Quickview (Eye Icon)
    - Assign Blocks to VLAN (Plus Sign)
    - Edit VLAN (List icon)




VLAN Manage / VLAN Utilization Action Panels

These action panels are available from both the VLAN Home page and VLAN Manage, and may be opened or closed by clicking on the associated header bar icons. Each panel allows you to view data specific to that VLAN, or perform common management actions.

Utilization


The Utilization panel displays breakdowns for all blocks assigned to the VLAN by both status (available, allocated, assigned, holding) and by resource. Recently assigned blocks are noted under the "Recent Assignments" section, and links are provided to the Resource Entry page for each resource listed. To open or close the Utilization panel, click on the "Pie" icon in the grey header bar.



Quickview


The Quickview panel provides a condensed, filterable list of all blocks assigned to that VLAN, separated into three columns - IPv4 blocks, IPv6 blocks, and grouped by resource.

To open or close the Utilization panel, click on the "Eye" icon in the grey header bar.




While in the Quickview panel, you may easily search for a block by typing the all or part of the CIDR into the IPv4 or IPv6 Filter boxes - useful for verifying an assignment or quickly scanning ranges.

You may also remove a block from the VLAN with a single click of the "Remove" button.



Assign Blocks to VLAN


Blocks may be assigned to the VLAN from the Assign Blocks Panel, opened or closed by clicking on the plus-sign icon. Two assignment options are available - Direct Assign to VLAN, if you know the specific block to assign, and Smart Browse to VLAN, where you can specify filter conditions and select one of more blocks meeting those conditions.



To open either option, click on the appropriate header bar to expand the module.

Direct Assign to VLAN

To Direct Assign a specific block to the VLAN, expand the "Direct Assign to VLAN" module, then enter the CIDR to assign into the "CIDR" box, and click "Add IP Block" .




If blocks exist with the same CIDR (such as in duplicate 1918 space), you may differentiate between the two by clicking on the "Advanced Options" link and providing additional filter criteria to use to assign a specific block.

Smart Browse to VLAN

Smart Browse to VLAN is used to search for a general list of blocks available to assign to the VLAN that meets certain criteria.

Expand the "Smart Browse" module by clicking on the header bar .

Then, enter your filter criteria. At minimum, block "Type", "Size", and "RIR" must be provided; "Region" and "Tags" are optional.



If further filtering is needed, you may click on "Advanced Options" to open the "LIR", "Custom Code" (here: as "GRT"), and assigned "Resource" fields to use.

Once you have entered your filter criteria, click on the "Smart Browse" Button to display your results.


Assigning from Smart Browse

The Smart Browse results list will display a list of blocks that a) meet your filter criteria, and b) do not already have a VLAN assigned.


You may assign individual blocks immediately ("Add IP Block"), or select multiple blocks and delay assignment until after your final selections are complete ("Assign Selected").

Immediate Assignment:

To assign an individual block immediately from the list to the VLAN, click "Add IP Block" for the desired block.



After clicking "Add IP Block", the block will immediately be assigned to the VLAN, and an "Assigned" status will display for the block in the Smart Browse list.




From here, you may assign additional blocks, clicking "Close" to exit when complete.

If the "Assigned" status displays for all blocks you intend to assign, then you may skip clicking "Assign Selected"- as nothing else remains to assign - and instead click "Close" exit.

Delayed Assignment / Selecting Multiple Blocks:

If you wish to assign multiple blocks to the VLAN at the same time, or mark a single block to assign later while continuing to browse the list, you may select a block to mark for later assignment and then assign all selected blocks at once.

To select a single block, left click on row for the block, taking care not to accidentally click on a blue link. Note that the row will have a yellow highlight indicating it is selected:




To select additional blocks, shift-click on each row you wish to mark for assignment. You may freely scroll through the results to review your selection.

When done, click "Assign Selected". All highlighted blocks will be assigned to the VLAN at the same time, and the Smart Browse window will close.

Edit VLAN

The Edit VLAN panel allows you to view and edit the data associated with the VLAN (Note: not all VLAN fields may be editable).

To open or close the Edit VLAN panel, click on the "List" icon in the grey header bar.




Typically, editable VLAN fields include the VLAN Name and any enabled VLAN "Metadata 1-10" fields enabled in VLAN Columns. To change the information in these fields, click inside the relevant box, type your change, and then click "Save Changes". The information provided in these fields will also display in the "VLAN Advanced" Global View.

VLAN Advanced (Global View)

VLAN Advanced displays a list of all domains / vlans added to ProVision. Here, you can perform domain level management tasks, view data on added VLANs, including Domain, VLAN Name, applied Numbering Domains, associated routers, and any enabled VLAN metacolumn data.

From this page, you may add domains or vlans, edit a domain (by clicking the "List" icon), and perform various actions from the VLAN Action Menu (right click on a VLAN entry).



Reporting v2

CFR - 148: Fully updated ProVisions reporting system, including an updated user interface, new report types, user-created reports, report customization, and the ability to export/schedule reports.


CFR - 148a: Added user-customizable Resource Reports, including the ability to filter by Section and Category; export to .csv

IM - 3351: Added DNS Zone Reports with zone filter options

CFR - 149: Added user-customizable DNS Zone Reports, including the ability to filter by zone record type(s); export to .csv

IM - 3564: Added new Default Reports, including IPAM, Peering, DNS, Users, and Resource reports.

Reporting v2 replaces ProVision's previous Reporting Tab with a new interface, new reports, and exciting new features. Reports existing from v1 (IPAM Utilization, Customer List, User Activity) have been updated and included as default report options. New report types and default reports have been provided under the categories of IPAM, Peering, DNS, Users and Resources. Note: Reporting v2 is only accessible to admin level users, non-admin users will instead be directed to Reporting v1.



*To access Reporting v2, select the **Reporting** Tab. To view the available report modules (IPAM, Peering, DNS, Users, and Resources), click on the applicable sub-tab button at the top of the page, or select it from the **Reporting** Tab dropdown menu.*

Included Features

- Ten default system reports for IPAM, Peering, DNS, Users, and Resources
- Customizable user-created reports
- IPAM Utilization and Peering Status charts
- Export reports to .csv and/or pdf
- Schedule reports to be emailed at selected intervals
- Safely view existing reports and apply filters without overwriting saved report settings, or chose to permanently save changes.
- Copy existing reports to use as editable templates
- IPAM reports include integration with IPAM Metacolumn data and IPAM Column settings

Available Reports

IPAM Reports

IPAM Utilization reports display IPv4/IPv4 utilization charts organized by RIR and SWIP status, and provide a listing of ProVision blocks meeting the applied filter criteria. The report view includes the block data for all applied IPAM Columns, in the order set under IPAM Admin IPAM Columns . IPAM Reports may be exported to .csv (limit: 100,000 records; no chart provided) or PDF (limit: 1000 records; chart included). Default reports include:

- Default Utilization: IPAM utilization report for all aggregates
- Default Utilization - 30 days: IPAM utilization report for all aggregates assigned in the past 30 days

Peering Reports

Two new peering report types are available - Peering Health and Peering Status. Peering Health reports display the sessions existing in ProVision, with the associated fields of Router Name, Peer Name, IP, Session Type, Session State, Peer Group, and session Created Date. Peering Status reports are set per-exchange, and display pie charts for Peer Status/Qualification Status, as well as a data table of the Peer Name, Request Status, Peer Status, Qualification Status, Message Count, and Last Message Time.

All Peering Reports may be exported to .csv (limit: 100,000 records; no chart provided). Default reports include:

- Default Peering Health Report: Displays the peering session state for all currently existing sessions in ProVision
- Default Peering Status: Displays Peer, Request, and Qualified status for the default (first available) exchange in ProVision

DNS Reports

DNS Zone reports provide a list of zones existing in ProVision, along with the fields of Zone ID, Name, Last Modified Date, Forward/Reverse Type, and Record Count information. DNS Zone Reports may be exported to .csv (limit: 100,000 records). Default reports include:

- Default DNS Zones: All DNS zones in ProVision
- Default DNS Zones - 30 days: All DNS zones in ProVision modified within the past 30 days

User Reports

Users reports provide a listing of ProVision log events associated with user actions. Provided fields include the Timestamp, User, IP, Log Level, and the Action, and the report may be filtered to include one or more users / user groups, as well as basic data filters. User Reports may be exported to .csv (limit: 100,000 records). Default reports include:

- Default User Activity - 30 days: All ProVision user activity within the past 30 days
- Default User Activity - Year to date: All ProVision user activity for the current calendar year (ISO Standard/Gregorian calendar)

Resource Reports

Resource reports provide a list of all (non-DNS) ProVision resources, and field data from the Contact, Billing, Tech Info, and Resource Field Gadget(s) associated with the resource. The report may be filtered to include one or more Sections or Categories, as well filtered by resource name. Resource Reports may be exported to .csv (limit: 100,000 records). Default reports include:


- Customer List Report: ProVision resources which are of the "Resource Holder" Section and "Customer" Category; matching the reporting v1 Customer List report.
- Default Resource Report: All ProVision resource entries - matching resources listed in the Resource Tab -> Entries page list, and all applicable resource fields
    - TIP: Due to the large scope of the ProVision resource system and its fields, we strongly recommend using the Default Resource Report as starting template from which to further define more specific resource reports. Simply "Copy" the Default Resource Report, apply your desired Section/Category filter combination(s), and click the Gear Icon Save to create a more manageable data set.

For additional information, see Reporting and Working with Reports.

Reporting IPAM Stats Widget

IM - 3454: Converted the Reporting IPAM Stats module to a Dashboard Widget

The "IPAM Stats" module, displayed on the Reporting page in prior versions, has been updated and converted into a Dashboard Widget.




For additional information see the walkthrough below, or Customizing the Dashboard and Working with Dashboard Widgets for details on performing basic Widget tasks.

Add the IPAM Stats Widget

To add the IPAM Stats widget to a dashboard, click "Add Widget" from that Dashboard (Note: Default Dashboards require admin permissions to edit or save changes to the Dashboard).




In the "Add new widget" list, click on "IPAM Stats". The IPAM Stats Widget will be added to the Dashboard. If using the Default Dashboard, be sure to save your changes.



From here, you may move the widget to a new location, edit the name, or remove the Widget from the Dashboard. See Customizing the Dashboard and Working with Dashboard Widgets for details on performing basic Widget tasks.

Using the IPAM Stats Widget


The IPAM Stats widget contains read-only IPAM data under three tabs - IPv4, IPv6, and 1918. Click on the desired tab for the block type you wish to view.



DNS Route 53 Connector (Beta)

IM - 2649: Added a DNS Connector for Route53/AWS

ProVision now supports Route53/AWS servers for DNS!



To use the Route53 connector, you must have Route53/AWS account set up and be able to provide the API Key, API Secret, and API Region provided to your Route53 account. For information on setting up a Route53 account, learning resources, or FAQ, see https://aws.amazon.com /route53/ .

For additional information, see Working with DNS Servers, or expand the area below:


Before you Begin

To use the Route53 connector, you must have Route53/AWS account set up and be able to provide the API Key, API Secret, and API Region provided to your Route53 account. For information on setting up a Route53 account, learning resources, or FAQ, see https://aws.amazon.com /route53/ .

To add a new DNS Server in ProVision, you must be logged in as an Admin-level user.

Add a Route53 Server to ProVision


From the DNS Tab, click the **DNS Servers** sub-tab. From there, click "Add Server" to open the Server Settings page.



In Add Server Server Settings, enter a Display Name for the new Route53 server, *skip FQDN, and* select Server Type.


Under "DNS Service", select the "AWS Route53 (Beta) connector. The FQDN field will automatically be disabled, and AWS/Route53 specific settings will be enabled in the next section.

If desired, adjust the other available settings in this section, then scroll down.



Set Route53 Specific Settings

Under the section for **AWS Route53 (Beta) Settings**, enter the API Key, API Secret, and API region provided to you for the AWS/Route53 account. You may choose to click "Test Server" at this time to verify the credentials and connection.



Enter additional Dynamic Updates, NS Records, and Group settings if desired, then click "Save Changes".

For information on working in the rest of ProVision's DNS system, see DNS Tab, DNS Administration, andWorking with DNS Servers.

Additional Features / Improvements


IPAM Improvements

Add Aggregate UI Update

IM - 3474: Updated IPAM Add Aggregate interface to be more consistent with other ProVision areas.

IPAM Add Aggregate is now accessed via a green button located a header bar on the IPAM Tab home page. Clicking "Add Aggregate" will open a new page to input the aggregate data.

The IPAM home page will automatically load after saving the new aggregate.




For additional information, see link here.


RIR Filters

IM - 3417: Added "RIR" filters to IPAM Aggregate Blocks and the IPAM Manage Filter

From the "Aggregate Blocks" list on the IPAM Tab, click "more filters" to view or change the RIR filter.



From IPAM Manage for an aggregate, click the "filter >" option to view or change the RIR filter for the current IPAM Manage view.



For additional information, see link here.


Holding Tank Improvements: "View Pending Blocks" / Column Sort

CFR - 160: Added the ability to view "Pending" items in the Holding Tank and sort by column.

IPAM Admin Process Holding Tank now includes three view options - View Blocks over the over period, View Pending, and View All.

"Pending" blocks (displayed with light blue/grey text) may not be selected for processing until they reach the provided Holding Tank Day setting, but otherwise provide the same viewable data and IPAM Manage link as processable blocks.

In addition, the Holding Tank now provides ascending / descending column sort for all fields, by clicking on the up/down arrows next to the column name.



For additional information, view details below or see IPAM Administration - IPAM Configuration and Holding Tank Management.


Holding Tank Views

Select the desired view from the top of the "Process Holding Tank" page in IPAM Admin:

View Blocks over X days (Default View)

The default Holding Tank view is "View Blocks over X days", which only displays blocks over the "Holding Tank Days" setting in IPAM Configuration. To change to this view from a different view, click "View Blocks over X days" from the view list in the top center of the Holding Tank.


In this view, all processable blocks are shown, and you may select either specific blocks or all blocks for processing.



View Pending Blocks

To view only Pending blocks, click "View Pending Blocks " from the view list in the top center of the Holding Tank. "View Pending Blocks over X days" only displays blocks more recent than the "Holding Tank Days setting".


Pending blocks are not selectable or processable, but display the same data as processable blocks. You may view additional details for the block in IPAM Manage by clicking on CIDR link for the desired block.



View All Blocks


To all blocks, click "View All" from the view list in the top center of the Holding Tank. "View All" displays both Pending and processable blocks, but only processable blocks older than the Holding Tank Days may be selected for release.

Pending blocks display in a lighter color text than processable blocks, and do not have a selection box available. Any block may be viewed in IPAM manage by clicking on the CIDR link for the block, and the list may be sorted into ascending/descending order for any field.



Sort Blocks

From any view in the Holding Tank, click on the up/down arrows next to the column name to sort the results by ascending/descending order for that field.




Peering Improvements

Peer Templates

IM - 3291: Added Peering Templates


*Peering Templates are accessible to Admin users from the **Admin Preferences** page, under Peering Settings.*




Peering Templates allow users to create their own reusable session configuration files. When the default ProVision session configuration template doesn't do everything required for your specific use case, you can create your own template that does. Revisions to Peering Templates are tracked, and a template may be reverted to a previous version at any time.

Viewing Templates


View the Template List by navigating to the **Admin Preferences** page, in the Admin area of ProVision. From there, scroll to the Peering Settings section. Next to "Templates", click "Manage Custom Templates".



The Template List will open, displaying all existing Peering Templates.




Click on any template to open Template Details, where you can edit, delete, or preview the template.




Add a Template

From any page in the Peering Templates area, click the "Add Template" button on the right side of the page header to start a new template.




In the Add Template form, enter a name for the template and the template body. When complete, click "Add".



The "Template Details" view displays for the newly created template, here you can update, preview, or delete the template.

Edit a Template

From the Template Details view, edit the template by clicking inside the template body and typing the desired changes - if you need a reminder as to syntax or variables, click the help icon (Question Mark button) at top right to open the template editing guide.



Click "Update" when done.

Syntax

Templates use the Mustache Format

Template Syntax

Basic Variables

Values on the session object are inserted when referenced by double curly braces {{ }}

```
The router name is {{router_name}}
```

When given a session object with `{router_name:'TheName'}` the line becomes

```
The router name is TheName
```

If / If-Not statements

To only include a block (or part of a line) if a variable exists, enclose that part of the template starting with `{{#variable}}` and ending with `{{/variable}}`

```
{{#color}}The color is {{color}}.{{/color}}
{{#city}}
The city is {{city}}.
{{/city}}
```

When given `{color:'blue'}` the output will be

```
The color is blue.
```

To only include a block if a variable does *not* exist, start with `{{^variable}}` and end with `{{/variable}}`


Common Variables

- source_asn
- vrf
- type_ipv6
- peer_ipaddr
- peer_asn


- peer_group
- peer_name
- ttl
- prfx_max
- prfx_alert_threshold

Preview Template

While editing or viewing a template, you may preview the template's output against a specific session by clicking the "Preview" button. A "Preview Template" section appears.



Select an existing Router/Session from the dropdown list to use to generate the preview. Once selected, the template output will display directly underneath the selected session.



Template Revisions

The Revision History area will display on the Template Details page after an update has been made to the template, with each update displaying as a separate revision item.

Click "View" under the "Actions" columns for a revision to see the template contents at that revision snapshot.




To restore the template back to that revision number, click the "Restore" button for the revision preview.


For additional details on Peering Templates, see Peering Templates.

Peering File Connectors

IM- 3450: Added File Connectors for Cisco, Juniper and Arista router types for use in Peering BGP Import



Added the ability to create File Connectors to import router data files in Peering BGP Import, instead of connecting directly to the router for cases where direct router access is unavailable.



For additional information, see Import Peering Sessions, or expand the link below.

Using Router File Connectors

Step 1


Generate a router response data text file (it should be named "cisco_router_data.txt", "juniper_router_data.txt" or "arista_router_data.txt") and place it in ProVision's /data directory.

To generate the router response, run the following commands:

Cisco	Juniper	Arista
terminal length 0 show bgp ipv4 unicast sum show bgp ipv4 unicast neighbor show bgp ipv6 unicast neighbor	show bgp neighbor | display xml | no-more show bgp group | display xml | no-more	terminal length 0 show ip bgp summary show ip bgp neighbors

Step 2

Create a new 'Router' in ProVision, selecting the appropriate file connector as the Router Make type - CiscoFile, JuniperFile, or AristaFile.




Note: These connector types are only used for this direct data import process - do not select these for standard ProVision router/session creation, as management functions (config pushes, session states, etc) do not obtain a router connection while using File Connectors.


Step 3

Navigate to Admin Data Import Peering BGP Import.

Select the appropriate exchange, then the File Connector Router that you created.



Click "Load Sessions", and the sessions contained within the router data file will be available to review, select, and/or import into ProVision.



Via APIv2

The same import process may also be performed via APIv2, using the following information:

1) "router id" contained within the URL for an already-created File Connector Router

2) "ix_id" (the ID of the exchange) in the body

3) "router_response" (the output from the router) in the body

The APIv2 details can be view from ProVision swagger documentation at ['instance']/dev/swagger/spec.php?family=peering#/default /single_parse_bgp_info

That command will parse the router output and return an array of detected sessions and groups. The sessions and groups then need to be individually added using POST /peering/sessions and POST /peering/peergroups.

Improved Peering Import / Peering DB Coordination


IM - 3290: Improved peering import to suggest Peer Names that match PeeringDB for existing sessions.

If the ASN of a session belongs to a Peer which is in PeeringDB, that name is now suggested as the name to use when importing the session.

Peering Cache Check

IM - 3470: Added a PeeringDB cache status check to Admin Preferences Peering Settings

Peering Settings now displays a status notification to show whether Peering DB cache is enabled or disabled.



For additional information, see link here.

Resource Export to .csv

IM - 3324: Added the ability to export a Resource's field information to .csv

Resource Entry pages now have an "Export As CSV" button, which generates a .csv file containing the Resource's basic field information.

To export the Resource, click the "Export as CSV" button in the header on the Resource Entry Page.




The downloaded .csv file will contain the fields containing values from the Resource Info, Contact Info, Tech Info, and Resource Field Gadget(s), with the field name in the first column, and the field values in the second column.

	A	B	C
1	Name	A QA Entry	
2	Section	Resource Holder	
3	Category	QA	
4	Created	2019-06-27T13:32:02-0700	
5	Modified	2020-01-13T12:34:51-0800	
6	Street 1	123 Main St.	
7	City	Sometown, CA	
8	Zip	12234	
9	Street 1	123 Main St.	
10	City	Sometown, CA	
11	Zip	12234	
12	Phone Main	123456789	
13	Last Billing Date	awd	
14	Country	DZ	
15	Country	DZ	
16	Residential Customer Privacy Enable	TRUE	
17	ns1	ns1	
18	Contract Number	12345	
19	Notes	Test	
20			
21			
22			
23			

Resource Linkage Gadget Updates

IM / CFR - 156: Added "Export to .csv" option for linked resources

The Resource Linkage Gadget Action Menu (wrench icon) now includes an option to export resource field information for the linked resource(s).



To export .csv information for the linked resource, click on the wrench icon for the desired resource, then select "Export to .csv".

A .csv file will download, containing resource metadata and available resource field data.

Example .csv Output

To export .csv information for the linked resource in the Resource Linkage Gadget, click on the wrench icon for the linked resource, then select "Export to .csv". The file will download from your browser.

The .csv outputs data in two columns, arranged as Field Name (column 1) and Field Data (column 2).

Standard resource metadata fields ("Name", "Section","Category", "Created", "Modified") will always be exported for a resource.

Additional custom fields - those that have been added to the Section / Resource Field Gadget and contain data - will also be exported if they exist, and included after the standard metadata information.

In this example, "Hostname", "Resource Holder ID", "Contract Number", "URL", "Text Area", "Text Input", and "Status" are custom fields.


Name	**A QA Entry 3 Child**
Section	Resource Holder
Category	QA
Created	2020-01-30T10:28:42-0800
Modified	2020-02-05T16:20:49-0800
Hostname	test.com.
Resource Holder ID	123
Contract Number	12345
URL	http://google.com
Text Area	Some Text Box Information
Text Input	Some Data Here
Status	Active

For additional information on adding fields to Sections, the Resource Field Gadget, and the Resource Linkage Gadget, see: Customizing Sections , Customizing Fields, and Gadgets.


Log Rotation (Admin Settings / Scheduler Task)

CFR - 127 / IM - 3469: Added automatic log rotation

*The **Admin Preferences** page now contains an option under **Application Settings** to "Delete Logs after X days". By default, this field is set to 180 days.*



To support this, a new default Scheduled Task has been added - "Rotate Logs" - that removes all logs older than the number of days set (default is 180 days).



For additional information on how to edit Admin Preferences or Scheduler Tasks, see Admin Preferences and Scheduler Tab.


ACP Improvements

For detailed information on 6connect ACP (API Composer Platform), see ACP Overview Documentation or request a demo at info@6connect.com.

Admin ACP Settings

IM - 3472: Added ACP Instance Settings to Admin Preferences


Admin Admin Preferences has been updated to include a section for ACP Settings. Users may enter the URL for an ACP instance and associated login credentials.



Once settings have been entered, the ACP Workflow Form Gadget will load the available Workflows from that instance/provided user.

ACP Workflow Form Gadget Updates


IM - 3473: Updated the ACP Workflow Form Gadget to integrate with Admin ACP Settings, updated ui, and added a JSON Response option



The ACP Workflow Form has been updated to automatically integrate with and load the workflows available for the instance/user specified in Admin ACP Settings. Additionally, the option "Display JSON Response" has been added to the form, along with minor ui improvements.

Setting up ACP Access in ProVision

Before using the ACP Workflow Gadget, you must set the ACP URL and user credentials in Admin Admin Preferences.



Enter the ACP URL for a licensed ACP instance, then provide the ACP Username and Password for the user that should be used to execute Workflows. To verify the account, click "Test Configuration" - you will be notified whether the account is valid.


When done, click "Update".

After setup, the ACP Workflows Gadget will load with the available Workflows from your ACP instance, and can be configured to select which Workflow and inputs you wish to use.

Configuring the ACP Workflow Form


The ACP Workflow form is access from the Edit Section page, under "Manage Gadgets".

Once ACP settings have been added to Admin Preferences, the "ACP Workflow Form" Gadget can be added to a Section, and Workflows from the associated ACP instance will be available to select. containing fields to select the desired Workflow to Run, Title, and map input options.



Select a Workflow, then edit the title to display on the gadget and map input options. Input options will vary according to the selected Workflow.

You may also choose to refresh the page once the workflow execution is complete, and/or show JSON results.



Multiple Forms may be added to a Section, in order to run additional Workflows or option settings. When complete, click "Save".

Working with the ACP Workflow Form

Once enabled, the Gadget will show on the resource page for any resource of the section type.

Input the field data necessary for the Workflow - here, it's adding a hostname - then click "Execute Workflow" to process the chain of workflow calls.



If "Display JSON Results" has been enabled, a display modal will appear showing the JSON response of the executed workflow.



When done reviewing the response, click "Close".

If the page has not refreshed, you will see a message informing you whether the Workflow has successfully executed.



In this example, a "Customer Turn-Up" Workflow was selected (created in ProVision's ACP product) that performed six functions with one button click. The successful "Execute" for "Customer Turn-Up" created a new customer resource entry, assigned IPv4 and IPv6 blocks to them, created a DNS zone for the hostname, and lastly created 'A' and 'AAAA' records for the zone.

API Updates

APIv2 Updates

Endpoint links / references for APIv2 Swagger documentation are updated once each release is live, and may not be available prior to release.

Peering File Connectors

IM - 3450: Added an APIv2 Endpoint supporting Peering file connectors .

See APIv2 docs from your instance at: https://host.com/[your instance]/dev/swagger/spec.php?family=peering

Or, public APIv2 docs at: https://cloud.6connect.com/APIv2/spec.php?family=peering

Bug Fixes/Minor Improvements

CFR - 111: Global Search now supports search by full and partial MAC addresses for DHCP Pools and Resource MAC address fields.

CFR - 162: Added an Admin Preferences DNS setting to omit backups for zones with over X number of records.

CFR - 163: Added a DNS Admin Scheduler Task remove backups for zones with that are older than X number of days.

IM - 1940: Updated the "IPAM Alerts" task to be added by default to the Scheduler Task List.

IM - 3134: Removed the following obsolete DNS Global settings from Admin Preferences: Checkzone path, rndc path, and dig path.

IM - 3407: Improved error messaging for misconfigured DHCP Pool pushes.

IM - 3436: Added the "System" category dropdown option to Admin Log Tab.

IM - 3465: Updated Peering tables to display Peer names of up to 255 characters.

IM - 3499: Resolved an issue that prevented IPAM aggregates from merging if located on separate pages of the aggregate list.

IM - 3521: Updated DHCP Host Pool Change MAC address to better handle error cases of removed or corrupted associated IPAM netblocks.

IM - 3554: Improved search to support search by contact First Name / Last Name.

IM - 3555: Resolved an issue where deleted LIRs could still be associated with netblocks and prevent the IPAMv2 Gadget from loading.

IM - 3557: Improved DNS Autogenerator messaging and handling in cases where zones already existed or provided nameservers were not valid FQDN format.

IM - 3571: Removed the now-obsolete "Reports Importer" task from the Scheduler task list.

IM - 3606: Added new error messaging to IPAM Regions to inform users of Geocode API account errors.

IM - 3609: Updated error messages in IPAM Add Aggregate to instruct the user to select a resource if they do not have create permissions on "available".

IM - 3683: Resolved an issue where IPAM "Metadata 2" fields would not save data.

ProVision 7.3.1

ProVision 7.3.1

ProVision 7.3.1 is a minor release with bug fixes.

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Major Features and Improvements in this release:

- ProVision 7.3.1
  - Bug Fixes/Minor Improvements

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes/Minor Improvements

IM - 3686: Removed an Admin-level permissions requirement on performing SWIP functions

IM - 3685: Resolved a DHCP Push error that would occur if pools had duplicate host names

ProVision 7.2.0

ProVision 7.2.0 is a major release with new features, improvements and bug fixes.

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Major Features and Improvements in this release:

- New Features
  - IPAM NAT Support
    - NAT IPAM Metadata
    - NAT/ Scheduler: Rotate Dynamic IPs
  - Numbering Authority
  - IPAM IPv6 Sparse Allocation
  - Resource Field Gadget
  - DNS Records List
  - Licensing
- Additional Features / Improvements
  - IPAM Improvements
    - 'Important' Blocks
    - Parent View Updates
  - Approvals Multi-Assign
  - Peering Improvements
    - Local Peers
    - Expanded Router Edit
    - Improved Messaging
  - APIv2 Updates
- Bug Fixes/Minor Improvements

Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

IPAM NAT Support


NAT tracking is now supported in ProVision IPAM.

NAT IPAM Metadata

IM/CFR -146: Added NAT association support to IPAM

Track NAT associations between public and private (1918) blocks via the IPAM "NAT" Field.

The "NAT" field accepts a single IPv4 CIDR (block or IP) to associate with the current block, and automatically updates the corresponding block with the NAT association.




For additional information, see below, or view at Working with IP Blocks.

Enable NAT

Enable the NAT field by navigating to IPAM Admin Edit IPAM Columns.


From there, ensure that the NAT column is checked (enabled), and customize the column location if desired. Be sure to click "Update" to save any changes.




Create NAT Association

Ensure that the two appropriate IP Aggregates (one public, one 1918 private space) containing the desired blocks to NAT have been added into ProVision. (See: Working with IP Aggregates)


Open IPAM Manage for either aggregate, then open "Edit Block" for the specific block you wish to NAT. (See:Working with IP Blocks)




In the Edit Block dialog, enter the IPv4 CIDR of the corresponding NAT block. When complete, click "Save".



Once the NAT field has been saved, the association will display in the NAT Column.




The corresponding block (here, the private 1918 space block) will automatically have the NAT associated applied - automatically splitting/merging available blocks as necessary to make the association.




Configure NAT to Router(s)

In the IPAM Manage Action Menu, select "Configure NAT" for the NAT'ed block(s).



Then, select the router. Add the custom configuration / interface information for the router and click "Configure".



Working with NAT'ed Blocks

Use caution when managing NAT'ed blocks or aggregates - major actions that change either block's assignment or size (assign, unassign, split, merge, autosplit/cleanup) removes the NAT association.

In this case, complete the necessary high-level block tasks, and then re-save the NAT CIDR association to either block.

NAT/ Scheduler: Rotate Dynamic IPs

IM/CFR - 3373: Added a Scheduler Task, "Rotate Dynamic IPs" for rotation of NAT IP Assignments

The Scheduler task "Rotate Dynamic IPs" reassigns single IPv4 NAT addresses (/32s) after 'x' days to an available address denoted by the Dynamic_Available tags.

Prior to using this task, two blocks (one public, one private) must be NAT'ed in IPAM, the NAT Config pushed to a router, and appropriate blocks tagged with "Dynamic_Base" and "Dynamic_Available". For additional information, see below, or view at Working with IP Blocks and Scheduler Tab.

Before you Begin

Before setting up NAT Dynamic IP Block Rotation, ensure the follow has been completed:


- The public/private IP blocks exist in ProVision (as /32s) and have been set up with NAT Metadata and matching IP Tags
- The NAT'ed blocks have been configured with a router
- The Aggregate(s)/IP's exist in ProVision with sufficient "Available" space to use for Rotating the NAT'ed block(s)
- IPAM Tags match between the NAT'ed blocks and intended available blocks

Add Dynamic Tags to Blocks

After NAT blocks and aggregates have been set up in ProVision with sufficient size, matching IPAM tags, and NAT metadata, you can identify which blocks to use for dynamic rotation by adding the "Dynamic_Base" and "Dynamic_Available" tags.

Go to IPAM Manage and:


- *Add the IPAM tag "Dynamic_Base" to the /32 block(s) currently NAT'ed.*
- *Add the IPAM tag "Dynamic_Available to the aggregate or blocks which match the NAT'ed blocks, and are available for rotation use. If used on a block larger than the Dynamic_Base block, the available block will be automatically split.*



Set up Scheduler Task

Go to Admin Scheduler, Add the scheduler task "IPAM - Rotate Dynamic IPs".

Enter a number for the days to wait (since last configure) until rotation.




Enter scheduled start / end dates, repeat settings, and click "Save" when complete.

The scheduled task will look for NAT'ed, /32 "Dynamic_Base" blocks that have last configuration times older than the provided day count, and rotate those IPs to "Dynamic_Available" blocks. Dynamic_Available blocks larger than than the Dynamic_Base block will be automatically split.

Numbering Authority

IM/CFR - 3322: Added "Numbering Authority" system to IPAM Admin to generate custom-configured number sequences

Numbering Authority allows Admin users to configure domain sets of values, for use with associated ProVision functions or external number tracking.



With Numbering Authority, you can create new numbering domains, track which values have been handed out, free values no longer in use, generate the next sequence value, and associate keys-value pairs to a number value. Numbering Domains may be used with ProVision's APIv2 to generate numbers for use within ProVision instances or custom applications.

Available Domain Types

Four numbering domain types are available in Numbering Authority: Sequential, Multi-Range, UIUDv4, and IPv6 Sparse Allocation.

Sequential:

Provides a sequential number domain starting with '0' and progressing in numerical order. Potential Applications: Ticketing Queues, Customer Numbers

Multi-Range:

User-defined numbers and number ranges (e.g.: 2-3,4-6, 25, 27-28) to include or exclude as available. Potential Applications: VLANs

UIUD v4:

Generates a Universally Unique Identifier according to v4 (Random) standard. Potential Applications: Unique Identifiers

IPv6 Sparse Allocate:

Determines the next IPv6 block to assign to evenly distribute assignments throughout the provided range. Used with the IPAM IPv6 Aggregate Sparse Allocate function. See: Working with IP Aggregates Applications: ProVision IPv6 Sparse Allocation


Working with Numbering Domains

See below for additional information on creating Numbering Domains and using domain actions. Information may also be viewed at Working with IP Aggregates and IPAM Parameters.

Create a Numbering Domain

Go to Admin IPAM Admin, and select the "Numbering Authority" page.

Create a new numbering domain by expanding the "Create New Numbering Domain" section, then typing in a name for the new domain and selecting a domain type.




Enter information for the specific domain type, if necessary, and select whether to allow number reuse. When done, click "Create".

Number Domain Actions

Once a numbering domain is created, you may perform the following actions:


Get Next Value:

Gets the next value in the domain, adds it to the list of used domain values (assigns to the domain), and displays that value to the user.



View Assigned Values:

View values that are assigned to the domain, view used/free status, free assigned blocks, and save key-value metadata to values.



- *Sort by Value and Free/Used values by clicking the column names*
- *To add metadata to a value, enter your information into the "Key" and "Value" fields under Metadata, then click "Save".*
- *Free a value for reuse, if allowed, by clicking "Free" under the value Actions column.*


Delete:

Deletes the numbering domain.

IPAM IPv6 Sparse Allocation

IM/CFR - 3322a: Added "Sparse Allocation" assignment for IPv6 blocks


Uses either a manually configured or automatically generated "Sparse Allocate" Numbering Authority domain algorithm to evenly distribute assignments throughout an IPv6 range.



For additional information, see below, or view at Working with IP Aggregates.


Sparse Allocation options are accessed from the IPv6 Aggregate's Action Menu.

From here, you can enable/disable Sparse Allocation for the aggregate, or Sparse allocate assign the next generated IP block.



Assign the next IP generated by selecting "Sparse Allocate".

Then, select the resource to assign (or create a new one) and click "Assign".



Resource Field Gadget

IM - 3347: Added the "Resource Field Gadget"

The Field Gadget displays the information fields available for the Section and specific Resource that is being viewed.

Users may add enabled fields to the resource, edit field values, and remove fields from the Resource through this Gadget. Field values in this Gadget (such as Hostname, Username, and Password, among others) may also be used by other Resource Gadgets and Provision modules. This Gadget replaces field edit functions previously performed via "Edit Resource".




For additional information, see below, or view at Gadgets.

Before You Begin

Fields must be enabled and added to the Resource's Section before they can be used in the Field Gadget.

Fields enabled in a Section (pictured below) will be available to add to the Field Gadget for any Resource of that Section.




Working with the Field Gadget


Once fields have been enabled for a Section, they will be available to select in the "Add New Field" dropdown.

To Add fields, click the "Edit" Button at the bottom right corner of the Field Gadget.

Then, next to "Add New Field:", select one of the available fields from the dropdown, and click "Add".




Once added, the field will be available to edit or remove. Edit field value(s) as desired, then click "Save".



DNS Records List

CFR - 151: Added a new DNS Records sub-tab under the DNS Tab


The DNS Records sub-tab provides a global list records for expedited searching, filtering, adding, and editing of DNS Records.



For additional information, see below, or view at Working with DNS Records.

From the DNS Tab, click on the "DNS Records" sub-tab button, or select it from the DNS dropdown menu.


All DNS records available in ProVision displays in a single Record List, along with Host, Type, Value, and Last Queried information.



Filter Records

Search for specific records by filtering by Host, Type, Comment, Value, Last Query, Last Modified, Record TTL, or Status.


After entering your filter criteria, click "Filter".



Work with Records


For each record, you may:

- *Click the "Check" button to run an DNS Monitor error check on the record*
- *Review or change record permissions by clicking "Perms" (Admin only)*
- *Delete the record by clicking "Delete"*
- *Review or Edit record details by double-clicking on the row for the desired record.*
    - *Review record revision dates or enter your desired edit, then click "Save changes" to complete.*




Add a New Record

Next to "Record List", select the desired record type, then click "Add Record".



Enter the record information for the record type. When done, click "Save Changes".




Licensing

IM - 3356: Added a ProVision Licensing Management Page to Admin Settings


The License page displays current product license details such as Product, Type, Versions, Expiration, Email, and the option to add/update the 6connect License Key(s). See Admin Preferences.

From the Admin Settings page, click "Manage License".



Current license details for ProVision, and other affiliated 6connect products will display.

To add/update a License Key, paste the key provided into the "Update License Key" box, and click "Update License".



Additional Features / Improvements


IPAM Improvements

Multiple improvements have been made to the IPAM Manage interface, including:


'Important' Blocks

IM/CFR - 3301: Added the ability to mark a block as "Important".

"Important" blocks display with a yellow background highlight. By default, any block that has been manually assigned, unassigned, or other high-level interactions will be automatically marked as "important" . See Working with IP Blocks.




Blocks *may be manually marked/unmarked as "Important" from the "Edit Block" interface or API.*



Parent View Updates

IM - 3308: Added toggle link to "Switch to Parent View" in IPAM Manage

Quickly Toggle back and forth between standard Block View and Parent View, where the parent block is displayed along with access to block tree and child assignment information. See Working with IP Blocks.




IM/ CFR - 3271: Updated the IPAM Manage "Has Children" status to include the associated resource name for the immediate child block.

Parent View now displays the resource assigned to immediate child blocks.



IM - 3307: Added Allocated/ sub-assignable block holders to the IPAM Manage Resource Block Tree.

From Parent View, click on any parent block to view the Block Tree with the assignment, allocated, and subassigned Resources.



IM / CFR - 3272: Updated text descriptions on the IPAM Manage Auto-Split template


We now help you out by giving examples for "power of 2"!

Approvals Multi-Assign

IM - 3303: Added the ability to assign multiple groups to an approval action.

From the Approvals Tab, select the Actions & Permissions sub-tab Actions tab.

For any Action, click "Assign Group", then select one or more Groups to apply the action policy to.




Peering Improvements

Local Peers

IM / CFR - 3289: Added "Local Peer" options to ProVision Peering

"Local Peers", peers that are 'private' or not registered with PeeringDB, may now be created in ProVision and used for session creation.


Local Peers will display in their own "Local Peers" list on the Peers page.



For additional information, see below, or view at Managing Peers.


Add a Local Peer

Add a new local peer by going to the Peering Tab Peers subtab, and clicking "Add Peer".



In the "Add Local Peer" form, enter the Peer details including Name, ASN, IPv4 or IPv6 Address, Route-Set, select an Exchange Option, and add notes if desired.

When finished, click "Create".




The Peer will be added to the "Local Peers" list, and be available to use while creating a session.




Create a Session Using a Local or Custom Peer


You may use existing Local Peers when creating a new session, or create a new custom Peer from the Create Session page.

Click "Add Session" from the Peering Sessions sub-tab.






*Under the **Destination** section, you may look up an existing Local Peer under "Local Peer Lookup" by selecting the peer name and address, and the destination fields will be automatically populated.*




If the Peer does not already in ProVision, you may add a new Local or Custom Peer by directly typing the Peer Name, ASN, and IP in the Destination fields.

When complete, click "Create".



The Local Peer Session will be added to the Session List.




Expanded Router Edit


IM-3327: Added the ability to edit router information directly from the Peering Router Details page.

All router information fields - Make, Model, IP address, Hostname, Username, and Password - may be edited from the Peering Router Details page. See below for additional information, or go to Peering Routers.

To edit a router field, click the "Edit" icon (pencil), and input the desired change.




When complete, click the "Save" icon.



Improved Messaging

IM - 3429: Added Success/Fail Messaging to Peering Router Sessions "Delete All" button.



APIv2 Updates

Follow endpoint links for detailed APIv2 Swagger documentation, updated once each release is live.

IPAM Generate DNS

IM - 2940: Added APIv2 endpoint: POST /ipam/netblocks/generate_dns

Automatically create a PTR record inside the proper zone, when provided IP and Hostname.

POST	/ipam/netblocks/generate_dns Generates DNS Zones and records based on the provided netblock
Description:	Returns a list of dns zones and records. If dry_run is provided, no records and zones will be created.
ipam_generate_dns	{
cidr*	[The IP block in CIDR format string]
group_id	integer($int64) DNS Group ID
domain	string
zone_types	[DNS Zone type. Use "forward", "reverse" or both string]
record_types	[DNS Records type. Use "forward", "reverse" or both string]
dry_run	boolean Use this option in order to see if your request is acceptable without committing the changes
}	

IPAM Soft Merge Netblock

IM-3275: Added APIv2 endpoint: PATCH /ipam/netblocks/{id}/soft_merge

Friendlier, gentler version of /merge API endpoint.This endpoint will merge as much as it can and skip over areas where it cannot cleanly merge blocks together. Returns whether it successfully merged every IP block or just partially, and list all unmerged blocks.

PATCH	/ipam/netblocks/{id}/soft_merge Merges IP Blocks under an aggregate wherever possible and reports on outcome
Description:	Friendlier, gentler version of /merge API endpoint.This endpoint will merge as much as it can and skip over areas where it cannot cleanly merge blocks together. Returns whether it successfully merged every IP block or just partially, and list all unmerged blocks.
soft_merge_netblock	{
id	integer($int64)
cidr	string
stopOnResourceMismatch	boolean
stopOnTagMismatch	boolean
stopOnRegionMismatch	boolean
}	

Resource GET Attribute Updates

IM-xxxx: Updates to APIv2 endpoint: GET /resource/

GET calls to /resources have been updated so that the return will always be an array of resource objects. Previously, it was possible to phrase a call so that it returned a single resource not encapsulated in an array. For consistency, this exception to the normal return format has been eliminated.

Example Value | Model


```
{
  "id": "string",
  "name": "string",
  "slug": "string",
  "type": "string",
  "parent_id": "string",
  "category_id": "string",
  "date": "string",
  "modified": "string",
  "attrs": [
    "string"
  ],
  "options": [
    "string"
  ],
  "field_type": "string",
  "help_block": "string",
  "permissions": {}
}
```




Bug Fixes/Minor Improvements

IM - 2124: Updated IPAM to support aggregates of 0.0.0.0/n

IM - 3229: Updated User-Group permissions to prevent users from editing/deleting permissions on a User Group to which they belong

IM - 3243: Action buttons are now hidden in the Resource Linkage Gadget for Read-only users

IM - 3244: Updated the Notes Gadget to prevent edits by Read-only users

IM - 3260: Blocked the 'Remove' action for approval group assignments if a pending approval request is outstanding for the group

IM - 3300: Fixed a bug that would occur in the IPAM Gadget Smart Assign when a resource was selected under advanced filter settings

IM - 3305: Resolved an export error in Logs where only the first log record would successfully export

IM - 3317: Minor text and layout updates made to the Admin -> IPAM Regions page

IM - 3318: Fixed an issue in IPAM Regions "Add Region" where a new single-word address value would disappear into the void. Regions may now be addressed as "Cher", "Bono", or "Adele" - we won't judge.

IM - 3320: Resolved an issue where certain IPAM aggregates would fail to display the "Ignore Assignments" checkbox while performing the "Clean Up" action

IM - 3348: The resource selector in IPAM "Add Aggregate" now displays a portion of the resource list prior to a search term being entered

IM - 3355: Minor text updates made to DNS error messages

IM - 3368: Scheduler tasks set for weekly repeat now run at the correct time for the specified timezone

IM - 3385: Updated IPAM Manage Edit Block to include the ability to deselect the LIR value

IM - 3389: Reordered and updated the display names of the "Task" selector options under Scheduler Add Task

IM - 3394: Resolved an issue where DHCP Pool assignments would fail if VLAN filter criteria were provided

IM - 3405: Updated the IPAM Manage "Assigned To:" resource filter option to include DHCP Pools

IM - 3428: IPAM Log timestamps now correctly display in Safari

IM - 3430: Peering IXs -> Communications Log timestamps now correctly display in Safari

ProVision 7.2.1

ProVision 7.21 is a minor release with improvements and bug fixes.

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Major Features and Improvements in this release:

- Improvements
  - Resource Linkage Updates
  - Peering Session Import Updates
  - NAT Dynamic Rotation
- Bug Fixes/Minor Improvements


Contact 6connect at info@6connect.com to schedule a demo or get more information.

Improvements

Resource Linkage Updates

CFR - 152: Added "Copy" options to the Resource Linkage Gadget

Two "Copy" options have been added to the Resource Linkage Gadget, to allow users to copy and paste linkage data into other applications.



To copy all rows in the Resource Linkage table, click "Copy table content" at the top of the gadget. To copy a single row, click on the newly-returned action menu (wrench icon), and select "Copy row". After copying, paste into your desired application.

Peering Session Import Updates

IM - 3451: Added multiple improvements to Import BGP Sessions, to better handle non-peering DB and anonymous peers.

Multiple improvements have been made to importing peering sessions:

- *Session import will no longer fail with non-peeringdb peers.*
- *“Anonymous peers” (peers not in peeringdb or local) do not show broken links in the session details*
- *Added multi-edit to session import to manually change session information prior to import.*

To edit a session loaded in the importer, click on the wrench icon for the session.



Change the fields as desired, and click "Done" when complete.



NAT Dynamic Rotation

IM/CFR - 3452: Added the ability to restrict the dynamic NAT rotation scheduled task to a single IP

Bug Fixes/Minor Improvements

IM - 3453: Updated IPAM Manage Last Updated time to display the full datetime after being assigned from the NAT dynamic rotation task.

IM - 3460: Added error message improvements to IPAM Manage to indicate ASN value must be an integer.

IM - 3461: Resolved a bug in IPAM Gadget where blocks with an existing LIR value could not be saved without changing LIR.

ProVision 7.1.0

ProVision 7.1.0 is a major release with new features, improvements and bug fixes.

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Major Features and Improvements in this release:

- New Features
  - APIv2 Documentation
  - Approvals
    - Admin Approvals Tab
    - DNSv3 Approvals Updates
    - Scheduler Approvals Updates
  - ACP ("Workflows") Gadget
    - Working with the ACP Workflow Form
    - 6connect ACP (API Composer Platform)
  - Linked IPs Gadget
  - SAML Authentication Support
    - SAML Setup
    - SAML Login
  - DUO Mobile Authentication Support
  - Peering Communications Page
- Additional Features / Improvements
  - DNSv3 Improvements
  - Scheduler Updates
    - New Scheduler Tasks
    - Scheduler "Forever" Tasks Are Back
  - IPAM Gadget Updates
  - Log Updates
  - IPAM Regions Updates
    - Applying a Google Geocoding API Key:
  - IPAM 'Advanced' Button
- Bug Fixes/Minor Improvements

Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

APIv2 Documentation

Public APIv2 documentation is located at https://cloud.6connect.com/APIv2/.

APIv2 documentation includes:


- IPAM API
  Includes actions for LIRs, IP aggregate and block management, VLAN, IP Rules, and SWIP.
- Resource API
  Includes actions for managing the ProVision Resource System.
  The resource API provides CRUD endpoints for resources, resource attributes, resource attachments and resource backups.
- DNS API
  ProVision DNS API allows you to manage DNS Zones, Records, Servers, Groups and ACLS.
- Users API
  Includes actions for ProVision Users, permissions and actions.
- Usergroups API
  Includes actions for ProVision Groups, permissions and actions
- Scheduler API
  The API Allows you to easily schedule tasks.
- API Composer Platform
  API Composer Platform (ACP) is an additional module in ProVision to help automate frequently used combinations of calls.

Approvals

CFR / IM - 2937: New Approvals Module integrated with DNSv3 - See Approvals.

The Approvals module stores and queues DNS actions made by selected User Groups, and sends those actions to a Pending Changes list for administrative review.

Later, an administrator (or combination of administrators) can approve or reject these stored actions.



Approvals features include:

- Ability to associate existing ProVision User Groups with "Deny", "Approve", or "Requires Approval" permissions on DNS actions.
- Supports Approval by one or more Admin Groups
- Approval restrictions may be high level or fine-grained; set for the whole of DNS, by DNS Family, Action Type, or any combination thereof
- Option to send notification emails
- Bulk Approve or Reject requests
- View user approval event history
- Filter and Sort Approval request list
- Notification display on DNS pages with pending change requests


Approvals-related updates include:

Admin Approvals Tab

A new "**Approvals**" tab has been added to the Admin area of ProVision, containing two sub-tabs - "**Pending Approvals**" and "**Permission Groups**", the primary areas from which to manage Approvals items.

- **Pending Approvals Sub-Tab**


  The ***Pending Approvals*** sub-tab lists Pending approval requests for the current Admin user for which they have permissions to "Approve" or "Reject". The Pending Approvals list may be sorted by Name, Family, Action Type, Updated time, or by submitted user and searched by resource name.



  Approving and Rejecting change requests may be done individually, or in bulk by selecting multiple item checkboxes / clicking the "select all" checkbox. Once selected, an option to Approve/Reject all selected items will appear. If notifications are enabled for the Group or Action, an email will be sent notifying the request submitter of the status change.
  At the bottom of the page, historical approval items for the user are shown. The user may filter their previous approval items by Executed, Approved, Rejected, or Pending by Others (for items requiring multiple Groups to approve). For more information on the **Pending Approvals** subtab, see Pending Approvals.


- **Permission Groups Sub-Tab**

  The ***Permission Group*** page contains areas to manage what type of Approval permissions each User Group has, and on what actions. There are two tabs available under Permission Groups - **Groups** and **Actions**.



  There are two tabs available under Permission Groups - **Groups** and **Actions**.


  - In the **Groups** tab, each ProVision User Group is listed. Clicking the "Assign" button for a group brings up a checklist to select what policy to apply to the group for what Family and Actions (i.e. DNS Zone 'Add' or DNS Group 'Update').



Policy Settings include:


- **Deny** : All users in the group will have the selected actions automatically denied at an attempted change.
- **Must Approve Action:** A User in the group must approve or deny change requests submitted for the selected Family / Action(s), for any Group requiring "Action to be Approved" for the same action(s) in order for the change to execute. If multiple groups are set as "Must Approve Action" for the same type of change, then the change will be held as "Pending" or "Pending by Others" until a user from *each group* approves the change request.
- **Action to be Approved:** Users in the group will have the selected actions submitted to Pending Approvals for the change to be approved or denied. A second Permission Group must exist with the "Must Approve Action" policy assigned to the same action for the submittal to succeed.

In the list of Permission Groups, clicking on a Group name will bring up the permission details for that Group.




Here, you may view, edit, or remove current policy assignments, and enable/disable notification emails for each action type. The list of assigned actions for the group may be sorted by Family or Method, and filtered by Family (here: "DNS Groups").


- The **Actions** Tab lists the group permissions organized by Family/Action type. Expanding a Family shows the available actions, and a matrix of how many groups are assigned under each policy.



Clicking the "View Groups" button shows the list of each group assigned to that action, with the option to unassign a group.



The "Assign Group" button lets you assign a Group and Policy to that action. This performs the same function as the earlier assignment window - but is organized to only assign a single group/policy to that action, rather than assigning multiple actions to a group.




For more information on the Approvals **Permission Groups** subtab, see Permission Groups

DNSv3 Approvals Updates

Updates have been made in DNSv3 supporting the Approvals system:

- **"Resources Awaiting Approval" module**

  A "Resources Awaiting Approval" module will now display in selected DNSv3 pages to Users with Admin / Approval permissions, if a change has been submitted on that page that is pending approval by the User's Approval Group. See DNS Tab and Approvals,



Scheduler Approvals Updates

Added two new scheduler tasks in support of Approvals:

- **Approvals - Process Subscription**

  The "Approvals - Process Subscription" task processes approval request events and handles the sending of notification emails to subscribed Approvals Groups.

  If Approvals are in use with notifications, it is recommended to create this task with a run time of "every 5 minutes" and no end date.

- **Approvals - Delete events older than 1 month**


  The "Approvals - Delete events older than 1 month" task deletes any Approvals history events older than 30 days. It is recommended to run this task monthly to clear out obsolete approvals items and reduce approvals page load time.

  For more information, see Scheduler Tab and Approvals.

ACP ("Workflows") Gadget

CFR / IM - 3119: Added the ACP "Workflows" Gadget to the available Gadgets list for Resource Entry pages. See Gadgets.

The ACP Workflows Gadget allows users to specify and execute Workflows (created in the ACP product) on a ProVision Resource Entry page.




Working with the ACP Workflow Form

The ACP Workflow Form is a Gadget add-on connecting 6connect's ACP (API Composer Platform) with the ProVision interface to run Workflows.

See below for additional information on enabling and using the ACP Workflow Form.

Customers with an ACP license can select and add the "ACP Workflow Form" Gadget to a Section, containing fields to select the desired Workflow to Run, Title, and map input options. Multiple Forms may be added to a Section, in order to run additional Workflows or option settings. When complete, click "Save".



Once enabled, the Gadget will show on the resource page of the section type. Input the field data necessary for the Workflow, and click "Execute Workflow" to process the chain of workflow calls.




In this example, a "Customer Turn-Up" Workflow was selected (created in ProVision's ACP product) that performed six functions with one button click. The successful "Execute" for "Customer Turn-Up" created a new customer resource entry, assigned IPv4 and IPv6 blocks to them, created a DNS zone for the hostname, and lastly created 'A' and 'AAAA' records for the zone.

6connect ACP (API Composer Platform)

6connect ACP (API Composer Platform) is a separate plugin product that enables you to create and share API workflows via a graphical editor.

ACP & Workflows

With ACP, you can pull in data from multiple APIs and easily combine it into a new API endpoint – on the fly – with no code necessary, and share your setup using JSON for convenience or adding to a version control system.



In the example above, a "Customer Turn-Up" Workflow was created in ProVision's ACP product that chained together six ProVision API calls into one function.

When clicking "execute", a prompt displays requesting values for required inputs - such as the customer name for the newly created resource - before continuing.


Then, a successful "execute" creates a new customer resource entry, assigns both an IPv4 and IPv6 block to that resource, creates a DNS zone for the hostname, and lastly creates 'A' and 'AAAA' records for the zone.

For more information, see https://www.6connect.com/acp/. To schedule a demo, visit https://www.6connect.com/demo/ or send an email to info@6connect.com.

Linked IPs Gadget

CFR / IM - 3066: Added a "Linked IPs Gadget" to the available Gadgets list for Resource Entry pages. See Gadgets.

The Linked IPs Gadget lists IP blocks assigned to Linked Resources (via the Resource Linkage Gadget).



SAML Authentication Support

CFR / IM - 3137: Added support for SAML login, and authentication settings to AdminAdmin Settings Authentication Options. See the Authentication section under Admin Preferences.

SAML is a Single Sign On (SSO) authentication method that uses an external identity provider to authenticate a user at their first login, saving a token to the user's browser that is then used for subsequent logins, so that the user does not need to re-submit credentials.



SAML Setup

Before configuring SAML in ProVision, you must have an account set up with an Identity Provider (IdP) and ProVision users / groups set up in the IdP.

Set up the IdP


To use SAML authentication, you will need SAML set up for your instance with an Identity Provider (IdP), such as *Microsoft ADFS, OneLogin, Elastic SSO,* or others. You can view a list of available SAML IdPs at Wikipedia's SAML based products page.

Users and Permissions:

User credentials will need to be created and associated with ProVision permission group names via the IdP. All user creation, management and permissions handling occurs via the IdP, externally from ProVision.

Configure SAML in ProVision

ProVision setup for SAML is located in Admin Admin Settings Authentication Options.



Under **SAML Configuration**:

Enable SAML authentication by clicking the checkbox next to "Enable".

The following fields are required and will need to be obtained from the IdP:

- **User Attribute(Required):**
- **Group Attribute(Required):**
- **IdP Metadata(Required):**

Under **SAML Service Provider Configuration:**

- **Sign logout request:**
- **Sign redirect request:**
- **Unencrypted Assertions from IdP Will be rejected:**
- **Private Key:**
- **Certificate (Required):**

Links are provided below the configuration settings for the ProVision SP Metadata file in php and xml format, which will be needed to provide to the IdP.

You can test the configuration by clicking the "Test SAML Configuration" button, a new page will open giving health check information for your provided attributes.

SAML Login

Once the correct configuration has been established and users set up for SAML in the IdP, users will be able to use SAML logins.

Documentation Note: Depending on the IdP used, some screens may appear different from what is shown here.

Initial Login:


The initial login process occurs for the first time a user logs in, and anytime afterwards if the browser token is not present (e.g., cookies are cleared from the browser, the browser closed, or a new browser is used).

From the ProVision login page, select SAML from the authentication options dropdown - you do not need to enter Username or Password.



You will be redirected to the IdP site as set up in the Admin Configuration - here, we are using Microsoft ADFS (Active Directory Federation Services).

Log into the IdP site using your SAML credentials, and click "Sign In".



If the sign in is successful, you will be logged into the ProVision home page.

Subsequent Logins:

After the initial login via the IdP (as long as the auth token is present) users will be able to login to ProVision simply by selecting the "SAML" options from the ProVision login page without entering credentials.




The auth token may be destroyed or not available if browser cookies have been cleared, a different browser used, or the browser fully closed, depending on security settings. In these cases, the user will need to sign in again via the IdP.

DUO Mobile Authentication Support

SEC-14 / IM - 3200: Added support for DUO Mobile authentication options to Admin Authentication Options. See the Authentication section under Admin Preferences.

To use DUO Authentication, an account must first be set up with DUO. Once an account is set up, obtain the Integration Key, Security Key, and DUO API Host name.


Enter those items into Admin Authentication Options DUO Mobile Configuration, and click "Update" to save your changes.



Peering Communications Page

CFR/ IM - 3261: Added Peering "Emails" Sub-tab to the Peering Tab (Accessible to Global Admins). See Peering and Peering Emails.

The Peering "Emails" page associates a single company peering email account (such as peering@company.com) with your ProVision instance, creating a 'shortcut' email system to keep on top of the most recent peering requests while in ProVision.



Load, view, and reply to the most recent 3 days of emails received at that address, view requests sent from ProVision's Exchange Communications page, and process emails associated with ProVision Peers.

Freely trim down the ProVision 'Inbox' to keep only those emails on your short term ProVision To-Do list; 'deleting' ProVision emails only affects what messages are loaded into the ProVision instance - your original messages remain intact on your original email server.


The Peering Emails page is only accessible to Administrative users in the primary "Global Admins" User Group. Ensure that Peering Administrators using ProVision's Peering Emails area are included as members of that group for full access.

Additional Features / Improvements

DNSv3 Improvements

Multiple improvements have been made to DNSv3 areas:


- IM - 2500: Updated the DNS "Scheduled Push" interface to be more user-friendly
- IM - 3019: Added the ability to view/download the zone file to to Zone Details page
- IM - 3046: Added ability to select "Delete all zones" when deleting a DNS Group
- CFR/ IM - 3053: Added the ability to import Zone/Record information to an existing zone via a "Import File" button in the Zone Details page
- IM - 3054: Added additional fields to / support for S64x86 KNOT connector
- IM - 3062: Added individual "Push" buttons to the "Attached Servers" section in the Zone Details page.
- CFR/ IM - 3180: Added "Public IP" field to DNS S64 server types.
- IM - 3126: Added a permissions shortcut button ("Perms") throughout DNS, for quick CRUD permissions adjustments to specific DNS resources. Available to Admins only.




- IM - 3202: Added "Advanced Settings Inherited by the Zones" to DNS Group Default Parameters. New zones created from the Group will also inherit the Advanced Settings fields as set from the group defaults.

  Open the "Advanced Settings Inherited by the Zones" module by going to any DNS Group and opening the "Group Default Parameters".

  The Advanced Settings module will be at the top of Default Parameters area. To expand it, click on the expansion arrow on the right side of the header bar.




Once expanded, settings may be entered for DNSSEC, Dynamic Updates, Master-Slave Handling, Lists, and free lines.



Save your changes!

Important - to ensure that your changes are saved, click the "Save Group Defaults" button under the Default SOA Values section - this save button will save any changes made to Advanced Settings, Default Nameservers, or Default SOA Settings.



For detailed information on DNS, see DNS Tab, Working with DNS Groups, DNS Zones Overview, Working with DNS Zones, and DNS Administration.

Scheduler Updates

New Scheduler Tasks

IM - 3104: Three new scheduler tasks have been added: *Delete Archived Data*, *Approvals - Process Subscriptions*, and *Approvals - Delete events older than 1 month. See Scheduler Tab and Approvals.*

Delete Archived Data

The "Delete old archived data" task removes data of the following types older than 30 days from your ProVision instance:

- *Archived resources*
- *Logs*
- *System logs*
- *Statistics*

Be sure to use care with running this task, to prevent accidental deletion of log data that may still be necessary for reference. It is typically recommended to run this task once every 1-3 months to reduce log data volumes.

Approvals - Process Subscription

The "Approvals - Process Subscription" task processes approval request events and handles the sending of notification emails to subscribed Approvals Groups.

If Approvals are in use with notifications, it is recommended to create this task with a run time of "every 5 minutes" and no end date.

Approvals - Delete events older than 1 month

The "Approvals - Delete events older than 1 month" task deletes any Approvals history events older than 30 days. It is recommended to run this task monthly to clear out obsolete approvals items and reduce approvals page load time.

Scheduler "Forever" Tasks Are Back

IM - 2422: "Forever" Tasks are once again able to be set in the Scheduler. See the Scheduler Tab documention.


To set a "Forever" task, just leave the "End Date" field blank when setting up the scheduler task.

IPAM Gadget Updates

The IPAMv2 Gadget has been updated to more closely match the functions available in IPAM Manage. See: Gadgets and IPAM Tab documentation.

- IM - 3144: Added Split, Merge, and Assign functionality to the IPAMv2 Gadget Action Menu.
- IM - 2155: Updated IPAMv2 Gadget Action Menu to correlate to IPAM Manage available actions and functionality, including multi-select.

Action Menu (right click) updates include the additions of Split, Merge, Assign, Unassign - Skip Holding, IP Rules, Templates, and Multi-block Edit.




To select multiple blocks in the IPAMv2 Gadget, left click on a single block, and the shift-click or cmd-click to select additional blocks. Once all desired blocks have been selected, right click to show the multi-block Action Menu.

Log Updates

IM - 3107: Added a color-coded "Chart View" to Admin Logs. See: Log.


To view the graphical chart version of Logs, click the "chart" toggle on the bottom right of the search fields. Each log event will be displayed as a color-coded box.

View log details by hovering the mouse arrow over an event box.



IPAM Regions Updates

IM - 3156: Updated IPAM Regions to support a Google Geocode API key setting (required for proper geolocation function of IPAM Maps). See: IPAM Tab and IPAM Parameters.



IM - 3214: Added Address validation if IPAM Maps is enabled, and a Google Geocode API key field setting has been provided.

Valid addresses (according to Google's API) will show a green check mark next to the address field, invalid addresses (unable to be mapped) will show a yellow exclamation mark.



Google Geocode API Key Requirement

Due to changes in Google's licensing and Geocoding API, the previous geolocation method used in ProVision is no longer supported. IPAM Regions now requires a Google Geocode API Key in order for IPAM Maps to properly determine a Region's location.

6connect is exploring adding additional map integration options for ProVision.

Any customers who require an alternative geocode option supported apart from Google Geocode API key, please contact us at feedback@6connect.com.

Applying a Google Geocoding API Key:

Step 1: Obtain a Google Geocoding API Key


To get a Google Geocoding API Key, follow the instructions listed here:

How to get a Google Geocoding API Key

Note: In order to obtain a Google Geocoding API Key, a company must have a subscription enabled to Google Cloud Platform Console.

Step 2: Assign the API Key to IPAM Regions

Once assigned a Google Geocoding API Key, paste the API key into the IPAM regions page under "Apply google geocode api key" and click the "Assign" button.



IPAM 'Advanced' Button

CFR - 143: The IPAM "Advanced" button has been brought back, by popular demand. See:IPAM Tab



*The IPAM "Advanced" Button opens the **IPAM Manage** screen for all blocks, under all aggregates. See Working with IP Blocks for more information on working in IPAM Manage.*

Bug Fixes/Minor Improvements

IM - 2524: Fixed minor console errors in the DNSv3 Server Settings page.

IM - 2657: Updated the default 'Router' Section to be a required Section, preventing deletion.

IM - 2668: Resolved a Scheduler calendar selector display issue where "End Date" would display as the day after the user provided value.

IM - 2948: Improved label display and behavior in the Dashboard IP Charts gadget.

IM - 2988: Updated Smart Browse to assign the next available single block for /32s and /128s, if the first block found meeting criteria is reserved via an IP Rule.

IM - 2998: Updated APIv1 IPAM Get Blocks call to better handle ONLY_FULL_GROUP_BY setting.

IM - 2999: The APIv1 IPAM Update 'tag' attribute has been updated to remove duplicate tags.

IM - 3025: DNSv3 now allows the last nameserver under "Group Default Parameters" to be deleted.

IM - 3031: Updated sample .csv links and page layout in the Admin Data Import tab.

IM - 3035: Added an error message response when 'Name' and 'Code' fields are not provided when adding a new IPAM Region.

IM - 3041: The IPAM Configuration "Scanner Max Block Size" option is once again editable (API only feature).

IM - 3042: the Mask/Host field in Edit IPAM Columns / IPAM Manage has been disabled by default. It may be re-enabled at any time in IPAM Admin Edit Columns.


IM - 3044: Fixed an issue in the IPAM Gadget where the IPAM Edit Block modal would display partially offscreen while direct and smart assign modules were expanded.

IM - 3045: Added error messaging to IP Rules - Create New Rule if block positions have not been provided.


IM - 3047: Resolved an issue in IPAM Manage where the 'Merge' option was not updating properly after unassignment.

IM - 3055: Resolved a PowerDNS-SQL push connection issue.

IM - 3056: Added subassignable status (blue arrow display) to the IPAM Gadget address column.



IM - 3057: Added the ability to "clear" error alerts from DNS records and zones (Note: use with caution!).



IM - 3058: Fixed DNS record pagination on DNS Zone View pages.

IM - 3059: Updated the IPAM gadget to no longer erroneously show IP Aggregates/Split Parent blocks.

IM - 3061: Updated DNS Groups' Zone list individual push buttons to limit the push to the specific DNS Group.

IM - 3064: Minor bug fixes made to DHCP module creation.

IM - 3069: DNS "Add Server" IP/FDQN field will now be grayed out when using non FQDN/IP based services.

IM - 3094: Fixed an issue in IPAM Regions Edit Regions list where the "Address" value would not save for newly created regions.

IM - 3095: IPAM Regions now checks for duplicate name values when creating a new IPAM Region.

IM - 3096: IPAM Admin Subnet lists have been updated to check for valid values when adding a subnet.

IM - 3099: Improved error handling and messaging in the DNSv3 error monitor

IM - 3118: Removed extraneous border display from the DNS Gadget.

IM - 3121: Updated the Resource Linkage Gadget with minor interface changes, and for automatic reciprocal links.

IM - 3129: Revised DNS Error check messaging to be more informative.

IM - 3130: Resolved save issues with S64x86 DNS server types.

IM - 3133: Updated the IPAM Gadget and IPAM Manage Block Edit modals to restrict height to the visible screen area.

IM - 3134: Added DHCP Pool links to the IPAM Manage interface.

IM - 3139: Improved push handling of DHCP pools when a pool is duplicated to multiple DHCP groups.

IM - 3140: DNS Bind server settings "Freelines" field now correctly supports multi-line freeline entries.

IM - 3141: Resolved connection errors that would sometimes occur when clicking "Test Connection" with DynDNS servers.

IM - 3145: Fixed handling of Aggregate Locations/ map coordinates in IPAM Map.

IM - 3157: Resolved an issue in IPAM Manage where "Propagate to Children" would not propagate IPAM Tags.

IM - 3164: Added the parameter "assignedResourceId" for IPAM / DHCP direct assign to APIv1.

IM - 3179: Updated handling of Gadgets in the Resource Entry page when viewed in Edge /IE browsers.

IM - 3185: DNS Add Zone Clone Zone option no longer prevents the clone if a record error exists in the zone.

IM - 3190: Users are no longer limited to 50 IPAM Tags in IPAM Admin. Add tags to your heart's content!

IM - 3191: When adding IPAM tags to a block in IPAM Mange "Edit Block", a scroll bar will now appear if over three lines of tags have been added.

IM - 3219: Improved LDAP authentication system.

IM - 3239: Truncated very long resource names appearing under the "Recent Assignments" area of IPAM Aggregates.

IM - 3242: Added informational message to the PeeringSessions page if the user does not have sufficient permissions.

ProVision 7.1.1

ProVision 7.1.1

ProVision 7.1.1 is a minor release with improvements and bug fixes.

Local Software Requirements Update

⚠ For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Features and Improvements in this release:

- ProVision 7.1.1
  - Minor Features & Improvements
    - Peering Routers: View all Router Sessions / "Delete All Sessions" Button
    - Updated Peering Lists
  - Bug Fixes/Minor Improvements


Contact 6connect at info@6connect.com to schedule a demo or get more information.

Minor Features & Improvements

Peering Routers: View all Router Sessions / "Delete All Sessions" Button

IM-3309: Added a list of Router Sessions to the Router Details page, and a button to delete all sessions from a router. See: Peering Routers.


View all sessions associated with a router by going to that router's detail page and scrolling down to the "Router Sessions" section. Clicking on any session will open up the Session Details for that session.



Delete all sessions in ProVision for the router by clicking "Delete All Sessions" under Router Sessions.

Updated Peering Lists

IM - 3287: Added Router Name/ Router Link to the Peering Session List.



IM - 3286: Added Pagination to Peering Lists



Bug Fixes/Minor Improvements

IM - 3264: Resolved an issue in the POST IPAM Netblocks APIv2 call where metadata field values were dropped.

IM - 3269: Fixed an error with the DNS "Clear Errors" button where an error message of "The record has been modified after has been pushed" would appear when no modification had been made.

IM - 3270: Improved handling of PTR records by template with the DNS Error Monitor.

IM - 3277: Updated the IPAM Rules: Create New Rule UI to better handle large quantities of provided positions.

IM - 3285: Fixed an issue where the Peer List "Has Sessions" check mark would not sync with session updates.

IM - 3298: Updated DNS Add Server page to fix a "The password must be of type string" error message that would appear when performing multiple saves on the same server edit screen.

IM - 3304: Updated APIv2 Swagger Documentation to not use placeholder ID values in "Try It Now".

IM - 3310: Updated error message provided when the Peering Email credentials fail.

IM - 3312: Resolved an issue where Peer's contact information was not displaying on the Peer Details page.

IM - 3314: Removed case-sensitivity from DNS error monitor record validity checks for all records (except TXT).

IM - 3315: Contact information on the Peering "Peer Details" page now correctly shows.

IM - 3316: Resolved an issue where an empty SAML Settings field prevented Auth Settings from saving in a newly created instance.

ProVision 7.0.0

ProVision 7.0.0 is a major release with new features, improvements and bug fixes.

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Major Features and Improvements in this release:


- New Features
  - IPAMv2 - New IPAM Tab Updates
    - IPAM Tab
    - Aggregate Blocks List
    - Host Utilization
    - IPAM Manage
  - DHCPv3 - New DHCP Tab Updates
    - DHCP Groups:
    - DHCP Servers:
    - DHCP Pools:
  - Peering v2 - New Peering Tab Updates
    - General
    - IXs Subtab
    - Routers Subtab
    - Sessions Subtab
    - Peers Subtab
- Additional Features / Improvements
  - ProVision Backend Updates
  - IPAM Manage - IPAM / VLAN Multi-Edit (IPAMv2)
  - Customizable IPAM Columns (IPAMv2):
  - Updated IPAM Gadget (IPAMv2):
  - Updated Dashboard IP Charts:
  - Updated DNSSEC Toolstack:
  - DNS Push Policy Configuration
  - IPPlan (MySQL DB) Zone Import
  - Logging
- Bug Fixes/Improvements

Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

IPAMv2 - New IPAM Tab Updates


IM - 2851: Updated the **IPAM** Tab to support IPAMv2, and added new features and improvements. See IPAM Tab for additional details.



IPAM Tab

Updates and New Features to the **IPAM** tab include:

- Added Subtab navigation at the top of the page to switch between IPAM, VLAN, and Logging.
- Updated the UI for "Add Aggregate" - click on the expansion arrow to show the Add Aggregate form.
  Note: the "DHCP Aggregate" option has been removed, any IPAM block may now be used for DHCP Pools.




- Updated to a cleaner interface for IPAM Maps - click on the expansion arrow to see the map, then click on the gear icon to adjust the map settings, such as selecting the map positioning, viewing aggregates, or to view recent assignments. As in previous versions, the IPAM map may be enabled or disabled in the IPAM Admin -> IPAM Configuration page.

Aggregate Blocks List

Updated the IPAM Aggregates Block List to include:

- Updated interface
- Improved search filter - accepts CIDR, Region, RIR

- Added filter by IPAM Regions under "more filters". To exit out of all filters, right click on the list and select "Reset View".




  - Top Level Aggregates may now be merged from the Aggregate Blocks List by right clicking on the list, clicking "Select Aggregates", clicking the check boxes for the two aggregates to merge, and then selecting "Merge Selection". ProVision will pre-test the merge, and if valid, give you the option to proceed. To Exit out of the selection prior to merging, select "Unselect All".
  - The IPAM Aggregate Blocks list now has pagination
  - A shortcut to IPAM Manage for an aggregate is provided by clicking the "open" link that appears when hovering over an aggregate block in the list.

Host Utilization


Host Utilization Aggregate List updates include:

Simplified the Action menu (Gear Icon) to "Edit" (Open IPAM Manage for the Aggregate) and "Delete" (Delete Aggregate). Alerts, Auto-Split, and Clean up functions have been moved into the IPAM Manage page for the Aggregate.




Added More Charts! Four Charts are now available: Pie (standard), Bar (by resource), Tree (hierarchy), and Grid (Block detail). To access these, click on the chart icons in the Aggregate Header.


- Bar chart:



- Tree:




- Grid:




IPAM Manage

IPAM Manage Updates Include:

- Updated interface to support sortable columns, adjustable column widths, IPAMv2 column customizations, and user defined metadata fields.
- Moved modules for Auto-Split, Clean Up, and IPAM Alerts into the "Actions" flyout for IPAM Manage. To access, click the "Actions" link in the Manage header.



- Updated IPAM Block multi-edit: Shift-click multiple blocks to select blocks, then right click within a selection to chose "Edit Selected Blocks", "Assign Selected Blocks", or "Unselect All". See "IPAM / VLAN Multi-Edit (IPAMv2)" on this page for additional details.
- Multi-edit now includes Domain, VLAN, and customized metadata fields. (CFR -109)
- Block Assign / Multi-Assign is now a searchable / filterable resource list.
- Override Holding has been removed (instead, use "Unassign Skip Holding", or empty the holding tank).
- RIR integration has had interface and back end operation improvements.
- Minor UI updates have been made to "IP Rules".
- Improved IPAM Filter options to be searchable fields, include user-created metadata fields, and added a "select all masks" option. To toggle the filter flyout, click the "filter" link at the top, right most section of the IPAM Manage aggregate header. Enter your filter criteria, and click "Apply". To reset, click "Clear". You may also choose to set the chosen filters to the default setting by clicking "Make Default". (CFR-120, CFR-122)



See IPAM Tab for additional details on working with IPAMv2.

DHCPv3 - New DHCP Tab Updates

IM - 2648: The DHCP Tab has been updated to support DHCP Groups, an improved interface, and improved backend functionality. See DHCP Tab for details on working with the updated DHCP system.


Three new DHCP areas have been added - DHCP Groups, DHCP Servers, and DHCP Pool List. A fourth area, DHCP Logging, links directly to the Admin Logging Tab.

DHCP Groups:

The DHCP Groups page allows you to group DHCP Pools the same way ProVision allows zones under DNS Groups.

Create DHCP Groups by clicking the "Add Group" Button, then add subnet or host pools under the group by clicking "Add Pool" for the desired Group. Pools may be pushed individually, as a part of a DHCP Group, or through pushing an entire DHCP Server.

In the Pool list, clicking on the Pool name will open a pool details page to edit assignment, range, settings, reservations, or servers. Clicking on the pool Subnet will open IPAM Mange for the assigned pool block.




Additional DHCP Group options exist under "Attached Servers", where you can manage which server(s) is attached to the Group, and "Group Settings", where a Parent Resource and Failover name may be set.

Refer to the Working with DHCP Groups documentation for additional information.

DHCP Servers:

The DHCP Servers page shows a list of DHCP servers, created via the "Add Server" button. Supported server types are ISC BIND or Cisco Prime Network Registrar. During server creation, you may select to attach it to a DHCP group, or leave it unattached.

DHCP servers may be pushed or deleted directly from the Sever list. Clicking on the server name will open the Server Details page, where settings may be edited, directly connected pools viewed, server pushes performed, or server scanned.




Refer to the Working with DHCP Servers documentation for additional details.

DHCP Pools:

The DHCP Pools list provides the same pool-level functionality as the DHCP Groups pool lists, but includes all pools regardless of Group attachment. New subnet or host Pools may be added by clicking "Add Pool".

Clicking on the Pool name will open a pool details page to edit assignment, range, settings, reservations, or servers. Clicking on the pool Subnet will open IPAM Mange for the assigned pool block.



See Working with DHCP Pools for additional information.

Peering v2 - New Peering Tab Updates

IM - 2946 Updated the Peering tab to support Peering v2, including new peering pages, improved UI, and direct data connections to Peering DB.

General

Peering v2 has an improved backend, interfacing with Peering DB's new API. Users may chose to use PeeringDBs "main" or "beta" systems, by editing PeeringDB_URL in ProVision's global configs.

ASN validation and handling has been improved.


Users now need to specify a PeeringDB account (set in Admin-> Peering settings) to connect with PeeringDB information.

The peering interface has been updated with new subtabs: IXs (Exchanges), Routers, Sessions, and Peers. Additional detailed information pages are available from each of these subtabs.


See Peering for additional information.

IXs Subtab


The Exchanges subtab shows the list of exchanges current set in ProVision, with IP type, city, peers, and session counts.



Clicking on an exchange in the exchange list will bring up an exchange details page, where Exchange Details, Session Details, and Exchange Communications may be viewed and managed.




ASNs and PeeringDB account settings may be edited by clicking "Settings" in the IXs or Exchanges pages, or by going to ProVision's Admin settings page.



See Peering Exchanges for additional information.


Routers Subtab

The Routers subtab is where routers may be added and managed. Routers are divided into two lists - those with Peer Groups, and those without.



Add a new router by clicking the "Add Router" button, which will direct to a page to input the router details.

Clicking on a router entry in the router list will open the router details page.




From here, routers may be added as well, or you can use the filterable list in the left sidebar to select a router to view.

The router details area gives basic router information, which you may edit via the "Edit" button, and Peer Group management options.

See Peering Routers for additional information.


Sessions Subtab

The Sessions subtab is where current sessions may be added, managed, and updated.



Add a new session by clicking the "Add Session" button, which will direct to a page to input the session details.

Clicking on a Session entry in the list will open the Session details page.




From here, new session may be created, but it is primarily for session management. The Session may be manually configured via "Config Manager", or automatically via "Configure".

"Email" opens an Email communications form, with data automatically generated from PeeringDB. Other available tasks include Admin Up/Down, Edit, and Delete session.


See Peering Sessions for additional information.

Peers Subtab

The Peers subtab lists existing peers, and allows for you to search for new peers to add via the "Add Peer" button.




Clicking on a peer in the list will open the Peer Details page.



From here, additional Peers may be added, or you can view details for the existing peer, including available exchanges and what routers you have available on that exchange.

You may also choose to "Configure Multiple Sessions" - clicking the configure multiple buttons opens a page where you may select and set up multiple sessions for that peer, and then choose to either "Configure Now" or Schedule the config to run later via the **Scheduler** Tab.



See Managing Peers for additional information.

Additional Features / Improvements


ProVision Backend Updates

IM - 2651, IM-2627: ProVision has been updated to support(and require) PHP 7.1 / PDO and mySQL 5.7. Local installation customers should ensure that they meet the software requirements for ProVision 7.0.0.

IPAM Manage - IPAM / VLAN Multi-Edit (IPAMv2)


IM-2077: IPAM Manage - Multi-edit now supports Domain and VLAN fields.

To select multple blocks to edit, hold down the shift key and click on the blocks you wish to edit - the selected blocks will be highlighted. Right click anywhere in the blue highlighted area, and select "Edit selected blocks".




The "Edit Block" modal window will pop up for the selected block(s). Edit the domain by clicking in or typing in the domain search box, and select the desired Domain.

Then, select the VLAN for the blocks from the enabled VLAN list. When done, click "Save".




Customizable IPAM Columns (IPAMv2):

CFR - 109: The IPAM Admin "Lists Management" area has been updated with an "Edit Columns" page to support IPAMv2 column customization.




In "Edit Columns", you can change the column order, column name, and visibility of IPAM columns globally for IPAM areas in ProVision. See IPAM Parameters for additional details.

*To access "Edit Columns", you must be logged in as a user with Admin access. From the Admin area of ProVision, go to the **IPAM Admin** tab, then click "Edit Columns" under IPAM Lists Management.*



Eleven default ProVision fields and ten user-defined "Metadata" fields are available for customization.




From here:

*To **edit** a column name, simply type your changes in to the text box. and click the "Update" button.*

*To **reorder** the columns, click and hold on the "list" icon (three lines) to the left of the subet, then drag to the desired location in the list and release.*


*To **toggle visibility** for a column, click in the checkmark field to the right of the column name to enable / disable visibility. This affects the columns that show in both IPAM Manage and the IPAM Gadget.*



When complete, be sure to click on the "Update" button to save your changes.

Keep in mind that "Edit Columns" is a global edit. If the values for order, header, or visibility are changed, it will affect ALL users of the ProVision application!

Once changes are saved, the enabled columns will show in IPAM Manage Aggregate screen and the IPAM Gadget "IP Blocks" List.




See IPAM Parameters for additional information.

Updated IPAM Gadget (IPAMv2):

IM-2850, CFR-109, CFR-119, CFR-120, CFR-122: Created a new IPAM Gadget that supports IPAMv2, additional columns, user defined column order and visibility, and other improvements.

A new IPAMv2 Gadget is provided with the IPAMv2 7.0.0 updates!

The IPAMv2 Gadget will automatically replace currently enabled IPAMv1 Gadgets during the 7.0.0 upgrade. However, the IPAMv1 Gadget will remain available to manually add to a Section until a future 7.1.0 release.




The new IPAMv2 Gadget features:


- Improved layout
- Improved backend handling with faster loading, updates, and assignments.
- Pagination! (CFR-119)
- Advanced Filter options for Direct assign and Smart Assign
- Columns able to be sorted into Ascending / Descending order
- Support for customized column order, name, visibility, and up to ten custom columns (CFR-109. See: Admin - Edit Columns)
- Improved IP Block filter options (CFR-120, CFR-122)
- Single-click reverse zone generation (left mouse click on the block CIDR link).

Enabling the IPAMv2 Gadget:

*To Enable the IPAMv2 Gadget, navigate to the **Resources** Tab -> **Sections** subtab, and click on the Section you wish to add the IPAMv2 Gadget to, and Click "Edit Section".*



In the "Edit Section page, navigate to "Manage Gadgets", then select "IPAMv2" from the Gadget dropdown list. (Note: the previous IPAM gadget - "IPAM" is still available, and may be concurrently placed in the same Section with the IPAMv2 Gadget).



Click the "Add" Button, and then Save your changes.




The IPAMv2 Gadget will now display on Resource Entry pages under the edited Section.

Working with the IPAMv2 Gadget:

Additional details provided below on specific tasks involving the IPAMv2 Gadget:
Direct Assign:

Simple Direct Assign:

Expand the "Direct Assign" module of the IPAMv2 Gadget by clicking the "Expand" arrow on the right side of the header.




Type the desired CIDR to assign in the CIDR input box, then click "Assign". A message will appear to confirm success, or provide details on an error.


Advanced Direct Assign:

In some cases, you make need the ability to further specify a block to direct assign - such as if you have duplicate 1918 blocks. The "Advanced Options" filters allow for further detail to be provided to ensure ProVision assigns the specific block that is intended.

Expand the "Advanced Options + " link to the right of the "Direct Assign" module header.




Then, add in the desired CIDR, and set your additional filter criteria, such as RIR, region, LIR, VLAN, and so forth. When done, hit "Assign".



Smart Assign / Smart Browse:

Expand the "Smart Assign" module in the IPAMv2 by clicking the expansion arrow in the right side of the Smart Assign header.

For a basic assignment, enter at least the IP type, RIR, and block size.




IP Tag filters are optional. IP Tag filters exist in three modes:

Standard - checks to see if the selected tag is associated with the block

Strict: limits results to blocks with exactly the selected tag(s)

Exclude - blocks without the selected tag(s)


For Advanced Options, Click the "Advanced Options +" expansion link in the top right of the header. Additional filter criteria will be available to apply to both Smart Browse and Smart Assign.



Then click "Smart Browse" or "Smart Assign".


For Smart Assign, you will receive a message indicating a successful assignment, or information regarding an error. If no blocks are available meeting the criteria, the message will say so. In this case, try removing one or more of your filter criteria and try again.

For Smart Browse, a screen will pop up showing blocks meeting your criteria. Browse to the block you want to assign, and click either "Assign this block", or "Assign from this block"(splits a larger block down).



Successful assignments will be added to the "IP Blocks" list in the IPAMv2 Gadget, and are able to be managed in the IPAM Gadget, IPAMv2 Gadget, or IPAM Manage Screen.


Managing IP Blocks in the IPAMv2 Gadget:



Managing IP blocks in the IPAMv2 Gadget remains similar to the previous IPAM Gadget, with minor updates:


The IP Block list may be sorted by field! Just click the column name to toggle between ascending / descending by that field.

IP Blocks may now be filtered! Click on the "filter +" link in the top right header to display the filter options. Type in or search for the term under your desired field, and hit "Apply". When done, click "clear". To hide the filter flyout, just click the "filter -" link again.



To edit a block, you may either click on the Action Menu (now a Gear Icon), or double click on the row of the block you wish to edit.

"Edit Attributes" supports additional IPAM attributes, including RIR, LIR, ASN, Propagate attributes to children, and up to ten user-defined metadata fields as set in IP Admin->Edit Columns. Just add in your custom data, and click "Save"!



Changes to attribute field name and visibility (as set up IP Admin-> Edit columns) are reflected in the "Edit Attributes" modal.


Click-to-create-reverse-zones is back! Single left click on the Block address to automatically generate a reverse DNS zone for that block.

The IP Blocks list now includes pagination. Up to 15 blocks are displayed per-page.


Columns widths are now manually adjustable, and side-scrolling is automatically enabled when additional columns exist out of view range.

IPAMv2 Gadget column customization is accessed via the IPAM Admin area of ProVision - you must be logged in as a user with Admin access.

*From the Admin area of ProVision, go to the **IPAM Admin** tab, then click "Edit Columns" under IPAM Lists Management.*



Eleven default ProVision fields and ten user-defined "Metadata" fields are available for customization.



From here:

*To **edit** a column name, simply type your changes in to the text box. and click the "Update" button.*

*To **reorder** the columns, click and hold on the "list" icon (three lines) to the left of the subet, then drag to the desired location in the list and release.*

*To **enable** / **toggle visibility** for a column, click in the checkmark field to the right of the column name to enable / disable visibility. This affects the columns that show in both IPAM Manage and the IPAMv2 Gadget.*




When complete, be sure to click on the "Update" button to save your changes.

Once changes are saved, the enabled columns and their changes will be visible in the IPAMv2 Gadget.


Updated Dashboard IP Charts:

The Dashboard "IP Charts" Widget has been updated to show block percentages that are assigned, unassigned, allocated, or in the holding tank. Hovering over a status will show additional details.



Updated DNSSEC Toolstack:

IM - 2629: ProVision now supports new DNSSEC toolstack bind-utils (dnssec-genkey and dnssec-signzone), set in the Admin Preferences page "DNSSEC Tools" settings. See Admin Preferences for additional details



Field Details:

zonesigner path : Enter the zonesigner path that will be used for DNS. Zonesigner is required if dnssec-keygen and dnssec-signzone are not set.

dnssec-keygen path: Enter the keygen path. Required if zonesigner is not set.

dnssec-signzone path: Enter the signzone path. Required if zonesigner is not set.


dnssec-dsfromkey path : Enter the dnssec-dsfromkey path that will be used for DNS. Required in all cases.

DNSSEC validation server: Enter the IP of the nonauthoritative DNSSEC validation nameserver. Optional.

DNS Push Policy Configuration

IM - 2674: Added configuration options for DNS Push Policy under DNS Groups.

*To set or update the Push Policy for a Group, go to the **DNS** Tab and expand the "**Group Default Parameters**" section for the desired DNS Group. Click the radio button for which policy you want applied, and click "Save Push Policy".*



Three Push Policies are available:


- Zone-centric : Pushes all the zones to all the servers attached to them including servers not attached to the group.

- Server-centric: Pushes all the servers with all the zones attached to them, including the zones not attached to a group.

- Group-centric: Pushes all the zones in the group to the servers attached to the group.

IPPlan (MySQL DB) Zone Import


IM-1950: ProVision now supports importing IPPlan data via the Data Import tab. IPPlan Zone Import pulls zones from IPPlan MySQL databases. It is advised to create a DNS Group prior to the import with default parameters and NS records to be inherited by the imported records.



*To import zones from a IPPlan MySQL database, navigate to the Admin area **Data Import** Tab, and click on "IPPlan Zone Import".*



From there, enter the IPPLAN DB Options - Host, Database Name, MySQL Username, and MySQL Password, then select the desired DNS Group to add the zones under.




When done, click the "Import" button.

For more information, see IPPlan Zone Import.

Logging

The **Log** Tab has decided to join its other Admin-only brethren in the Admin area of ProVision. You may now find it between the **Scheduler** Tab and Exit Admin.



Bug Fixes/Improvements

IM - 994: Added mouseover display definitions in IPAM aggregate listing for "Available", "Allocated", "Assigned", and "Holding" statuses.

IM - 1463: Updated SOA validation to allow all valid characters for hostmaster email.

IM - 1616: Roles from the Contact Manager gadget may now be used to assign ARIN-ADMIN and ARIN-NET roles for RIR Integration / SWIP.

IM - 1828: The Reverse API Console Gadget now displays a header name.

IM - 2110: Added "VLAN" as a Log Category filter.

IM - 2207: Improved IPAM Domain / VLAN selection interface.

IM - 2391: The "Resource" toggle in VLAN -> Manage IPs -> "List Available" once again allows VLANs to be added to blocks assigned to specific resources.

IM - 2394: User Group Resource Permissions may now be set specifically for IPAM "Available" and "Holding" statuses, allowing limited or partial permission users to interacts with available or held blocks.

IM - 2397: Added a "Reorder List Alphabetically" button to the IPAM Admin "Edit Regions List".

IM - 2439: Resolved an issue where "Default Dashboard" would not display in the dashboard selector dropdown.

IM - 2443: Updated "Help" page information and links.

IM - 2453: Added check to ensure "Name" is provided when adding a new IPAM Region.

IM - 2466: Resolved an issue where adding multiple new user dashboards at a time would result in earlier dashboards being overwritten.

IM - 2467: IPAM Manage filters once again self-limit filtering options based on current viewable blocks.

IM - 2539: The IPAM "Clean Up" feature is now an Admin-only task.

IM - 2606: The "Click CIDR to Create Reverse Zone" feature has been brought back in the IPAM and IPAMv2 Gadgets.

IM - 2633: Removed DNS Zones and Records from displaying in the Dashboard "Resource Tree" Widget.

IM - 2643: Scheduler DNS Server pushes created in the Scheduler tab now show the correct datetime display.

IM - 2656: Resolved an error that would produce a "timeout on read select()" message when checking DNS zones.

IM - 2661: Fixed an issue where the APIv2 call DELETE /api/v2/ipam/tags/{value} would fail.

IM - 2663: Updated DNSv3 "Add Server" error messages.

IM - 2664: The LDAP remote authenticator will now correctly recognize ProVision groups.

IM - 2666: Fixed the color displayed for some buttons when viewed using Chrome for Mac.

IM - 2667: The IP Import from .csv mapping step has been updated to replace the deprecated field option "Resource Holder ID" with the now correct field "Custom ID".

IM - 2689: Resolved a minor error that would occur when saving edits made to DNS Group Default Parameters.

IM - 2697: Updated a login issue where using valid credentials immediately after a failed login attempt would not redirect to the Dashboard page.

IM - 2705: Updated various IPAM error message text.

IM - 2732: The ACL selection dropdown in DNS Groups now updates immediately when an ACL is added or deleted.

IM - 2739; IM-2858: Updated the IPAM Configuration page to remove "Generic Code" and "Regions" settings, which are now handled under IPAM Edit Columns.

IM - 2743: Added a "Reorder List Alphabetically" option to IPAM Admin -> Edit Regions List.

IM - 2794: All existing Categories are now available for selection when creating a new Section.

IM - 2810: Added "DHCP" as a Log Category filter.

IM - 2820: Updated DHCP Management and DHCP Customer Configuration Gadgets to no longer utilize the concept of "DHCP Available" blocks (removed with DHCPv3).

IM - 2821: Added "Subtab" buttons for IPAM, VLAN, and Logging to the VLAN page to replace the previous radio toggle.

IM - 2898: Updated Application settings so that if a custom logo is not set, the logo will default to the 6connect logo.

IM - 2904: Updated button styles on the API Tab's "Reverse API" page.

IM - 2953: Fixed a bug in Resource Chart View "Quickview", where child resources for the first parent resource views were being displayed under an unrelated second parent resource.

ProVision 7.0.2

ProVision 7.0.2 is a minor release with bug fixes.

- Local Software Requirements Update
- Bug Fixes / Minor Improvements

Local Software Requirements Update

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/

Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes / Minor Improvements

IM - 3048: Resolved an issue in APIv2 where the custody chain IPAM Attribute failed to update after enabling subassignments.

IM - 2650: Minor DHCP improvements, including:

DHCP Customer Configuration Gadget:

- User can now accept a status of "suspended"
- VLAN is now displayed with the DHCP Pool information

DHCP Push has been updated to include:

- Strict validation for hostname in order to avoid broken DHCP configuration files
- Updated the DHCP service so that DHCP Push can be initiated by APIv2

ProVision 7.0.1

ProVision 7.0.1 is a minor release with bug fixes and improvements.

Local Software Requirements Update

For local installation customers, ProVision versions 7.0.0 and newer have upgraded software requirements (in red, below):

	Required	Link
Operating System	Linux/BSD/OSX	
Apache	Apache 2.4	http://httpd.apache.org/
PHP	**PHP 7.1**	http://php.net/downloads.php
MySQL	**MySQL 5.7**	http://www.mysql.com/downloads/


Note on MySQL: We recommend setting the max_allowed_packet setting in the MySQL configuration file to 128MB (or similar) to account for the typical dataset size handled in ProVision.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Improvements

Holding Tank Improvements

IM-3013 Added the ability to select specific blocks to release from the Holding Tank and links to each blocks IPAM Manage page.



Select individual blocks to release from holding by clicking the checkbox for the desired block(s), then click "Process Holding Tank".

To release all blocks from the Holding Tank, click the "select all" checkbox at the top left header of the table, ensuring all blocks are selected, then click "Process Holding Tank".

Bug Fixes / Minor Improvements

IM - 1161: Added checks for semicolon email address separators for Peering email options.

IM - 2659: Added "MD5 Password" and "Max Prefixes" fields to Peering multi-session config.

IM - 2997: Resolved an error where deletion of a field would prevent access to the Edit Section page.

IM - 3008: The Resource Linkage Gadget once again saves link updates and additions.

IM - 3009: Fixed an issues where using Assign / Unassign after using a global IP block search link resulted in an error.

IM - 3011: Updated TTL and CNAME validation for the DNS Record Monitor scheduled task.

IM - 3015: The IPAMv2 Gadget - Smart Assign tag selector will no longer truncate the tag list when more than 32 tags exist.

IM - 3016: Updated Data Import from RIR "Continue to ProVision" link to direct to IPAMv2.

IM - 3022: The Session "Notes" field now saves correctly.

ProVision 6.1.0

ProVision 6.1.1 is a minor release with improvements and bug fixes.


(Version note: 6.1.0 was an internal release only, and incorporated into 6.1.1.)

Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

DHCP Group Management (BETA)

This section of the DHCP Management Gadget allows you to create and manage DHCP Groups. DHCP groups help you to organize all of your Pools and Servers together into a single place, and push pools linked to a DHCP Group to all of the servers attached to that Group. It also allows for the designation of a DHCP Failover Peer for ISC BIND servers.



The walkthrough below is an abriged overview of the beta DHCP Groups feature. For detailed information, please see DHCP Tab - Working with DHCP Groups .


Step 1: Create DHCP Servers

*Ensure that all necessary DHCP servers are created via the **DHCP** Tab **Add DHCP Server** button, ensuring that Connection Configuration is set. All DHCP servers listed under the DHCP tab will be available to select to attach to DHCP Groups (in the format of "ResourceID - DHCP Module").*

Step 2: Create DHCP Groups

Select a DHCP server page with the DHCP Management Gadget from, and expand the Group Management section. Note: Any DHCP server page with the Manangement Gadget is fine to use, as the Group Management section will globally update to be the same in any DHCP Management Gadget.

A "Default Group" should be available immediately, or you can click the "Add Group" button to create a new DHCP Group. Type in the desired Group Name and select a Parent Resource for the Group, then click "Create Group".




Your new Group will be available in the DHCP Management Gadget. To delete the DHCP Group, click the "X" next to the Group name.

Step 3: Attach DHCP Servers to Groups

All DHCP servers listed under the ProVision DHCP Tab will be available to select and attach to the Group. They are identified by their resource ID number, so if necessary, check the server's resource ID number in the resource information Gadget.

Select the desired server from the "Attach Server" selector, then click "Attach". The server is now attached to the group and available for pushes.



Step 4: Identify Failover Peer (Optional - ISC Bind Only)

If a DHCP failover peer is configured for the server, enter the server name and click the "Save" button. In the event that the primary server fails to push, the push will be sent to the failover peer instead.



Step 5: Link Pools to DHCP Groups


From the Existing Pools list under the DHCP Pools section, click the Action Menu for the pool you wish to link to a DHCP Group. From there, click "Link to Group".



If multiple DHCP Groups exist, a dialog will pop up for you to select the desired Group to link the pool to. Select the DHCP Group, then click "Confirm" to add the pool to the Group.

Step 6: Push the DHCP Group

Lastly, click the "Push" button for the DHCP Group to push the linked pool(s) for the Group to the linked DHCP Module, and then push all DHCP servers linked to the Group.



While pushing, a status box will appear to show status and any errors, if applicable.

Additional Features / Improvements

CFR - 135 Optional RIR for IPAM Gadget Smart Assign

The RIR selector for the IPAM Gadget is now an optional value when using Smart Assign (RIR is still required for Smart Browse).

CFR - 136 IPAM Automerge option to respect tags / regions

The IPAM "Merge after unassign" option (under IPAM Configuration settings) now has a sub-option to respect tags and regions.

When enabled, the merge after unassign will stop if the two merging blocks do not have identical tags and regions.

To enable, ensure "Merge after unassign" is checked in IPAM Configuration, then also check "Automatic Merge Respects Tags & Regions" below it.



IM/CFR - 2655: CPNR Updates

The ProVision CPNR now has IP Reservation support in the ProVision API/CPNR Connector.

Bug Fixes/Improvements

IM - 2626: Resolved an issue where pagination would disappear in very long DNS zone lists.

IM - 2628: Updated handling of IP blocks in the DHCP Customer Configuration Gadget when Smart Browse is used with an IP Rule set for a DHCP block.

IM - 2658: Resolved an issue where APIv1 DNS PTR record updates would fail when searched by zone id without a parent id being provided.

IM - 2669: Escaped characters are now supposed in the DNS Records SOA mail field.

IM - 2671: Resolved an issue in DNSv3 server settings where MYSQL password would not save for PowerDNS with MySQL Settings.

IM - 2673: Fixed an error that would occasionally occur in Safari for OSx, where an empty IPAM Gadget would hang until a block was assigned.

IM - 2677: Removed a row from the Contacts Gadget that would show an action menu, but no Contact.

IM - 2679: The Resource entry list now shows correct zone count.

IM - 2680: Resources with zones may now be recursively deleted from both the Resource Entry page and the API. Recursive deletion will continue to not be available for blocks with child entries or allocations.

IM - 2681: Updated handling of "Update Session State" in Peering Sessions in instances where ASN had been changed, leave inactive sessions that would attempt to update.

IM - 2683: Import BGP Sessions now correctly clears session details when changing router selection prior to clicking "Load Sessions".

IM - 2687: Resolved an issue with DHCP CPNR delete not working on scope named as CIDR.

IM - 2688: Improved empty error messages in CPNR.

ProVision 6.1.2

ProVision 6.1.2 is a minor release with bug fixes.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes/Improvements

IM - 2696: Improved chain-of-custody handling in subassignable IPAM blocks.

ProVision 6.0.0

ProVision 6.0 is a major release with new features.


Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

(CFR denotes customer requested)

DNSv3

IM -2552: Updated and replaced the DNS Admin and DNS Tabs with DNSv3 - featuring a more efficient backend, new user interface, and a DNS "Group" system.



DNSv3 restructures ProVision's DNS tab to organize DNS zones into "DNS Groups". Zones are gathered under Groups, default parameters and servers are set per Group, and pushes may be done on a per Group level. A "Default Group" is automatically provided in ProVision, but other Groups may be desired to organize zones and default values. See the updated workflow for DNSv3 at DNSv3 Workflow Concepts.

DNSv3 changes ProVision's approach to Admin-level DNS tasks, integrating them under the **DNS** tab rather than a separate "Admin" tab. Server management has been integrated into the DNS Tab, under "DNS Servers" (accessible only to admin-level users), default parameters, SOA, ACLs, and exports are incorporated into each DNS Group.

Permissions for interacting with DNS elements in DNSv3 have been adjusted, incorporating DNS items under the "Resource" system when setting User Group Permissions. This allows for fine-tuned settings on individual DNS Groups, servers, and zones within the Permissions Group.


For an overview flowchart of working in DNSv3, see the updated workflow for DNSv3 at DNSv3 Workflow Concepts.

DNSv3 Related changes include:

- Access DNS Servers, Groups, and Zones from the same ProVision **DNS** tab.
  - See: DNS Tab
- Removed the **DNS-Admin** tab. Functionality previously in **DNS-Admin** is now contained under the **DNS** tab "DNS Servers" area (Admin only), with SOA and Nameserver defaults set per-Group.
  - See: DNS Administration and Working with DNS Servers
- Introducing "DNS Groups" - Organize your Zones and Servers together into a single place. With Groups, you are able to organize groups and push whole group configurations at the same time.
  - See: Working with DNS Groups
- Updated Zone list interface and View Zone pages.
  - See: Working with DNS Zones - Common Tasks and Editing DNS Zones
- Zone Error Monitoring - Check zones for errors, and receive detailed feedback.
  - See: Working with DNS Zones - Common Tasks
- Schedule Pushes at the server, group, or individual zone level.
  - See: Working with DNS Groups, Working with DNS Zones - Common Tasks, DNS Administration
- DNS Templates have been removed and replaced with an option to "Clone Existing Zone" when creating a new zone.
  - "Template" Zones may be created under a "Template" DNS Group, and given an appropriate name (templateABC.com.) to reference when cloning. Any existing DNS Templates with automatically be migrated to a new "Template" DNS Group during the 6.0 upgrade.
  - See Working with DNS Groups and Working with DNS Zones for more information on creating new Groups and zones, respectively.
- Incorporated ACLs / Views into a DNS Group module.
  - See Configuring Split Horizon/Views
- Enabling and configuring DNSSEC has been revised to work within the DNSv3 server / Groups system.
  - See Configuring DNSSEC
- The Users tab Group Permissions have been updated to remove "DNS" as a separate permissions area, as DNS entities (servers, groups, zones) are now considered "Resource" items.
  - In order to push a DNS Group or zone, Users without global or admin permissions will need to have resources permissions specifically added for that server, DNS Group, or zone.
  - See Users & Permissions
- Revised the Data Import -> BIND DNS Zone Upload / Import tool to be compatible with DNSv3 and ProVision-exported DNS Group export .zip files. Imports may now associate a DNS Group to import zones under, and server mapping has been removed (as servers are now associated at the DNS Group level).
  - See BIND DNS Zone Upload / Import


Peering "View By Peer" tab

IM-1551: Added "View by Exchange" and "View by Peer" options for the **Peering** Tab.




"View by Peer" allows you to select a peer, and view Peering DB information and all ProVision sessions for that Peer.
"View by Exchange" returns you to the standard Peering Tab view, with Peer sessions organized under each exchange.

To see "View by Peer", navigate to the ProVision Peering Tab. At the top left of the page, click the "View by Peer" button.



On the "View by Peer" page, click on a Peer from the list on the left. You may also filter the list by typing a few characters from the Peer name into the filter box.


Once a Peer is selected, View information and sessions for that peer by clicking on the "Info" and "Sessions" tabs at the top of the center information panel.



When done, return to the main Peering Tab by clicking on the "View by Exchange" toggle at the top of the page.

DNS Autogenerator Gadget

The DNS Autogenerator Gadget uses the Hostname field (6c-hostname-fqdn) of the Resource to generate a list of DNS forward and reverse zone entries based on the blocks assigned to the Resource in the IPAM Gadget It will generate a list of potential zone records - just select the ones you want to create, save the changes and you are ready to push the zones. See Gadgets - DNS Autogenerator for more details.



Enabling the DNS Autogenerator


To set up this Gadget, ensure that the Section of the Resource (typically, "Resource Holder"), has the "Hostname" field (6c-hostname-fqdn) and the DNS Autogenerator Gadget added to the Section. (See: Customizing Sections and Customizing Fields).

Then, check that the Resource itself has information entered into the "Hostname" field. If the field is already filled out, it will show in the "Fields" information area at the bottom of the Resource Entry page. To add or edit the hostname, click "Edit" at the bottom of the resource entry page, add the information to the Hostname field, and click "Save".

Once a hostname has been associated with a Resource, and the page refreshed, the DNS Autogenerator Gadget will be visible.

Working with the DNS Autogenerator


One enabled and visible, the DNS Autogenerator Gadget will initially show a short description, the hostname, and a button to "Autogenerate Records".



Before starting, check that the blocks assigned to the Resource in the IPAM Gadget are correct and up-to-date - the Autogenerator uses these blocks to create the records. If using a DNS Group other than "Default" to hold zones, ensure that the desired DNS Group to hold the generated records has been set up. (See: Working with DNS Groups).


When ready, click the "Autogenerate Records" button. The Gadget will search through the blocks in the IPAM gadget and provide a list of found blocks.

Next, add in a subdomain if desired (optional), and select the DNS Group to hold the records (required). Click on the listed blocks to select (highlighted green) or deselect (grey) for DNS zone / record creation.



Finally, hit the "Save" button at the bottom of the gadget - the selected forward and reverse DNS records will be created and added into the DNS Group, viewable in the DNS Tab. From there, you can choose to push / schedule push the newly generated zones, or re-run the generation if desired.

DHCP Customer Configuration Gadget



The DHCP Customer Configuration Gadget allows users to assign IP aggregates to the DHCP server pools and generate DHCP Server Configuration changes.

These configurations are then sent to the associated DHCP server Management Gadget as "Unpushed Configurations", where they may be held until a manual or schedule push occurs.

Before using the DHCP Customer Configuration Gadget, the following should be set up in ProVision:


- *The associated DHCP server should be created in ProVision and set up in the DHCP Management Gadget (See: DHCP Tab).*
- *Add the DHCP Customer Configuration Gadget to the desired Section. You may want to create a specific "DHCP Customer" Section for DHCP customer entries (See: Customizing Sections).*
- *Have, or set up DHCP Aggregates from the IPAM Tab with the desired IP space type, RIR, Region(s), Tags, and any desired VLAN criteria. Regions are a required field when assigning IPs from the DHCP Customer Configuration Gadget.*

Using the DHCP Customer Configuration Gadget


- *Step 1) Link the Gadget with the desired DHCP Server*



- *Step 2) Assign IP's for Pools from DHCP Aggregates*



- *Step 3) Set up configuration information - add Option 82 Elements, Circuit ID, and notes. Use the "Preview" field to confirm the accuracy of the data, and select the status as "Activate" or "Terminate".*
  Once saved, the updated configuration will be sent to the DHCP Management Gadget.



- *Step 4) an admin user may manually push the updated configuration from the DHCP Management Gadget, or use a scheduled DHCP push task to automate the pushes.*

See Gadgets - DHCP Customer Configuration for more details.

Additional Features / Improvements

New DNS Import Options




Provision DNSv3 supports the addition of four new DNS Zone Import options to the Admin **Data Import** Tab:

- **InfoBlox DNS Zone Import**

  *To import zones from an Infoblox server, navigate to the Admin area **Data Import** Tab, and click on "InfoBlox Zone Import".*

  From there, fill out information for the Infoblox server host, username, and password. Select the Import options for zone type, view, and DNS Group.




  When done, click the "Import" button.

  For more information, see InfoBlox Zone Import.

- **NS One DNS Zone Import**

  *To import zones from a NS One server, navigate to the Admin area **Data Import** Tab, and click on "NS One Zone Import".*

  From there, enter the NS One API Key and select the desired DNS Group to add the zones under.




  When done, click the "Import" button.

  For more information, see NS One Zone Import.

- **DynDNS Zone Import**

*To import zones from a Dyn DNS server, navigate to the Admin area **Data Import** Tab, and click on "Dyn DNS Zone Import".*

From there, enter the DynDNS Customer Name, UserName, and Password, then select the desired DNS Group to add the zones under.




When done, click the "Import" button.

For more information, see Dyn DNS Zone Import.

- **DNSMadeEasy Zone Import**

*To import zones from a DNSMadeEasy server, navigate to the Admin area **Data Import** Tab, and click on "DNSMadeEasy Zone Import".*


From there, enter the DNSMadeEasy API Key and API Secret, then select the desired DNS Group to add the zones under.



When done, click the "Import" button.


For more information, see DNSMadeEasy Zone Import.

Peering - Configure Sessions for Existing / Approved Peers:




An option has been added to the Peering Communications action menu to "Configure Sessions" for that Peer. With this option, you can view and configure all sessions, from any or all exchanges, for that Peer from one menu. "Configure Sessions" becomes available once a peer has been marked "Existing" or "Approved" in the Communications Action Menu. For more information, see Peering Sessions.

Clicking on "Configure Sessions" opens a modal showing the available exchanges with routers, sessions for that Peer under those exchanges, and options to change the router, peer group, and Peer type.




Select the checkmarks for the desired sessions to configure. As a shortcut, you may also check the "Select all exchanges" option to select all sessions under all exchanges, or, check "Select all networks" next to the exchange header to select all sessions in that exchange. From there, deselect items as needed.



*When your selections have been made, click "Configure Now" to immediately configure all selected sessions, or you may schedule the configuration through the **Scheduler** Tab.*

Users Tab/ Permissions Updates:

The Users tab in the Admin area of ProVision has been updated to reflect DNSv3 changes for permissions groups. Changes include removing "DNS" as a separate permissions area and incorporating DNS items under the "Resource" permissions area. DNS Groups, Zones, and Servers may now be selected as "Resource" items when settings up permissions groups.



CPNR Updates:

CPNR Updates include:

- Added a check to ensure CPNR modules in ProVision are reachable prior to Push
- Option 43 is now integrated
  scope_upsert call now is taking 2 new parameters "option_43_name" and "option_43_value".
  - The "option_43_name" must be predefined inside CPNR (Design->Options)
  - "option_43_value" should be the value that is going to be set for the Scope for example "241 11.22.33.44" (typically 241 followed by the IP).

DNS APIv1 Updates

To support the release of DNSv3, the following updates have been made to DNS APIv1 endpoints:

- As of DNSv3, zones are now considered their own resource. Thus, DNS APIv1 zone parameters "zoneResourceId", "updateZoneResourceId", and "deleteZoneResourceId" now refer to (and equal) the zone ID instead of the parent resource ID, and are no longer editable values.
- The DNS Zone Control "GET" optional parameters "selectOffset" and "sortArray" have been removed.
- DNS Zone Tags are no longer supported. Zone Tag parameters under target=zone and target=record have been removed.

IPAM APIv1 Updates:

Get:The following updates have been made to IPAM APIv1 "get" endpoint. Valid tagsMode options are now "strict", "exclude", "intersection", and "union". See API Module - IPAM for additional details.

- If tagsMode is omitted from an IPAM Get request, the mode defaults to 'intersection'
- tagsMode=union has been implemented for IPAM Get. It selects any block which has any one of the tags.
- tagsMode=intersection matches any blocks which has all of the tags.
- tagsMode=strict and tagsMode=exclude remain unchanged.

smartAssign: if the phrase "assignedResourceId=ignore" is supplied, then a matching IP block is selected from the Available pool or any sub-assignable block on any resource.

DNS Gadget Updates:

The DNS Gadget has been simplified to support DNSv3 changes.



- Zone creation, editing, and deletion has moved into DNSv3, under the **DNS** Tab.
- The action menu has been simplified to a "View Zone" option, which links to the DNSv3 view zone page (also accessible from clicking on the zone name).
- Zone delegation has been removed.

Bug Fixes/Improvements

IM - 1719: Removed "Edit" link on Contact Gadget for read-only users.

IM - 1948: Added a "Clear Search" function to DHCP Pool searches in the DHCP Management Gadget.

IM - 2089: Added the ability to deselect Domain and VLAN from "Create a New Pool" in the DHCP Management Gadget.

IM - 2380: When adding a Peering session, the Router selector will now correctly reset to the appropriate router list if the selected exchange is changed.

IM - 2385: Resolved an issue where "Invalid Date" would show in the Document Manager "Date" column.

IM - 2387: Fixed an issue where IP Rules would not reserver the first address in an IPv6 block.

IM - 2440: Updated the "Resource Tree" widget on the Dashboard to show text as angled while in vertical mode.

IM - 2456: Updated error message(s) in LIR Manager to show the correct color.

IM - 2458: Resolved an issue where the "Add Session" modal would populate a different router list between multiple modal instances.

IM - 2460: Improved the Resource Linkage Gadget to use the resource_linkage table instead of resource_attr, improving API access.

IM - 2469: Peering import BGP sessions will now detect router sessions in cases where no local sessions currently exist in ProVision.

IM - 2472: Resolved an API issue where a parent block could be direct assigned if specified by ID.

IM - 2487: Resolved an issue that occurred when a non-address string was provided for a Region's Address field. Non-address addresses will now default to global zero positioning on the IPAM Map.

IM - 2486: IPAM APIv1, the parameter tags_mode="strict" has been updated return only blocks with no tags, if no tags are specified in the call.

IM - 2517: Read only users will no be able to view the "Delete" button for RIR Contacts.

IM - 2535: Mobile navigation search box now correctly returns search results.

IM - 2544: Resolved an issue in the DHCP Management Gadget - Create Pool where selecting a Domain / VLAN would prevent selection of an IP Rule.

IM - 2595: Removed "Audit DNS" link from the IPAM Manage Action Menu.

IM - 2599: Resource API fields "category__in" and "category__not_in" are once again returning responses.

IM - 2604: The IPAM Aggregate "Clean Up" function now respects subassignable blocks as assigned when used in conjunction with the "ignore assignments" flag.

ProVision 6.0.2

ProVision 6.0.2 is a minor release with bug fixes.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes/Improvements

IM - 2635: Resolved an issue where the DNS Autogenerator Gadget would show a "The forward zone doesn't exist" message after an initial run.

IM - 2636: Updated KEXINIT handling in Peering configuration pushes.

IM - 2638: Resolved an issue in DNSv3 where editing a zone record would respond with a "host/value already exists" error if skip validation was not checked.

ProVision 6.0.1

ProVision 6.0 is a minor release with bug fixes and minor improvements.

Contact 6connect at info@6connect.com to schedule a demo or get more information.


New Features

(CFR denotes customer requested)

DNSv3 Zone List page

CFR / IM - 2616: Added a "Zone List" subtab to DNSv3 to list all zones, regardless of DNS Group organization.

Also: Added a link to the DNS Zones page from the DNS tab dropdown, and renamed "DNS Groups and Zones" tab to "DNS Groups".



From the DNS Zones page, users may view all forward and reverse DNS zones that they have permission to see, add new zones, delete, push, and check existing zones.


To access the DNS Zones page, click on the DNS Tab, and then the DNS Zones subtab. The zone list will be displayed with separate tabs for forward and reverse zones.

All DNS zones that the user has permission to see will be displayed, as well as options to add new zones, delete, push, and check existing zones. The list may be sorted by Zone Name or Last Modified, and filtered by Zone Name. For additional details, see the DNS Tab documentation on working with DNS Zones.

Additional Features / Improvements

Peering

IM - 2403: Improved the Admin Settings to allow the Peering - ASN field to be left blank. If blank, the Peering tab will now display a message that no ASNs are set.



APIv1

IM - 2612: for IPAM GET calls, added a boolean "true"/"false" parameter called "includeAttributes" to allow loading the attributes for all of the blocks in the collection. See API Module - IPAM , under the GET call for additional details.

The syntax for this parameter is: /api/v1/api.php?target=ipam&action=get&block=64.88.192.5/32&includeAttributes=true

Bug Fixes/Improvements

CFR - 134: Updated the DHCP Customer Configuration Gadget to support only APNIC RIRs.

IM - 2429: In the IPAM Map, corrected a bug which was preventing Recent Assignments from showing correctly. Region pins now correctly appear and dis-appear under Recent Assignments when an existing block is moved or a new block is assigned when a region is associated with the block.

IM - 2487: In the IPAM Map, regions with address information that is not a logical address format now defaults to out-of-the-way pin at global zero point off the coast of Nigeria.

IM - 2608: Resolved an issue where non-numerical IP attributes were incorrectly being converted to a number.

IM - 2610: Updates to IPAM API attributes now return all attributes rather than only the updated attributes.

IM - 2611: Resolved an issue in the IPAM API where updates to multiple blocks with attribute values were not returning error messaging if the update failed.

IM - 2613: Corrected an issue where the DHCP Customer Configuration Gadget - Smart Assign would not assign if IP Rules were in effect for the DHCP block.

IM - 2614: Resolved multiple minor DNSv3 bugs including: Fixes with AAAA and NS record monitors, resolving a temperamental Dynamic Update switch on converted dnsv2 zones, and added a new option relative path (in the server config) for a chrooted environment for ISC BIND.

IM - 2619: In the DHCP Customer Configuration Gadget, clearing out the Domain selector will now also clear out the selected VLAN.

IM - 2621: In the DHCP Customer Configuration Gadget, limited the block size valid for Direct Assign to /32 and /128s.

IM - 2623: Slightly extended the time that the DHCP server waits before checking to verify server restart.

IM - 2624: Corrected an issue where the DHCP Customer Configuration Gadget - Browse Assign would not assign correctly if IP Rules were in effect for the DHCP block.

ProVision 5.3.0

ProVision 5.3.0 is a major release with new features.

PHP Compatibility

Please note that ProVision version 5.3.0 will require php version 5.6.

5.3.0 Peering DB Changes

ProVision version 5.3.0 uses the Peering DB 2.0 API. As of PeeringDB 2.0, SQL dump files are no longer provided. If you are using ProVision 5.3.0 or higher, you must follow the new install process detailed at Local Installations: Peering Setup. If you are a ProVision Cloud customer and are hosted out 6connect's environment, this has already been setup and requires no further action on your part.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

(CFR denotes customer requested)

IPAM Rules

CFR-113: Add IPAM Rules system to automatically exclude certain IP addresses from an IP Range so that they cannot be assigned with either Smart Assign or Direct Assign. For more detail, see Working with IP Rules for typical IP Rules tasks, or IPAM Rules for Admin level information.

IPAM Rules allows users to exclude IP addresses from being assigned based on the address position in the block (ie, first address, last address, nth from last).

- *Access from IPAM Manage, in the block's Action Menu*
- *Set reserved addresses by position in block:*
  - *the first position is '1', second is '2', and so forth.*
  - *the last position is '0', next from last is '-1', then '-2', and so on.*
  - *May reserve one or multiple positions in a rule.*
- *Only one rule may be applied per block*
- *Admin users may view all existing IPAM Rules, the blocks affected by each rule, and delete rules.*

Disable VLAN

CFR-112: Add "Disable" / "Reclaim" VLAN to domains (API Only).

An API parameter "enabled" has been added to the VLAN "Update" endpoint to disable VLANs that have previously been enabled for a Domain.

In addition:

- *An "enabled" field has been added to the VLAN table, and is now used to check if a VLAN is enabled or disabled*
- *The 5.3.0 upgrade script will update currently enabled VLANs to set enabled as true*
- *Text notes and relevant help links have been added to the "Enable VLAN" area of ProVision describing disable functionality via API.*

To enable / disable a VLAN via the "Update" endpoint, set the parameter "enabled" to "true" or "false", respectively, after providing the required id.

Example: /api/v1/api.php?target=vlan&action=update&id=41438&enabled=false


For details on the VLAN update endpoint, see API Module - VLAN - (update)

Resource Linkage Gadget

CFR - Users would like a way to link Resources to other Resources without needing a hierarchy relationship.

In the ProVision GUI, you can now create links to other Resources and display them in one place. This gives you more flexibility to centralize data without requiring direct relationships.

For additional information on using the Resource Linkage Gadget, see the Gadgets page.




Updated Chart View

Chart View has been replaced with an updated, interactive tree similar to the Resource Tree Widget.

In addition:

- *Chart View now displays as a node-based tree. View in horizontal or vertical tree mode by clicking the "Switch Chart Orientation" button.*
  - *Left click and drag within the tree view, or scroll wheel in/out to change the area viewed.*
  - *Single or double-clicking on a node with children will collapse or expand the tree at that resource.*
  - *Clicking and dragging a resource node to another resource will relocate the resource to be a child of the resource it is dropped on.*
- *View in fullscreen mode by clicking the "Fullscreen" button.*
- *Filter the tree view by selecting a specific Top Resource and/or Section, and click "Reload" to apply. To return to a TLR level view, deselect the Top Resource and click "Reload".*
- *The chart view Action Menu (wrench icon) has been replaced by a context menu that opens at right-clicking on a resource.*
- *Context menu actions include Quick View, Edit, Clone, and Delete functions. Quick View shows summarized details about the resource and its children.*
  - *From Quick View, users can navigate to the resource's main Entry page, and that of its children.*



Additional Features


Updated Log Tab / Logging Portable Gadget

The "Log" tab has been updated and replaced with the ProVision Log Portable Gadget.

The Log Gadget provides detailed information on actions performed in ProVision. Actions may be filtered by Level, Category, Log ID, User, and Time (specific or a range), as well as results-per-page option set. Additional filtering options allow targeting of specific log entries.

Clicking on the blue arrow at the beginning of each log entry shows additional details about that log item.

For additional details on the Log Tab, see Log. For details on Portable Gadgets, see Portable Gadgets and Getting Started With Portable Gadgets .



The following filters and options are available for this module:

Level: Under the "Level" dropdown box, select "All Levels", "Emergency", "Alert", "Critical", "Error", "Warning", "Notice", "Info", or "Debug".

Category: Under the "Category" dropdown box, select "All Categories", "User", "IPAM", "Resource", "Resource Holder", "DNS", "Peering", "Assistant", "API", "NTP", "Device", or "Reporting".

Results per page: In the "Results per page" text box, type the desired number of log entries to see per page. By default, this value is set to 100.

Search: Type a search string, such as the name of a resource, then click the "Search" button.

Additional detailed filter and search options are available under the "More Options" link.

Log ID: Retrieve a specific log entry from its log_id parameter.

IP: Search by IP of the machine that created the event in the log.

Username: Filter logs by ProVision username, or by "Unknown" user.

Time: Filter log entries by exact time created. Must be in datetime format (2016-08-14 16:41:18).


Time Minimum: The earliest day and time of log entries to show in results. Must be in datetime format (2016-08-14 16:41:18).

Time Maximum: The latest day and time of log entries to show in results. Must be in datetime format (2016-08-14 16:41:18).

User Preferences Page

IM - 2245: A User Preferences page has replaced the previous User Preferences pop-up module.


To access the User Preferences page, click the gear icon at the top right section of the header from any page and select "User Preferences".The User preferences page allows users to update their password and enable/disable help pop-up bubbles.



VLAN Chart UI Updates

The VLAN chart page under VLAN Admin has been updated with a new UI. For details, see Working with VLANs.


- Hovering over VLAN Ranges displays Tag, VLAN Start, VLAN End, and VLAN Count information.
- Editing Tags (Tagging and Untagging Ranges) now occurs under the "Edit VLAN Tag Range" section of the page.
  - *To Add or Remove a tag range, select the desired Tag to edit, then input the VLAN Start and End values. Click "Add Tag Range" or "Remove Tag Range", respectively.*
  - *Adding or removing a single VLAN tag may be done by entering the same value for VLAN Start and VLAN End.*
- The Domain Name may be edited for user-created Domains under the "Edit Domain Name" section.
  - *Edit the Domain Name as desired (limited to 30 characters), then hit "Save".*



IPAM Gadget Parent Aggregate Link

CFR / IM-2398: A link to the parent aggregate has been added to the IPAM Gadget -> Edit block module. This link takes the user directly to IPAM Manage for the aggregate.

In the IPAM Gadget, navigate to the desired block's Action Menu. Then, click "Edit". The Parent Aggregate link will be displayed at the top right of the edit module.



Bug Fixes/Improvements

IM-1868: Improved responsiveness of help icons in Contacts.

IM-1955: Removed erroneous delete link from the Resources -> Generic Name resource list.

IM-2099: In IPAM Manage, lists filtered by mask can now be exported to .csv.

IM-2127: A User with Read/Create permissions can now create / import contacts in the Contacts Manager.

IM-2146: Read-only users no longer have access to "Set Role" or "Unassign" in the Contacts Gadget Action Menu.

IM-2150: Fixed "User Preferences" link when accessed from Dashboard.

IM-2219: In the Scheduler date picker, calendar highlights now show on the correct date.

IM-2241: When viewed by a user with limited permissions, the IPAM Manage (Advanced) "Assigned To" filter will correctly limit to allowed resources.

IM-2242: Aggregates with only one block / mask will no longer disappear in IPAM Manage when filtered by that block's mask.

IM-2244: Resolved an issue where an Invalid Vlan would prevent IP block edits.

IM-2246: Resolved an error that occurred when clicking on blocks in expanded IPAM Manage parent view.

IM-2247: Cleaned up overhanging text on IPAM Manage labels.

IM-2256: A read only user will no longer be able to access the "Clone" or "Edit" pages from the Resource Action Menu.

IM-2260: A user with CRUD permissions on only specific resources may now create IPAM Aggregates for those resources.

IM-2261: Improved handling of various functions for users with characters in their first / last names.

IM-2267: Filtering by mask / searching in 1918 aggregates with duplicates no longer returns results from the duplicate block.

IM-2271: Can now use IPAM filters on results of IPAM Advanced search terms.

IM-2272: Improved global and IPAM search behavior.

IM-2273: Resolved errors that could occur when "Clean Up" template was used on an aggregate without a mask selection.

IM-2278: Resolved issue where an edited VLAN for a block would reset to the default domain.

IM-2280: Using IPAM get API call 'search' in conjunction with 'tags' will now filter the search results by the provided tag(s).

IM-2281: Global search now also searches a resource's CustomId field.

IM-2282: Resolved an issue with the IPAM "Update" API call where not including a region update would remove the region from the block.

IM-2284: Improved handling of double-byte characters for text input boxes throughout ProVision.

IM-2286: Updated "Cancel" button style in the Scheduler.

IM-2288: Failed Scheduled DNS Pushes now email a failure notice with the appropriate error message.

IM-2293: The search box will no longer display below the navigation bar in the Admin area of ProVision when viewed in Chrome from a Windows 10 OS.

IM-2303: Users will now get an appropriate message when attempting to edit non editable system resources (6c resources).

IM-2304: Resolved an issue where the Resource Entry Action Menu Edit option would link to the wrong Resource.

IM-2312: Fixed an issue where email notification options (NOC / Policy / Technical) for peering sessions were not populating.

IM-2316: The notes field for a local contact will no longer display "array" when editing instead of the user value.

IM-2331: Revised VLAN Domain Names to accept double-byte and special characters, with a limit of 30 characters.

IM-2333: Revised "Add" VLAN link text to "Enable" for clarity.

IM-2349: Resolved an issue in the IPAM Gadget where Smart Browse would not respect the "Resource" filter selector. Results will now correctly return only subassignable blocks from the selected resource when provided, or only "Available" blocks otherwise.

IM-2350: Smart Browse will now correctly limit results when "strict mode" is enabled for tags.

IM-2353: Dashboard Resource Tree Widget will now restrict or hide the tree elements if the user does not have permissions to view at the current parent level.

IM-2358: Smart Assign will now return an appropriate error message when unable to assign a block due to only non-subassignable blocks meeting the provided filter conditions.

IM-2362: Fixed treeview IPv6 parent link.

IM-2370: Replaced the DNS zone "Reassign" option resource dropdown with a searchable list of all Resources.

IM-2365: Improved IPv6 aggregate address validation when creating new aggregates.

IM-2381: Notes once again display in the peering session list "Notes" column.

IM-2382: Improved handling of the peering sessions window when no sessions are found.

IM-2388: Resolved issue with Peering Email cc: / bcc: fields not sending.

IM-2390: Resolved issue with IPAM Gadget "Strict Mode" tag filtering when used with tags containing special characters or double-byte characters.

IM-2399: Having a user assigned to multiple groups no longer duplicates entries on the Resource Entry list page.

ProVision 5.3.2

ProVision 5.3.1 is a minor release with bug fixes.

PHP Compatibility

Please note that ProVision version 5.3.0+ will require php version 5.6.

5.3.0 Peering DB Changes

ProVision version 5.3.0+ uses the Peering DB 2.0 API. As of PeeringDB 2.0, SQL dump files are no longer provided. If you are using ProVision 5.3.0 or higher, you must follow the new install process detailed at Local Installations: Peering Setup. If you are a ProVision Cloud customer and are hosted out 6connect's environment, this has already been setup and requires no further action on your part.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Additional Features

IPAM Rules for DHCP Pools

IPAM Rules may now be applied to DHCP Pool ranges when using Smart Assign.

For Smart Assign DHCP Pool creation, existing IPAM Rules may be applied to reserve additional addresses out of the pool range. To create an IPAM Rule, see IPAM Rules.

DHCP Pools and IP Rules


For DHCP Pools, ProVision automatically reserves the first and last address of the pool for Gateway and Broadcast addresses, respectively.

If an additional IPAM Rule is applied, the rule will begin with the second address in the block.


For example: if a DHCP Pool is created using 10.0.0.64/29 with an IPAM Rule of "Reserve First Three", the resulting pool range would be 10.0.0.68 through 10.0.0.70, as the first four as well as the final address would be reserved.
To apply an IPAM Rule to a DHCP Pool, select "Apply an IPAM Rule" to view a list of existing rules.



Select a rule, as well as any other criteria, and click "Add Pool".



The resulting Pool will be created with the adjusted range.



Bug Fixes/Improvements

IM-XXX: General CPNR connector enhancements.

IM-2434: Resolved an issue that prevented updates to Contact Info from saving.

IM-2438: Resolved an issue that prevented updates to Contacts from saving.

IM-2343: Resolve an issue where smart assign was unable to assign to /32 and /128 blocks under subassignable parents. Blocks of /32s and /128s are now subassignable as a result.

IM-2360: Smart Browse now only shows blocks not assigned to the current resource.

IM-2367: Subassignable blocks in IPAM Manage may now be merged, so long as it, its parent, and its sibling block are all assigned the same resource.

IM-2389: Users lists in the User Permissions Chart and Check User Permissions areas no longer include deactivated users.

IM-2446: Restored pagination on the Resource Entries lists.

IM-2449: Replaced "No User Groups" page with a "Permissions Error" page that displays for users attempting to log in with no Groups or Resource permissions.

IM-2450: The "Group Information" hover display now lists the resources the current user's group(s) affects.

ProVision 5.3.1

ProVision 5.3.1 is a minor release with new features and bug fixes.

PHP Compatibility

Please note that ProVision version 5.3.0+ will require php version 5.6.

5.3.0 Peering DB Changes

ProVision version 5.3.0+ uses the Peering DB 2.0 API. As of PeeringDB 2.0, SQL dump files are no longer provided. If you are using ProVision 5.3.0 or higher, you must follow the new install process detailed at Local Installations: Peering Setup. If you are a ProVision Cloud customer and are hosted out 6connect's environment, this has already been setup and requires no further action on your part.

Contact 6connect at info@6connect.com to schedule a demo or get more information.


New Features

(CFR denotes customer requested)


VLAN Metadata

CFR-114: Customizable metadata fields are now available to hold VLAN-specific information such as Location, Client, Firewall, Gateway, and more.

These fields can be enabled and disabled in the VLAN Admin section of ProVision, and viewed / edited under "Edit VLAN" in the VLAN Tab.




Access VLAN Metadata Fields by selecting "Metadata Fields" from the VLAN Admin navigation dropdown in the Admin section of ProVision:




- *To enable a new field, type the desired field name in an empty text input box under "Field Display Name", and select the check box next to the new name. Then, click "Save" to save your changes. Field display names may be edited at any time by simply typing the desired change into the "Field Display Name" box and saving your changes.*
- *Once enabled, a metadata field displays for all enabled VLANs.*
- *To disable a metadata field, deselect the check box next to the Field Display Name and click "Save". Any data that exists under a disabled field is retained, and will reappear once the field is re-enabled.*

View and update VLAN Metadata from the "Edit VLAN" module from the VLAN Tab:



From the VLAN Tab, expand the desired domain on the left sidebar. Click on the desired VLAN, and select "Edit".



In the "Edit VLAN" module, the enabled Metadata fields will be visible. Type in the metadata information for the selected VLAN, and click "Save".

For additional information, see Working with VLANs.

CPNR Connector

CFR-115: CPNR Connector - ProVision's DHCP system now supports the Cisco PNR DHCP device.

Additional Features

Report-by-Mask (API only)

CFR-116: Report-by-Mask endpoint that provides by-mask breakdowns of total IP addresses, assigned, allocated, in holding, available, assigned %, holding %, available %, and allocated %. See API Module - IPAM (Mask Report) or expand below for additional information.

Details:

Endpoint: /api/v1/api.php?target=ipam&action=maskReport

Example: /api/v1/api.php?target=ipam&action=maskReport&regions=DEN

Sample Return:

{"success":1,"data":{"IPv4":{"total":576,"available":21,"assigned":555,"holding":0,"allocated":446,"prefixes":{"32":{"assigned_percentage":91.666666,"holding_percentage":0,"available_percentage":8.333333,"allocated_percentage":0,"total":12,"available":1,"assigned":11,"holding":0,"allocated":0},"31":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":30,"total":20,"available":0,"assigned":20,"holding":0,"allocated":6},"30":{"assigned_percentage":50,"holding_percentage":0,"available_percentage":50,"allocated_percentage":0,"total":8,"available":4,"assigned":4,"holding":0,"allocated":0},"29":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":20,"total":40,"available":0,"assigned":40,"holding":0,"allocated":8},"28":{"assigned_percentage":66.666666,"holding_percentage":0,"available_percentage":33.333333,"allocated_percentage":33.333333,"total":48,"available":16,"assigned":32,"holding":0,"allocated":16},"27":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":50,"total":64,"available":0,"assigned":64,"holding":0,"allocated":32},"26":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":100,"total":128,"available":0,"assigned":128,"holding":0,"allocated":128},"25":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":100,"total":256,"available":0,"assigned":256,"holding":0,"allocated":256}},"assigned_percentage":96.354166,"holding_percentage":0,"available_percentage":3.645833,"allocated_percentage":77.430555},"IPv6":{"total":16777216,"available":0,"assigned":16777216,"holding":0,"allocated":0,"prefixes":{"41":{"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":0,"total":16777216,"available":0,"assigned":16777216,"holding":0,"allocated":0}},"assigned_percentage":100,"holding_percentage":0,"available_percentage":0,"allocated_percentage":0}}}

Required Parameters:

None

Optional Parameters:

resource_id	INTEGER	1234	Integer value of a Resource ID. If provided, the system will display an IPAM Mask Usage report limited to blocks associated with a single resource.
tags	STRING	"Customer"	Comma separated list of tags. If provided, limits the IPAM Mask Usage report to certain tags (standard tag mode).
regions	STRING	"DEN"	Comma separated list of regions. If provided, limits the IPAM Mask Usage Report to blocks associated with the provided region(s).

Bug Fixes/Improvements

IM-2056: User Dashboards now update in the dashboard selector dropdown after renaming.

IM-2408: Updated log sorting for events occurring at the same time to ensure descending sort.

IM-2417: Can once again add missing region references in IP Import from .csv.

IM-2420: Improved ability to move resources when viewed in vertical mode in Chart View.

IM-2421: Resolved issue in the Scheduler where "One Time" would temporarily be prepended on new tasks.

IM-2427: RIR Integration is now accessible for IPv4 /31 blocks.

IM-2428: Resolved an issue in IPAM Manage - Advanced where the domain filter would display a wrong domain-vlan combination.

ProVision 5.2.0

ProVision 5.2.0 is a major release with new features.

PHP Compatibility

⚠ Please note that ProVision version 5.2.0 will require php version 5.6.


Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

(CFR denotes customer requested)

Portable Gadgets

IM - 2165: Portable Gadgets are drop-in code snippets that use the ProVision API to bring in data to other systems or web pages.



Currently, three Gadgets are available: Global Search, IPAM Search, and DHCP Search. Each Gadget comes with various options for display style, number of records return, or behavior. Additional client-side style customizations may be made to further integrate the gadget with company styles.

For more information, see Portable Gadgets and Getting Started With Portable Gadgets.

LDAP/AD integration – option for Native Groups


IM - 2163: LDAP Authentication now has an option for native groups that does not require the 6connect schema.

How to use native groups:

From the Admin Preferences page of ProVision, under Authentication Options, find the "LDAP Group Attribute" field. Enter the attribute name for your LDAP server's internal list of user groups (for example, "memberOf"). If this Group Attribute has been set, it will be used first for authentication, otherwise the 6connect schema will be used.

After setting up the Group Attribute, the authentication settings can be tested for a user via the Remote Authentication Tester on the Admin Preferences page.

Remote Authentication Tester



Authentication settings can now be checked for a user with the Remote Authentication Tester.

Select the Login Method (Radius or LDAP), enter the Username and Password for the user, and then click "Test Login".

Additional Features


DHCP Server Monitoring and Pool Utilization

IM - 2164: A DHCP Scan Server function is now available in the DHCP Management Gadget.

Scan Server provides a "Scan Now" button, which scans the DHCP server and returns found IPs under DHCP Pools.



The returned IPs are divided by Pools and IPv4/IPv6. Returned fields include MAC address, IP address, and name. The percentage utilization of IP space out of the available DHCP Pool space is also included at the top of the list.




DHCP Current Pushed Configuration display / Improved error handling

CFR/IM - 2248: Improved DHCP error handling for cases of server misconfigurations.

Also added a display under the DHCP Management Gadget to view the last successfully pushed configuration. It does not reflect unpushed changes or failed pushes.

To view the configuration text, navigate to the DHCP Management Gadget for the desired DHCP server, then click on "Current Pushed Configuration". For additional details on the DHCP Gadget and Pushing, see our DHCP Documention.




Resource Query performance and security enhancements

IM - 2166: Resource Query has undergone various performance and security enhancements.

Direct Assign and Smart Assign enhancements

IM - 2160: Direct Assign and Smart Assign are now transaction-safe atomic operations, improving scalability of calls.

Revamped installer/upgrader




IM - 2167: install/configTest.php has been updated to provided a smoother install or upgrade experience. The installer now provides clear step-by-step checks for required dependencies and settings. At each step, all items marked in red must be corrected before proceeding to the next. If you have any questions or require assistance correcting a mis-configuration, please contact support@6connect.com.

URL Custom Field Type

CFR / IM - 2133: A URL custom field type has been added to the available fields when creating a Section. The URL field checks if the field value contains "https://www.", and if not, adds it as a prefix to the field value, providing a clickable link on the Resource's Entry page.


To add the URL field to a Section, edit the desired Section, then drag and drop the URL field type into the Section's field list and save your changes.




Edit the Entry page for the desired Resource (that is associated with the previously edited Section), and populate the URL field with desired address.

Note: The URL field will automatically prefix the value with "https://www." if it is not already included in the address. However, be sure to include the Top Level Domain.

After the field is filled out, click "Save".



The URL field will be then accessible as a clickable link that opens in a new tab.



Bug Fixes/Improvements

IM - 1782: IPAM, DNS, and VLAN Tags now consider spaces and letter case to prevent duplicate entries.

IM - 2061: Resolved duplication of Resource IDs in IPAM / VLAN Manage that occurred when the "Assigned" header was clicked.

IM - 2113-2115: Improved handling of limited permissions for adding DHCP servers.

IM - 2138: Resolved a hover issue when viewing the VLAN Tags chart in Firefox.

IM - 2142: The "Templates" link in the IPAM / VLAN manage action menu is once again functional.

IM - 2154: In the Dashboard Activity Chart Widget, clicking on DNS activity now shows detail text.

IM - 2156: Single-block IPAM Updates made through the API now respect the tags_action parameter.

IM - 2157: Resolved an issue where deleting an IP aggregate could result in orphan DHCP pools under that aggregate.

IM - 2158: Updated IPAM API parameter "isAggregate" to filter correctly when set to false.

IM - 2168: Revised the "Contact Us" Widget to have "feeback@6connect.com" as the default feedback address.

IM - 2173: The "Comment" section for local contacts no longer duplicates upon editing.

IM - 2176: Resolved an issue that would prevent some one-time scheduler tasks from running.

IM - 2183: IPAM Manage "Generic Code" filter header now updates with user provided value.

IM - 2184: Resolved issue where "LIR" and "Region" were not able to be de-selected when editing an IPAM block.

IM - 2187: Updated IPAM error message "(Block) is already assigned to (Resource)" to include both resource name and number.

IM - 2198: Resolved issue on a resource's Entry page where an extremely long breadcrumb would expand outside its boundary.

IM - 2200: Fixed an issue where unassigning a child block with skip hold could cause the parent block's sibling to lose assignment.

IM - 2201: Revised the DNS Gadget - Zone Delegation "Delete" icon.

IM - 2204: When "Merge after Unassign" is enabled in IPAM Configuration, sibling blocks will no longer merge if one block is in the holding tank.

IM - 2205: When "Merge after Unassign" is enabled in IPAM Configuration, blocks will now automatically refresh after merging occurs.

IM - 2206: Resolved an error that prevented the region from display for newly created top-level aggregates.

IM - 2209: VLAN Chart mouseover functions once again work in Firefox.

IM - 2210: Updated the resource selector in Edit Groups to be a searchable list.

IM - 2218: Smart Browse is now smarter in assigning blocks when duplicate 1918 aggregates exist.

IM - 2221: Removed the radio toggle for text / html email options under Peering - Email Tech /NOC / Policy Action Menu items.

IM - 2225: The IPAM Filter Aggregate List box will now be hidden if no aggregates are viewable.

IM - 2227: Cleaned up error messages when adding a user.

IM - 2231: Fixed an issue that would prevent updates to IPAM blocks propagating to children if tags were included.

IM - 2232: Resolved error in IPAM Manage that would temporarily hide the VLAN information when selecting "Unassign / Skip Hold" on a block.

IM - 2233: Improved IPAM Tab loading time.

ProVision 5.2.2

ProVision 5.2.2 is a patch release.

PHP Compatibility

⚠ Please note that ProVision version 5.2.0 and above requires php version 5.6.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes/Improvements

IM - X Fixed an issue with the IP Import Process.

ProVision 5.2.1

ProVision 5.2.1 is a minor release with bug fixes.

PHP Compatibility

⚠ Please note that ProVision version 5.2.0 and above requires php version 5.6.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes/Improvements

CFR- 96: Improved API return message passing in cases where you cannot split a block to direct assign it.

IM- 1590: After deleting a child resource, ProVision now navigates back to the parent resource's entry page.

IM- 2202: Title on redirect page changed to "6connect ProVision".

IM- 2259: In the Contacts Gadget, resolved a bug where users could erroneously use a single space as a search term.

IM- 2252: Fixed an issue in IPAM Manage - Multi-block edit where the LIR dropdown would not populate unless a single-block edit had been performed first.

IM- 2254: Resolved a bug where a Resource was not selectable when creating a Group.

IM- 2258: Users with permissions to only select resources can now create DHCP servers for those resources.

ProVision 5.1.0

ProVision 5.1.0 is a major release with significant new features.

PHP Compatibility

⚠ Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

(CFR denotes customer requested)

UI Updates:


Version 5.1.0 introduces a new look to ProVision! Minor graphical and user consistency improvements have been made throughout ProVision, creating a cleaner user experience.

Included in the UI changes, but not limited to:

- Throughout ProVision, the Action Menu (wrench icon) has been replacing individual action icons. Clicking on the wrench will open a menu of options specific to the ProVision area.
- Update color scheme, css, and many button styles: Close buttons are now a small "x" in the top right corner of a popup box, rather than an offset circle icon. Many delete icons have been replaced with a larger "Delete" button.
- IPAM - Top Level Aggregates have new look! They now show a chart view detailing allocations, the top five resources assigned under an aggregate, and recent assignments. The "Manage", "Template" (Merge / Clean Up), and "Delete" functions are now contained within the Action Menu (wrench icon).



- DNS Admin now has a drop down menu to quick-select common links.



- The **Templates** tab has been removed from the Admin tabs, and included under the DNS Admin drop-down menu.
- Peering Import has been removed from the **Peering** tab dropdown menu, look for it instead in Admin-> Data Import


Reverse API Tools - Beta

Reverse API calls and UI elements have been added to ProVision. This is a powerful tool that allows for integration with outside APIs to improve workflow and create custom display content.


Included in this feature:

- Reverse API calls: Available at Reverse API - Detail. An overview of the API format is available in the documentation at Reverse API
- Reverse API ProVision page: This page allows for endpoints to be built and provides a text editor to create presentation JavaScript commands.


  The Reverse API Management page is accessed from the **API** tab in the Admin section of Provision, just click on the circled link.



  Add endpoints, insert presentation scripts, and test calls against selected Resources. See Reverse API UI for more details.



- Reverse API Console Gadget: This new gadget allows for constructed endpoints to be selected, and their presentation code displayed on a Resource Entry page. For more information, see Gadgets.




Task Scheduler

The Task Scheduler allows you to manage and schedule repeating tasks in ProVision. Three predefined tasks are available to schedule - Process Holding Tank, DNS Zone Transfer, and Backup. Note: This provided Backup task is intended to be the primary reoccurring method of backup.

Included in this feature:

- Scheduler ProVision page: This page allows for tasks to be added to the scheduler and managed. It is accessed from the Admin section of ProVision, under the **Scheduler** Tab. An overview of the **Scheduler** Tab is available on the Scheduler Tab page.
- Scheduler API calls, available at Scheduler API. Please note that the Scheduler API is in beta, and is subject to change.



Enabling the Scheduler

To enable the scheduler for a hosted instance, add the following to cron:


* * * * * /usr/bin/php /var/www/html/6c_<INSTANCE_ID>/scheduler/task-runner.php

To enable the scheduler in a local instance, add the following to cron:
* * * * * /path/to/php /path/to/ProVision/scheduler/task-runner.php

Contact Manager

The new Contacts page under Resources allows you to manually create contacts, import contacts from ARIN/RIPE, and manage them in one place. See the Contact Manager documentation for additional details.

Access the Contact Manager from the **Resources** tab, under Contacts.




Included in this feature:

- Create Contacts manually and assign under a parent resource's permissions structure

  Add new contacts manually by hitting the "Create Local Contact" button.

  Fill out desired information and click "Create"


  

- *Import Contacts from ARIN / RIPE through a handle search*


  Import contacts by ARIN / RIPE Handle by clicking on the "Import from RIR" button.




Then enter the RIPE/ ARIN handle and press "Search".



- View Contacts as a list or tiles



- Assign contacts to a resource through the Contacts Gadget




Note: Contacts currently existing in ProVision will be moved to the new contacts area at upgrade, however, new contacts must be added through the new page to be under the Contact Manager. Any contacts added through previous methods (as a section, or through a resource import function) will not appear under the contact manager.

Improved Tagging

IM-1734: Improved DNS Tag functionality

- Added a "DNS Tag" management link to DNS Admin.
  Add and edit DNS Zone Tags similar to how IPAM Tags are added - Click "Add Tag", type in the new tag name, and hit the "Add" button.




- Updated the "Edit Tags" interface on the DNS Zonelist page.
  The list of DNS tags available now show in a dropdown menu, and multiple tags may be added / removed in one session. Click inside the tag listing box, select the desired tag(s) from the dropdown list, then hit the "Update" button. To remove a tag from the zone, click on the "x" in front of the tag.



IM- 1656 / 1697 The Tag / List system, including IPAM Tags, DNS Tags, and Subnets have been standardized to provide the same user experience when working with the lists.

- All lists now used the same Add Item interface, and have updated sorting and display.
  Click the green '+' / "Add Item" symbol to add new items to the list.




Additional Features

Backup Manager Updates

IM-123: The Backup Manager has been updated to allow for manual backups to be sent to a selected server Resource in ProVision. See Admin Preferences for additional information.

Select the backup location - either to the 6connect cloud, or an alternate server resource that exists in ProVision. Then hit "Backup Now" . It is recommended to perform a manual backup prior to imports or other major changes.




Smart Browse


IM- 1800: Browse Assign / List Available Blocks has been replaced with Smart Browse.

Smart Browse utilizes the smart assign parameters as search filter criteria, then allows you to manually select blocks to assign under that criteria.

Under the "Smart Assign" area, select the IPv4/IPv6, Size, RIR, Region, and/or Tags that you wish to filter to in the available blocks list.




Click on "Smart Browse" to bring up a list of IP aggregates meeting that criteria, which you can then select the block(s) to assign. A green check will show next to the block once assigned. You may assign multiple blocks per browse session.



API and GUI Skip Holding

IM- 1587: IPAM "Unassign" API call now has a parameter to skip the holding tank. *See: API Module - IPAM - Unassign, optional parameter "skipHolding" for more detail.*

IM- 1587b: The option to "Unassign and Skip Holding" has been added to the IPAM Manage Action Menu (wrench icon).



Automatic Re-aggregating of Reclaimed Blocks

CFR- 6: IP blocks are re-aggregated as they are reclaimed.

After unassigning blocks / overriding holding, newly available blocks will be merged upon next page refresh.


Initial State:



Unassigned / Override Holding:




Automatic merging after page refresh:



Propagate to Children


IM- 1725: Added "Propagate to children" option for single-block updates for IPAM.

When editing attributes for parent blocks in the IPAM Manager (Action Menu -> Edit), select "Propagate attributes to all children" to carry through changes to child blocks.



Holding Tank Improvements

IM- 1098: Holding Tank displays detailed block information



IM- 1777: Can now set permissions on the holding tank for subassigned blocks via the 6connect holding resource. See Holding Tank Management for details.


IPPlan Importer (Toolkit Item)

Now included in the Toolkit (collection of command-line tools available at /tools) is the IPPlan Importer. The IPPlan Importer is a command-line tool to facilitate importing IPs from an IPPlan database into ProVision. This tool can be used via two approaches: generating .csv files via the tool only, then using the ProVision IP Import UI to import the csv files (Connector), or as a full command-line import solution, bypassing the ProVision UI entirely (Importer). Detailed instructions are available at IPPlan Importer.

Duplicate Reverse Zones

IM- 1853: Allow user control over duplicate reverse zones

In DNS Admin, under the Global DNS Zone Defaults link is the option to allow duplicate reverse zones. Check to enable / disable allowing duplicate reverse DNS zones. If duplicate reverse zones already exist, those zones must be removed before disabling duplicates. If a zone has duplicates, a link appears in the top right corner of that zone's ViewZone page.



Bug Fixes/Improvements

CFR- 66: Searching for IPs brings up related search results

IM- 1227: Included reset tool in /tools for factory reset

IM- 1432: Updated warning message upon deleting a permissions group

IM- 1578: Updated license expiry check

IM- 1599: Configtest updated for Peering

IM- 1657: Updated UI alignment on DNS zone import page

IM- 1667: Duplicate DNS zone names are supported

IM- 1670: Improved Setup Wizard

IM- 1690: DHCP gadget UI updated to no longer allow an item in the existing pool to be added multiple times

IM- 1720: Updated user permissions to prevent a read only user from accessing DNS Edit Tag

IM- 1724: Updated Smart Assign to allow assigning blocks that have been multi-edited to allow subassignments

IM- 1726: Added example format to DNS SOA formatting error message

IM- 1730: 6connect logo now directs the user to the dashboard page

IM- 1733: Improved Peering "Add Session" error message

IM- 1736: Resolved an issue in IPAM RIR Integration where the Net name was not cleared from previous SWIP action

IM- 1737: Auth - testLDAP no longer returns error if ldapMode=SSL

IM- 1746: Resolved an issue in DNS zonelist where the Action Menu (wrench) was not functional after using header sorting

IM- 1748: Updated zone list sorting ability for Tags, DNSSEC, and Records.

IM- 1755: Fixed an issue where adding a slave under DNS gadget zone delegation would fail

IM- 1759: Nomenclature updates made to IPAM Manage Templates and Action Menu (wrench icon). "Auto Aggregate" is now "Clean Up", "Aggregate" has been renamed "Merge"

IM- 1760: Fixed the graphical display of the IPAM Manage email form

IM- 1769: Resolved an error where users with limited permissions were unable to edit IP blocks

IM- 1780: The IPAM "Advanced" button is now clickable for limited-permissions users

IM- 1783: Removed VLAN field for IPAM manage when editing multiple blocks

IM- 1789: Adjusted DNS Templates zone reordering arrows to have bounds checking

IM- 1790: Resolved an issue where API zoneTemplate update incorrectly reports success in some cases

IM- 1794: Dyn Server update no longer displays an SOA error

IM- 1796: Improved error messages in DNS Audit tool

IM- 1798: Section pages that have child entries now have an informational message of "This resource cannot be deleted because it has entries created from it."

IM- 1808: IPV6 Alphanumeric sort has been updated to be more alphanumeric

IM- 1850: Cleaned up foreign key restraints

IM- 1841: Removed unused columns from auth

IM- 1843: Resolved an issue where Peering Communications did not separate peer with 2 ASNs in an exchange

IM- 1844: Peering sorting for import and communications improved

IM- 1848: Peering import router list now shows routers with no peer groups

IM- 1849: Removed all old/unused columns from config table and admin page

IM- 1851: Removed unused columns from Auth

IM- 1852: Cleaned up unused tables

IM- 1881: Reallocate and Detail Reassign buttons have been removed from RIR Integration in preparation for a future SWIP update

IM- 1883: The default number of rows returned in reporting for either html or .csv is now 5000

IM- 1897: A newly added peer should now show as current peer in Communications list for that exchange

SEC- 4: Various security improvements implemented

ProVision 5.1.4

ProVision 5.1.4 is a minor release for cloud and local installations with bug fixes.

PHP Compatibility

Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade.

MySQL Compatibility

Please note that ProVision versions 5.1.3 and newer require mysql 5.6.+. For local installations, please upgrade mysql prior to installing the upgrade.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Improvements

IM- 2131: Improved IPAM Tab Limited Permissions Handling

Improved how the IPAM Tab handles viewing of top-level-aggregates with respect to limited-permissions users.

The handling rules are as follows:

- If you have permissions on the resource the top-level aggregate is assigned to, then you have vision over the entire top-level aggregate.
- If you have permissions on an IP block but not its top-level aggregate, you do not have vision of that top-level aggregate in the IPAM tab. Instead, you should manage your IP space via the IPAM gadget on the resource page.
- If you do not have permissions on an IP Block, you should not see it in the IPAM Tab regardless of the status of its top-level aggregate.

Bug Fixes

IM- 1899: Read only users can no longer assign Contacts to a Resource using the Contact Gadget.
IM- 1998: Resolved an issue in VLAN Admin > Manage, where hover over untag ability was lost after using single-point untag.
IM- 2098: IPAM Manage LIR filter once again filters LIRs.
IM- 2111: Editing a block that is located deep within an extensive list in IPAM Manage no longer causes the Manage screen to reset to the top of the list.
IM- 2116: The Scheduler "Last Run Time" now correctly displays according to server timezone instead of user timezone.
IM- 2117: Fixed an issue where some blocks associated with named VLANs were unable to be edited.
IM- 2127: The DNS create zone resource picker now limits selection list to match permissions.
IM- 2128: The DNS create zone ability is now hidden for users without DNS create permissions.
IM- 2135: Resolved an issue with email options not opening in the peering gadget.
IM- 2139: Fixed edge-case block condition that would interfere with the IPAM Gadget loading.
IM- 2141: VLAN Manage IPs - search by tag now works with Firefox.
IM- 2143: Fixed the "Update Session State" link in the Peering Sessions module.

ProVision 5.1.3

ProVision 5.1.3 is a minor release for local installations with new features and bug fixes.

PHP Compatibility

Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.

MySQL Compatibility

Please note that ProVision 5.1.3 requires mysql 5.6.+. For local installations, please upgrade mysql prior to installing the upgrade.


Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features

(CFR denotes customer requested)

Customizable Dashboards:

The Dashboard Tab has undergone a major UI overhaul, and is now customizable!



The new Dashboard is comprised of modular "Widgets" that show different types of information. These Widgets may be added, moved, and edited to create personalized Dashboards. On top of this, four different column layout options are available to organize the overall Dashboard layout to suit your needs.

Dashboards (excepting the Default Dashboard) are tied to user login, and do not have dependencies or requirements - they are just HTML / Javascript - so no additional installations are required, and users may access the same dashboard between different computers or browsers.

Browser Compatibility

It is recommended to use the most recent versions of the Chrome or Firefox browsers when working with the dashboard. Due to incompatibilities with Internet Explorer, the dashboard is set to read-only mode and is not editable when accessed from IE at this time.

There are two levels of Dashboards:

Default Dashboard: The Default Dashboard is a shared dashboard for all users of the ProVision instance. It may only be edited by admin level users, but it is viewable by all users.

Individual Users' Dashboards: Additional Dashboards may be created by individual users. These dashboards are tied to the user logged in, and are only viewable / editable by that user.


Widgets:

Ten Widgets are currently available for the Dashboard. Widgets vary in purpose from static display of text elements (Markdown, Status), to highly interactive (Activity Chart, Resource Tree). Only Admin users may add or edit Widgets for the Default Dashboard; however, any user may create a personal dashboard tied to their login, and add, move, or edit Widgets for that dashboard without impacting others.

A User's permissions apply to data inside of Widgets, therefore, some users may be limited to only viewing certain data for a Widget (ie, Resource Tree).


Below is a brief overview of each available Widget:

Activity Chart (Viewable by Admins Only): Illustrates activity level for API, IPAM, DNS, Peering, and Resource areas of ProVision.



Select the desired ProVision area by clicking on the radio buttons. Then, hover over the chart, and use the mouse scroll wheel to zoom in or out of specific date / times. Clicking on a bubble will show activity detail, and resource / IP block links if applicable.


Clock: Shows the current time and date for the selected time zone, based on format set by the user.




Status: General status information on number of user / admin accounts, ProVision version number, and a 'Coming Soon' link to the future releases roadmap in the the documentation.



IP Charts: Illustrates the percentage of assigned vs unassigned hosts for 1918 / IPv4 / IPv6 space out of the total available hosts in ProVision viewable by the user.




Contact Us: Provides support email, phone, and feedback form information.




Support phone number and email address are set from the ProVision Admin settings. The feedback form email address is editable within the Widget.

Markdown Widget: The Markdown Widget is a blank slate where users may add links, text, or other content through use of the Markdown language.




Resource Tree: An interactive horizontal or vertical treeview of a selected Resource and its children.




Users may click and drag to move within the Widget, as well as zoom in and out using a scroll wheel. Clicking on filled dots will expand the tree to show the children of that resource. Double-clicking on a resource in the tree will give you the option to navigate to the resource's entry page.

iFrame Widget: The iFrame Widget sets a https URL to be viewed in an iFrame, to view stats or commonly referenced websites.



RSS Feed Widget: Shows the most recent five entries of a selected https RSS Feed. Feed links open in a new window when clicked.



Links Widget: Shows a list of links. Link URL and display may be set from within the Widget.



For more details on the Default Dashboard, editing dashboards, and working with individual Widgets, see:

- The Dashboard
- Customizing the Dashboard
- Working with Dashboard Widgets

VLAN Manager

A new, integrated VLAN management system has replaced the previous VLAN text field. Under the new system, administrative users can create VLAN domains, enable numerical or named VLANs under each domain, and then associate IP blocks with a domain / VLAN pair. Also included in this feature is a VLAN tag system allowing individual VLANs or ranges of VLANs to be associate with user-defined tags for additional organization and search functionality.

Impacts to Current Customers:

For current customers who have been using the VLAN field in IPAM, existing VLANs in your IP Blocks will be migrated as numerical VLANS under the Default Domain.

Customers using the ProVision API for IPAM functions and using the VLAN text field will need to update their API calls.

Those customers who are not actively using the VLAN field, or are not using the ProVision API for IPAM functions will not be affected.

Changes included in this feature:

- A new "VLAN Admin" tab under the administrative area of ProVision for creating and managing VLAN domains and VLAN tags. See VLAN Administration and Working with the VLAN Manager for workflow and task details.
- A VLAN submenu accessible under the IPAM module including:
  - Areas where VLANs may be enabled for domains, edited, and associated with IP Blocks (via Direct, Browse, and Smart Browse type assigning)
  - VLAN utilization charts illustrating IP block utilization under each domain/VLAN pair.
  - A "VLAN Manage" page similar in function and scope to IP Manage, but for blocks organized under specific domain / VLAN pairs.
  - See VLAN Administration and Working with the VLAN Manager for workflow and task details.
- Updated IPAM and IPAM Gadget interfaces where the previous VLAN text input box has been replaced with selectable Domain / VLAN dropdowns. See updated information in Working with IP Blocks.
- Updated IPAM and VLAN API calls. See API Module - VLAN for the most recent VLAN API calls.

Resource Cloning / Template:


Cloning an Entry duplicates the Entry and, if desired, any Child Entries existing under it.

This feature can be used to quickly and efficiently create multiple resources with same format, field information, or similar hierarchy structure. See Working with Entries for additional information.


> **Information Cloned:** Format of the original Resource (which gadgets are enabled, location, fields), contact / tech information, field information, and (if selected) Child Entries, and Child Entry sections, fields, and field informaiton - in general, items that are chosen or input at the entry creation, or input into text fields.
>
> **Information not Cloned:** IP Blocks, DNS Zones, uploaded documents - in general, items that are *assigned* to the entry rather than input into fields.

Click below for an overview on how to close a Resource:


> *To Clone a Resource:*
>
> *The Resource Clone feature may be accessed from either the **Resources** Tab dropdown menu, or from a Resource Entry page.*
>
> *From the **Resources** Tab dropdown, select "Resource Clone". This will take you to the Resource Clone page.*



You may also select "Clone" from the bottom of a Resource Entry page, in which case the Entry page you clicked "Clone" from will be automatically selected as the resource to clone.



Once on the Resource Clone Page, enter the Resource to clone, Parent Resource, and the New Name for the clone. If you wish for all children of that resource (and their children, if applicable) to be cloned, check the "Clone Resource Children" checkbox. When complete, click the "Clone Resource" button.



CFR-103: One-Click IPAM Aggregate Manage:

In the IPAM tab, Clicking on the header for an aggregate now directly opens up the Manage screen for that aggregate.

Click on the header for the aggregate (CIDR / Region) to open Manage Aggregate screen.


Scheduler Updates:

Multiple updates have been made to the scheduler:

- Task List Filters: The Task Scheduler can now be filtered! Radio button filters have been added under the time information.

  Select "Show: All" to see all tasks scheduled, or "Show: Active" to only show active tasks.

  You may also use the text input filter box, located above and to the right of the task list, to filter tasks by Name or Repeat Info keyword.



- Clarified time zone display to represent the time zone selected in Admin - Application Settings - Timezone.
- UI elements such as selector lists and calendar pickers have been updated.

IM- 1957: Chart View Improvements:

An Action Menu has been added to entries in Chart View, allowing users to view, edit, clone, and delete entries.

From Chart View, left click on the Action Menu (wrench icon) to access links to the view, edit, clone, and delete functions.

IM-1944/1945: DHCP Gadget Improvements

The DHCP Gadget has improved searching and Smart Assign capabilities:

- Improved searching of pools by Name, MAC, or IP address

  Linked Pools:

  In the DHCP Gadget, select "Name", "MAC", or "IP" from the dropdown above the linked and existing pools lists. Enter the search criteria based on your selection:

  ***Name:** Enter the text of the full or partial name of the pool*


  ***MAC:** Enter the full (ex: 00:11:22:33:44:55:66:77) or partial (:22) MAC address associated with the pool, ensuring that a colon is included in part of the search text.*

  ***IP:** Enter the full IPv4 or IPv6 CIDR of the block associated with the pool (ex: 10.0.0.0/24)*



  Existing Pools:


  Existing Pool search uses the same criteria options as the linked pools, with the added ability to include "Region" or "Resource" criteria for IP Search:



After selecting the search type and entering your search term, hit the "Search" Button and the Pools list will be filtered to matching results.

- DHCP pool Smart Assign can now use Region, Resource, and VLAN criteria for assigning

  Additional criteria options of Region, Resource, and VLAN (Domain / VLAN) are available for smart assigning a new DHCP Pool.




Enter your criteria, then click "Add Pool".

(A DHCP aggregate must already exist with the selected Regions / Resource / Domain / VLAN properties for the assignment to succeed.)

CFR- 107: Set Default Tag Radio Behavior

The IPAM Configuration page now has a setting to select the "Default Tag Selection Mode". This sets which radio button will be selected by default when working with tags in the IPAM Gadget.

Selecting "Standard", "Strict", or "Exclude" will set that option as the default when working in the IPAM Gadget.



IM - 2014: Search Improvements

- Various efficiency improvements have been made for faster search returns.
- The search screen now highlights the search term in the return data.

CFR / IM-1954 IPAM API Update

The IPAM API - Get call now has a parameter "&lastUpdateTime" to query for IPAM blocks based on the last updated time. Timestamp format is in MySQL datetime format. Query may be made for blocks updated before, after, or at the exact time of the timestamp provided. See API Module - IPAM "Get" call for additional detail.

- To return blocks updated at the exact time provided, use =[MySQL datetime format] :

api/v1/api.php?target=ipam&action=get&lastUpdateTime=2015-8-19 21:08:54

- To return blocks updated prior to the given datetime, use =<[MySQL datetime format]:


api/v1/api.php?target=ipam&action=get&lastUpdateTime=<2015-8-19 21:08:54

- To return blocks updated after the given datetime, use =>[MySQL datetime format]:

api/v1/api.php?target=ipam&action=get&lastUpdateTime=>2015-8-19 21:08:54

Updated Resource Entry List Page

The Resources -> Entries page now has action menus for each resource listed.



Clicking on the Action Menu in the Entry List View will bring up the following options:

View: Opens the resource's Entry page

Edit: Opens to the resource's Edit page


Clone: Opens the clone resource page for the selected resource

Delete: Deletes the resource, if appropriate permissions exist.

IM-1958: Improved IPAM Parent Tree View

IPAM Parent / Tree View now shows applicable Tag, Notes, and Region details for blocks.

In the IPAM Tab, under IPAM Manage for an aggregate, enter Parent / Tree View by selecting multiple masks and click "Apply". In this view, clicking on a parent block link expands into a detailed tree list showing child blocks. This list now has additional detailed information.



IM-1889: Contacts Updates


Various improvements have been made to the Contacts system

- Improved handling of limited permissions in the Contact Manager and Contact Gadget.
- Cleaned up some UI elements (duplicate headers)
- In the Contact Gadget, the ability to add and delete roles has been limited to Admin users. Non-admin users may still set existing roles.

To select an existing role to apply to the contact, under "Select Role" choose a role from the dropdown, and click "Set Role".

Admin users may add a new role by typing the role name in the input box under "Add New Role", then click "Add".

Admin users may delete an existing role by selecting the role from the dropdown under "Delete Role", the click "Delete".



Bug Fixes

IM- 1887: Selecting a backup server in Admin-> Backup Settings will now only show servers
IM- 1901: Added the ability to delete roles from the contacts gadget (Admin users only)
IM- 1923: Resolved DNS zonelist search error when clearing, replaced "Clear" button with "x" in search field
IM- 1928: Fixed an issue where assigned contacts would sometimes not show in the contacts gadget if using Firefox
IM- 1933: Resolved an issue in Resource Import from csv where changes at data review were unable to saved
IM- 1937: Cleaned up UI on User Preferences - Password Reset form
IM- 1938: Added warning message to Password Reset when user submits empty fields
IM- 1943: Deleting a DHCP IP Block on the IPAM management page will also now delete all DHCP Pool Resources that are associated with that DHCP IP Block
IM- 1951: Adding a duplicate contact via the contact gadget no longer removes all contacts from the gadget
IM- 1956: Added pagination to filtered resource list page
IM- 1974, IM- 2019: Revised various button styles to display as blue with white text

IM- 1975: Resolved issue where a Resource Search for LAN resulted in page not found.
IM- 1978: Fixed error when selecting a country during creation of a local contact
IM- 1979: Removed duplicate headers in the Contacts: Assigned To section and the Contact Gadget
IM- 1982: Treeview now performs correctly in Firefox
IM- 2005: IPAM Default Map View no longer requires a manual page refresh to view after setting
IM- 2018: DNS Allow Duplicate reverse zones can no longer be unchecked by clicking the "update" button
IM- 2029: Resolved issues with a Limited Permission user adding DHCP server
IM- 2050: Updated backup php and mysqldump paths in template
IM- 2083: Removed DNS viewzone "refresh" button

ProVision 5.1.2

ProVision 5.1.2 is a minor release with new features and bug fixes

PHP Compatibility

Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.


Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features


(CFR denotes customer requested)

IPAM Map View:


Map View will show aggregate locations / recent assignments in geographical format, based on region data assigned to those aggregates. Clicking on a location icon will bring up a current utilization graph and a link to that aggregate's IPAM Manage page. A default map view may be set by either selecting a predefined map area from the dropdown (US, US & Europe, South America, All), and clicking on "Set Default View", or a custom area set by zooming / navigating to the desired map area and clicking "Set Default View".



The IPAM aggregate map view may be enabled / disabled from the IPAM Configuration page.



Once enabled, a map pin will be visible on the IPAM Tab next to the search box that will show / hide the map.



Regions must be enabled, the region address field populated, and regions assigned to aggregates / blocks for the IPAM Map view to populate data. See Edit Regions for additional detail.


IM- 1906: IPAM Aggregate Utilization alert

Aggregate utilization alerts allows you to set up an email notification to send once an aggregate's available space hits a chosen percentage threshold.

An "IPAM Alerts" task has been added to the Scheduler's list of available tasks - this task must be created and set up to the desired alert schedule. See Scheduler Tab documentation for additional information on setting up scheduled tasks.


Once the Scheduled IPAM Alert Task has been created in the scheduler, alert criteria for individual aggregates may be set up from the IPAM Tab Action Menu.

To set the alert, from the IPAM tab, select the Action Menu (wrench icon) for an aggregate, and click on "Alerts".



This brings up the "Manage Alerts" dialog. Enter the email address for the alert recipient and the available space percentage at which the alert is triggered.

When done, hit "Save Alert". You may also cancel at any time.




To clear an existing alert, hit "Clear Alert", and the alert information will be removed and status saved.

IM- 1907: DNS Save and Push/Schedule


DNS Schedule Push allows a user with Admin permission to schedule a one-time zone push directly from the view zone page.

If you have Admin access, a "Schedule Push" button will be visible below the "Push Zone Now" Button.



To schedule a DNS Zone push, hit "Schedule Push".

Select the desired UTC time and fill in the notification email address. When done, click on "Schedule Push" again.




When done, you will see a notification that a push is scheduled. It will also show in the scheduled task list on the Admin Scheduler Tab.



You may edit or delete the scheduled push via the Scheduler, similarly to any other scheduled task.

IM- 1909: Resources - Native Document storage


The Document Storage Gadget allows you to upload documents to a resource, and have those documents accessible to download from the 6connect cloud to your local machine. It may be enabled on any Section type. For detailed information on using the Document Storage Gadget, see the Gadgets documentation. For information on how to add a Gadget to a Section, see Customizing Sections.




Upload Files

First, ensure the Document Storage gadget is enabled for the Section type. Then, select the "Uploader" tab under the Document Manager gadget.


Click on the "Choose Files" button, and select the file(s) you would like to upload.



The selected files will show in a list under the Uploader tab. To upload the file(s), click on either the "Upload" button adjacent to the file to upload the individual file, or the "Upload All" button to upload all files listed. You may also choose to remove files from the upload list, or cancel.




Once the progress bar is filled in, your upload is complete! Your files will show under the "Files" tab.



Download Available Files

Successfully uploaded files are listed under the "Files" tab of the Document Manager gadget. From here, you can see the file Name, Size, Type, Date, and available Actions.

To download a file to your local machine, ensure you are on the "Files" tab, then click on the "Download from Cloud" icon.



If a file is no longer needed, you may delete the file from the Document Manager by clicking on the Delete (trash can) icon.
Note: The uploader has a file size limit of 14 MB, files above this size will not successfully upload.

Bug Fixes

IM- 1860: Resolved an issue where viewzone history would not display
IM- 1902: Contacts no longer display notice data in the comments field while editing a contact
IM- 1911: The custom ID display on the resource entry page has returned after going AWOL
IM- 1912: The contact gadget no longer displays header rows when empty
IM- 1913: Resolved an issue with Auto-split template and Auto-split limits in IPAM Manage
IM- 1917: The Chart View type selector is now visible for limited permissions users
IM- 1919: The Section and Category selection boxes are now visible while editing a Resource Entry page for a limited permission user
IM- 1920: Contacts Tile View now respects the same permissions as list view

ProVision 5.1.1

ProVision 5.1.1 is a minor release with bug fixes

PHP Compatibility

⚠ Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes

IM- 1903: Resolved an issue where edits were unable to be made to the contact info gadget

IM- 1905: Resolved an issue where password updates failed

ProVision 5.0.0

ProVision 5.0.0 is a major release with multiple customer feature requests and significant new features

PHP Compatibility

Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

- ProVision 5.0.4
- ProVision 5.0.3
- ProVision 5.0.2
- ProVision 5.0.1

New Features

(CFR denotes customer requested)

Resource Importer


Click on the following links for more details on the Resource Import Tool, and a Resource Importer Walkthrough.

Updates include:

IM- 1466: Resource Importer opens in a new tab

IM- 1490: Improved ability to adjust column locations

IM- 1557: New on-screen guidance



IM- 1580: Opening a .csv searches the first 10 rows for a valid header

IM- 1581: Streamlined menu options

IM- 1582: Removed resource search

IM- 1589: Revised appearance of required data columns

IM- 1591: Added UTF-8 warning

IM- 1592: Updated 'Edit Row' interface and functionality

IM- 1609: Active tab highlights

IM- 1611: Row number column able to resize


IM- 1643: Mac .csv files now supported


Peering Manager

Click on the following links for more details on Common Tasks, Managing Peer Communications, and Managing Peer Sessions.

Updates include:

IM- 1593: New ability to set Peer Groups when adding a router and adding a peering session:





IM- 1552: New "Configure" menu option for one-click config of session on the router

IM- 1553: Sessions of type "Peer" are removed from the router when deleted in ProVision

IM- 1554: Peering importer differentiates between peer sessions matched to an exchange and unknown sessions

IM- 1556: Peering "Source IP Address" column changed to "Router"

IM- 1570: Import list of groups from router during session import

IM- 1574: Improved read-only peering permissions configurations

IM- 1594: Option to configure router when adding a peering session

IM- 1597: Multiple Peer Groups may be created when adding a router

IM- 1651: Improved Config Manager functionality

IM- 1653: Peering Import section added to Admin->Import

IM- 1654: Added Peer Group import button to session import

Peer Group Gadget

The new Peer Group Gadget allows you to add peer groups for IPv4 and IPv6 for a selected exchange from a router's Resource Entry page. Peer Groups added from this gadget will be available to select in the "Add Session" dialog box. For more details on the Peer Group Gadget, see Gadgets.


Note: Peer groups listed in the Gadget are for ProVision only and should reflect groups that exist on the router. Adding or deleting peer groups from the Gadget will not add or delete them on the router.



Additional Features

CFR-22: Smart Assign 'Exclude' tags

CFR-80: Smart Assign 'Strict Tag' and 'Standard' (match all) interpretation




CFR- 68: If IP or DNS are not assigned to a Resource, the Resource does not show up on the Dashboard

CFR- 90: Add "Allow subassignments" when editing multiple subnets in IPAM Manage


IM- 878: Removed Generate API Request

IM- 1363: TTL field added to DNS bulk records changes




IM- 1506: admin.php checks for a valid license key

IM- 1508: Indicator (blue arrow) on blocks in Resource Gadget and IPAM Manage when subassignments are enabled




IM- 1514: IPAM interface improved for updating/editing multiple block notes and tags. Select "Update Field" to apply change for all selected blocks.



Bug Fixes/Improvements


IM- 362: IPAM header tab highlighting, added dropdown menu



IM- 930: When marked peer "Not Qualified" or "Rejected, entry is no longer removed

IM- 983: Adding a new Section with blank name now provides error message

IM- 1000: Added "CRUD" legend under manager users



IM- 1061: Fixed navigation breadcrumbs

IM- 1165: Added 'logged in as' text to header

IM- 1096: Relabeled Secure64 entry in dropdown menu

IM- 1097: Updated Holding / Assignment wording on notifications

IM- 1273: configTest.php Deprecated

IM- 1282: Admin-api.php daemon user visible

IM- 1289: Treeview functionality restored

IM- 1325: Test zonesigner is working for DNSSEC

IM- 1470: Fixed error message in Admin Preferences


IM- 1480: Stop creation of "system" resources through the UI and API

IM- 1483: Moved EULA location

IM- 1504: Can no longer create API key for daemon user

IM- 1506: UpgradeUtil doesn't check for valid license key

IM- 1513: Included note on CSV import screens to encode with UTF-8 for best results



IM- 1519: Import directory structure updated

IM- 1526: Edit IPAM tags empty field save

IM- 1527: Resolved IPAM tags alphabetical sort

IM- 1528: Smart / Direct Assign buttons in IPAM gadget sent two requests when double-clicked

IM- 1530: Revised IPAM Gadget text display

IM- 1531: Delete aggregate button does not refresh page

IM- 1533: ConfigTest.php doesn't test for the writability of the web root

IM- 1536: IPAM gadget displays log information for IPv6 blocks

IM- 1537: Deleting a zone from the DNS Gadget removes it from the chart

IM- 1540: Edited gray text in text box for Direct Assign to be clearer for IPv6

IM- 1543: Removed LIR option from the section dropdown when creating an entry

IM- 1545: Add aggregate has "Available" as the default assignee

IM- 1549: Duplicate customer sample import link removed

IM- 1550: Import customer from salesforce link removed

IM- 1559: User activity report download .csv updated

IM- 1562: Admin up/down now works for Juniper routers

IM- 1565: Treeview top level folder renamed

IM- 1567: Additional countries available in drop down menu

IM- 1568: Block param without mask causes error for ipam-get API call

IM- 1575: Improved handling of a no permissions user on IPAM page

IM- 1583: Restricted creation/editing of LIRs through the Resource entries

IM- 1598: Improved handling of no permissions user on Sections page

IM- 1604: Updated handling of names containing apostrophes

IM- 1606: Improved 'Edit List: IPAM Tags' functionality and sorting

IM- 1613: Revised ARIN ORG handle to 'Org ID'

IM- 1620: Revised "Edited the file: regions" log message

IM- 1621: Added Custom ID field to Resource entry creation

IM- 1622: Revised the default Section and Category options when adding a Resource Entry

IM- 1624: Revised label location for 'Resource IP Assignment %' on Dashboard

IM- 1625: Revised user account count to disregard system user account

IM- 1626: API User drop down hides 'daemon' user

IM- 1627: Revised phrasing for Dashboard 'Resource IP Assignments' label

IM- 1631: Entry list page improvements

IM- 1632: Added custom ID to resources with duplicate names

IM- 1634: Changed "Type" To "Section" on Resource Entry page

IM- 1636: Improved handling of restricted permissions user on Resource Entry page

IM- 1637: Improved handling of restricted permissions user on Reporting page

IM- 1644: Improved handling of restricted permissions user on Sections page

IM- 1646: VLAN added to advanced options in IPAM gadget

IM- 1647: Revised display of Password field on routers in section field view

IM- 1652: Improved handling of restricted permissions user on Reporting page

ProVision 5.0.4

ProVision 5.0.4 is a minor release with bug fixes and improvements

PHP Compatibility

Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.


Contact 6connect at info@6connect.com to schedule a demo or get more information.

New Features


DNS Audit Tools (Alpha): ***SEEKING USER FEEDBACK***

Introducing a first version of DNS audit tools to perform a simple audit of both forward and reverse DNS. The tools set includes UI, API end points, and a command line interface. The audit results include the DNS as found in the 6connect ProVision database, the results from a resolver, and if there is a conflict in these two pieces of information. 6connect is seeking user feedback on this tool; contact us at support@6connect.com with your thoughts.


Access the UI version of the Tool by going to the desired block in IPAM Manage, click on the Action Menu (wrench), then select "DNS Audit (Alpha):



This takes you to the DNS Audit page.



From there, select the "Audit Forward DNS" or "Audit Reverse DNS" buttons to provide a list of IPs, the Reverse Values, Conflict Status, and Resolved Host(s).



DNS Audit Tools: Additional File and Example Information:

- ***UI:***
  audit_dns.php

  Example:
  https://cloud.6connect.com/myinstance/audit_dns.php?block=209.183.188.0/28

- ***API:***
  Files:
  api/v1/auditDNS/execute.php
  api/v1/auditDNS/getStatus.php

  Examples:
  api/v1/api.php?target=auditDNS&action=execute&type=forward&block=209.183.188/28&jobId=1424218758
  api/v1/api.php?target=auditDNS&action=execute&type=reverse&block=209.183.188/28&jobId=1424218758

- ***Command Line:***
  Files:
  tools/audit_foward_dns.php tools/audit_reverse_dns.php


  Examples:
  php audit_forward_dns.php -b 209.183.188/28
  php audit_reverse_dns.php -b 209.183.188/28

Juniper Logical Systems support for Peering:

ProVision now supports Juniper Logical Systems for Peering, with the Logical Systems information tied to the router resource. UI elements have been added as follows:

- A Logical Systems field appears in the the Peering "Add Router" dialog when a Juniper router is selected.

  To add Logical Systems to a router, go to the Peering Tab and click on the "Add Router" button. Select the Juniper router make /model, and the Logical System text field will appear. Enter the Logical System and router information, peer group information, and hit "Add Router" when complete. For routers with multiple associated Logical Systems, you may create duplicate router resources with different logical systems information.




Associating the router with a peer group is necessary to link the router to a particular exchange.


Please be sure to add the Peer Group information either in the "Add Router" dialog or in the Peer Group Gadget prior to adding sessions.

- Peering - Main - Add Session: Router drop down indicates the router, then Logical System info in parenthesis (e.g. "Juniper (test)") .


    After having added a Logical System to a router, that router + Logical System combination will be available to select in the Peering - Add Session dialog box. The Peer Group associated with that router / Logical System will automatically be selected. Continue to fill in your session information, then hit "Save".




When viewing your session in the Sessions list, your router will appear with the Logical Systems information in parenthesis.



- Peering - Main - Config Manager: When configuring a session that is part of an Logical System, the first line of the config displayed should be "set cli logical-system <name>"




- Peering - Import: When importing sessions from a Juniper router, the Router drop down indicates the router, then Logical System info in parenthesis (e.g. "Juniper (test)"). Also, there is now a Logical System column in the results.



Improvements

DNS UI Updates:

Various user interface improvements have been made to the DNS Admin section. Documentation has been updated to reflect these changes on the DNS Admin page.



Selected changes include:

- *"DNS Configuration" has been renamed "DNS Global Defaults", and is accessed from the "Global DNS Zone Defaults" link. The default options list has been simplified.*
- *"Nameserver Management" has been renamed "Default Nameservers", and is accessed from the "Global DNS Zone Defaults" link.*
- *"Bulk Zone Assignment" and "Bulk Record Changes" are now accessed from the "Bulk DNS Change Tools" link.*

CFR- 97: Tests/ directory are now excluded from local and hosted builds

Bug Fixes

IM- 1564: Treeview search fixed

IM- 1722: Fixed DynECT page display warning

IM- 1710: Improved integration with mysql

IM- 1742: Chart view now respects permissions

IM- 1770: Default nameservers can now be removed

IM- 1771: Resolved issue where DNS was missing pointer generation for valid PTR records

IM- 1772: Generating API key no longer displays array bounds error

IM- 1774: Resolved an issue in IP Import preventing row edits after defining columns

IM- 1781: Update DNS links appear below hostname field for applicable resources with an assigned /32 block



ProVision 5.0.3

ProVision 5.0.3 is a minor release with bug fixes and improvements

PHP Compatibility

Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Improvements


Peering VRF:

VRF for Peering now supported for Cisco routers.

Enabling "VRF Support" in the Admin home page under "Peering Settings" will automatically add the VRF gadget to the router Section.



The VRF gadget, available on a router's Resource Entry page, allows you to add VRFs and ASN to a router



Once VRFs are set up for a router, the source ASNs for the associated VRFs will appear in the Source ASN dropdown when adding or editing a session for that router.
Currently only supports Cisco routers.

Bug Fixes

IM- 1758: Block without VLAN now returns a "No VLAN found" message from a getVlan API call
IM- 1764: Updated IPAM API "Get" call so that the search parameter supports tag filtering
IM- 1768: Resolved an issue where users without IPAM-update permission were able to edit multiple blocks

ProVision 5.0.2

ProVision 5.0.2 is a minor release with new features, bug fixes, and improvements

PHP Compatibility

⚠ Please note that ProVision 5.x requires php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes/Improvements


IM- 1706: API Direct Assign Tagging. See: API Module- IPAM DirectAssign

IM- 1705: API endpoint that will return utilization (assigned / available) across all aggregates based on a specific tag. See: API Module - IPAM GetHostUtilization

IM- 423: Improved logging for IPAM reporting actions


IM- 1252: Improved resource logging

Clicking on a resource log will provide additional log attributes (if available) and a link back to the Resource Entry page, API logs will display API detail:




IM- 1388: configTest improvements

IM- 1619: Additional information provided in logging: Log messages are more descriptive



IM- 1666: Expanded chart viewing width capabilities

Chart view now has an optional "Width" parameter, as well as a "Load More" button to continue viewing additional through the full tree width.



IM- 1675: Added API endpoint to do a recursive delete of resources (Parameter: &recursive=1). See: API Module - Resource delete

IM- 1688: Fixed password loading issue in Connection Configuration of the DHCP Gadget

IM- 1689: Resolved error in DHCP gadget after removing free line entries

IM- 1691: Resolved DHCP gadget duplicate error messages

IM- 1711: Blocks without parents can now be updated

IM- 1714: Resolved an issue with individual block assigning after a multi-assign

IM- 1716: Read only / Limited Permissions users can no longer add blocks via API

IM- 1717: Read only users can now access IPAM Manage dialog

IM- 1718: Read only users can no longer aggregate blocks in IPAM manage

IM- 1721: Resolved issues in 'IP Import- Import from .csv' with the "Generic Code" and "Allow Subassignments" fields.

IM- 1723: IPAM Gadget filter no longer duplicates mask entries in the filter drop down

ProVision 5.0.1

ProVision 5.0.1 is a minor release with bug fixes and improvements

PHP Compatibility

⚠ Please note that ProVision 5.x will require php 5.5.+. For local installations, please upgrade php prior to installing the upgrade. Also ensure that the correct Sourceguardian php extension is loaded for the new version of php.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

Bug Fixes/Improvements

IM- 1645: API attr_key multiple attributes filter and hyphen conditions

IM- 1659: Assignment date for IPAM reporting is not inclusive

IM- 1660: Add Session dialog not pre-selecting exchange

IM- 1661: Peering - exception thrown for invalid exchange prefix

IM- 1662: Install - configBootstrap requires valid email for version list

IM- 1663: Install - configTest add mod_deflate check and update version

IM- 1665: Subassignment indicator shows up on /32s (ipv4)

IM- 1678: Install - Fix install process with the secure directory

IM- 1679: Prevent deleting Resources which have children

IM- 1680: Updated "Getting Started" Link on Dashboard

IM- 1694: Updated default DNS sec resolver

IM- 1695: Session list doesn't refresh after clicking Update Session State

IM- 1696: Logging - Remote log attempting to log without host or ip

ProVision 4.2.0

The 4.2.0 release is a minor release that packs in some big updates and customer feature requests.

Contact 6connect at info@6connect.com to schedule a demo or get more information.

- ProVision 4.2.1

New Features

Peering Revamp

Peering

DHCP Integration into Resources

DHCP Tab

Bug Fixes

IM-1505 - IPAM Manage - Resource Filter improvements

IM-606 - Zone import optimizations for larger data sets

ProVision 4.2.1


ProVision 4.2.1 is a minor release with some customer feature requests.

Contact 6connect at info@6connect.com to schedule a demo or get more information. Documentation (PDF version) - Previous Documentation Versions

New Features


(CFR denotes customer requested)

CFR-86: Add "enable sub assignments" to IPAM gadget "edit" functions




CFR-71: Require CRUD permissions for a user to delete DNS server -> zone links

IM-1261: Pagination for IPAM aggregates






IM-1496: DNS - Add zone UI revamp



IM-1184/IM-554: Option to allow imported zones to automatically add target server



IM-1413: Reporting for IPAM, improve aggregate selection dropdown so it doesn't conflict with the IP Type checkboxes

Bug Fixes

IM-1500: Remove old remaining dns files from code base

IM-1154: Relabel "Transfer Type: SCP" to "ISC BIND"

IM-1126: Improved UTF-8 support for data imports

IM-944: Restructure Import Classes for more flexible data import formats

IM-323: logAction updates for global logging

IM-320: Cleanup of .txt file references/dependencies

ProVision 4.1.0

The 4.1.0 release is a minor release that packs in some big updates and customer feature requests.


Contact 6connect at info@6connect.com to schedule a demo or get more information.

- ProVision 4.1.23
- ProVision 4.1.22
- ProVision 4.1.21
- ProVision 4.1.20
- ProVision 4.1.19
- ProVision 4.1.18
- ProVision 4.1.17
- ProVision 4.1.16
- ProVision 4.1.15
- ProVision 4.1.14
- ProVision 4.1.13
- ProVision 4.1.12
- ProVision 4.1.11
- ProVision 4.1.10
- ProVision 4.1.9
- ProVision 4.1.8
- ProVision 4.1.7
- ProVision 4.1.6
- ProVision 4.1.5
- ProVision 4.1.4
- ProVision 4.1.3
- ProVision 4.1.2
- ProVision 4.1.1

New Features


Dashboard Redesign

The main dashboard is completely redesigned with pie and bar graphs for a variety of IPAM, DNS, and resource data.




IP Detail View Options

View your IP aggregates in the way you want to view them. Set filters for each aggregate based on Mask, LIR, ASN, Tags, Region, Code, VLAN, or Resource Assignment.



PowerDNS - MySQL Support

Full support for the MySQL PowerDNS backend. Zone updates are pushed out in easy SQL updates to the target server.



PowerDNS MySQL Importer

Just enter the target server information, click import, and watch all your zone data populate the 6connect database.



Global Tag Update/Delete Functionality


Update and delete tags globally from the primary tags list, just as nature intended.

DNS Audit Tools (Beta)

View both forward and reverse DNS for entire /24 to get a clear view for how the block is used. Audit against public DNS to see if records are mis-matched or out of sync.

CLI (Alpha)


Hate clicking and have a general disdain for UI? This feature is for you! Just press ctrl+shift+s to try 6connect on the CLI with simple commands for quick no-frills interaction.



Feature Improvements

Resource UI Functionality

Easier navigation and button placement, alphabetical browse, data usage charts and more!




Header Redesign

The header and menu bars have been streamlined to take up less space, and present menu/options in a clean format.


Option Menu Redesign

Say goodbye to icons. All option menus have been switched to simple text drop down for easier and more intuitive interaction.



IP Import Option Additions

You can now import all data relevant to an IP including Resource Holder ID, Resource ID, Org ID, Net Handle, Customer Handle, Generic Code, ASN, Allow Sub-Assignments, and of course all the basic information.



Bug Fixes

IM-919 - IPAM menu UI issues in IE9

IM-1054 - DNS Add Zone allowing spaces in domain name

IM-1057 - DNS edit - hitting enter key to save record creates strange pop up in Safari

IM-1119 - Odd session behavior on API calls

IM-1162 - Read Only user can edit IPAM blocks from IPAM gadget

IM-1163 - Read Only user can't see time machine data from IPAM gadget


ProVision 4.1.23

Bug Fixes

IM-1494 - IPAM - Incorrect SWIP parameters sent from IPAM gadget

ProVision 4.1.22

Bug Fixes/Feature Updates
IM-1493 - IPAM - Invalid LIR ID or entity handle error message when performing SWIP action
IM-1124 - DNS - PTR autogenerate - UPDATE



ProVision 4.1.21

Improvements

Call Subnet Scans via the API

Subnet scan can now be issued and retrieved via the API. Examples of the two commands and links to documentation are listed below:

/api/v1/api.php?target=ipam&action=scanBlock&block=<cidr>

/api/v1/api.php?target=ipam&action=getScanResults&block=<cidr>


API Module - IPAM

Call Swip Functions via the API

API Module - IPAM

Delete Functionality for All Blocks

Aggregates can now be deleted regardless of state of sub-blocks. An aggregate can be deleted even if sub-blocks or hosts are assigned to resources.




IPAM Aggregate Statistics

All IPAM aggregates now display statistics on how they are assigned to resource on the main IPAM screen.



Resource Field Management

A new easy to read display of field usage statistics for usage of specific resource field names, as well as usage of field types, and a list of all available fields for improved resource field management.



Bug Fixes

CFR-87 - IPAM - Consistently display Region name across IPAM management and gadgets
IM-1467 - Resource - Unable to enter Canadian Provinces
IM-1476 - IPAM - Smart Assign generic code parameter being ignored
IM-1477 - IPAM - Remove ability to dis-allow sub-assignments on blocks with children
IM-1482 - Resource - Can't edit fields in Section in Chrome/Safari
IM-1484 - Resource - Fix verbiage around Types and Sections, change all to Sections
IM-1486 - Resource - Remove system TLR field from breadcrumb display

ProVision 4.1.20

Bug Fixes

IM-1463 - DNS - Create zones drop down pulling incorrect resource list (DHCP)

IM-1449 - IPAM - Add loading/waiting indicator when waiting for swip/allocate transaction


IM-1332 - Import - File type issues, can't import files that are not Windows csv

ProVision 4.1.19

Beta Features


Resource Importer

A new stand alone application to import complex resource sets. Give it a test run! Go to Admin -> Data Import and click on the Link for "Resource Import Tool Beta". As always, please send feedback to support@6connect.com.





DHCP Management


New DHCP Tab - See all your DHCP server entries in a single place. The usual search functions work as well.




DHCP Management (Now with more Resources!) - We have integrated DHCP functions into a "Gadget". This means you can assign DHCP functionality to a Server of your choice and manage it just like any other resource in ProVision.









Improvements


Automatic Upgrades

You can now upgrade locally installed ProVision instances via the GUI, API, or command line. The product will automatically check if any new updates are available, fetch and install them. Note that you can only use this feature from 4.1.18 forward. If you are on an older version, please contact support@6connect.com to assist you.

GUI - Just click on Admin. Information will be at the top of general admin page.

API documentation: http://docs.6connect.com/display/DOC/API+Module+-+Upgrade

Command line: <6connect web root>/upgrade/upgrade.php (-h for help)



ARIN Swip Error Messages

ARIN swip error messages now show the full detail of the error in the GUI.

Bug Fixes

IM-1453 - Resources - Unable to remove existing fields from field collection

IM-1454 - IPAM - IPv6 radio button typo

IM-1459 - IPAM - Manage screen does not auto scroll/highlight block after edit

ProVision 4.1.18

Beta Features

Resource Importer

A new stand alone application to import complex resource sets. Give it a test run!

Improvements

Resource Importer - Add default name server columns to import

Resource - Add count of zone to Customer section display

Bug Fixes

IM-1277 - Dashboard - Resource zone assignments display even with no data

IM-1291 - Resource - Ability to move system resources via Resource Chart View

IM-1292 - Resource - Ability to move TLR anywhere in tree - subsequent crash

IM-1328 - Admin - Radius dictionary and LDAP schema links broken

IM-1442 - Resource - Redirect non-existant categories to uncategorized category

IM-1446 - IPAM - Add Swip error message to error displayed in UI on failure

ProVision 4.1.17

Beta Features


Resource Importer

A new stand alone application to import complex resource sets. Screen shots TBA.

Improvements

PowerDNS Server Connection Test

Test and diagnose connectivity issues to a PowerDNS server.



Bug Fixes

IM-1411 - DNS - Add "Test Config" option for PowerDNS servers in DNS Admin

IM-1430 - IPAM - Direct assign using block parameter throws error


IM-1431 - Setup - configBootstrap allows an empty registration email

ProVision 4.1.16

New Features

IPAM - Multi-assign

Assign multiple IP addresses to a resource via a single API call, or just a few clicks in the user interface! When multiple IP addresses are selected in the UI, a new tab to assign all at once will appear.



Bug Fixes

IM-1418 - IPAM - De-Swip estimated time too high

IM-1426 -IPAM - Filters resetting to default settings after multiple edits

IM-1427 - Resource - Chart view fatal error

IM-1428 - IPAM - Swip timer counting negative

ProVision 4.1.15

The 4.1.15 release is a bug fix release that contains a few feature improvements.

Feature Improvements

CFR-76 - Add Configuration setting for submitting changes to RIPE test v. live database

IM-140 (part) - Password management improvements - stored passwords are now stored outside of primary database structure.

Bug Fixes

IM-1395 - DNS - Assign DNS zone drop down displaying incorrect information

IM-1396 - IPAM - SWIP check mark displayed when IP is only assigned

IM-1421 - IPAM - Smart assign producing two log messages (should be one)

IM-1423 - API - Hashed API requests fail if first character of key is 0

IM-1424 - IPAM - Scan loading indicator never goes away

ProVision 4.1.14

New Features

Rebuild Permissions CLI Tool (IM-1405)

Command line tool to rebuild the user group permissions for a specific group or resource, or group/resource combination.

Bug Fixes

IM-1404 - User Admin - Group Management page error 'Circular Reference


IM-1403 - Dashboard - Warnings on dashboard when user has no IPAM permissions
IM-1402 - Reporting - IPAM reporting assigned numbers still incorrect
IM-1401 - DNS - Text update for Delete and Push confirmation window
IM-1400 - DNS - Default servers not added to zones as expected
IM-1399 - IPAM API - IPAM get call ignoring valid tags
IM-1392 - DNS - Action menu disappears when using filter function
IM-1390 - Admin DNS - Push to Secure64 errors (short timeout)

ProVision 4.1.13

New Features

Add User CLI (IM-1387)

Local installs can now add a user from the CLI with the add-user tool found in the ./tools directory.



Updates

IM-1385 - IPAM - RIPE API updates/invalid RIPE API URIs

IM-1382 - Remove edit/delete options from ipam tags list, options no longer needed

Bug Fixes

IM-1389 - Reporting - Utilization numbers incorrect for IPAM reporting

IM-1386 - IPAM API - Direct Assign - resourceHolderId parameter not working as expected

IM-1383 - Session timeout logs do not set username

IM-1375 - DNS - Delete and Push options shows in action menu when user does not have Delete permissions

IM-1374 - Resource - Unable to save resources on edit (javascript error)

IM-1359 - Dashboard - IPAM/DNS graphs inaccurate for some users, counting data out of permissions scope

IM-1041 - IPAM Admin - Edit Contact Roles link depreciated, should be removed

ProVision 4.1.12

Bug Fixes

The 4.1.12 release is bug fix only release.

IM-1372 - Search - Search box breaks on Admin navigation when large custom header image set

IM-1371 - Dashboard - Reverse DNS resource appearing on dashboard stats

IM-1369 - DNS - Large DNS pushes appear to be hanging

IM-1368, IM-1343 - Reporting - CSV and HTML column headers do not match values

IM-1366 - DNS - Menus not appearing on pages after 1

IM-1361 - DNS - Admin DNS "Edit DNS Records" links to nonexistent page (404 error)

IM-1360 - IPAM - Admin IPAM "Process Holding Tank" Back to IPAM links to nonexistent page (404 error)

IM-1358 - DNS Import - Can't edit resource assignment during import

IM-1357 - DNS Import - Hanging on single zone import

IM-1355 - IPAM - Aggregate details log menu not pulling log entries

IM-1354 - Reporting - Error on user reporting

IM-1352 - Reporting - All users showing in user list when permissions should restrict

IM-1335 - IPAM Import - Data not revalidated after editing import row

IM-1305 - DNS - Download of all zip files permissions issue

IM-1301 - Resource - Customer field type box disappearing on add

IM-1296 - Admin - Create backup now option updates general settings

IM-1224 - Admin - API request generator slow to load

IM-1223 - IPAM - LIR manager not saving Org info


IM-1039 - Resource - ZIP/Postal code field missing in edit dialog

ProVision 4.1.11

New Features

DNS Deletion Queue

Addition of a deletion queue for zones for flexible removal of zones from DNS Servers.



Bug Fixes

IM-1344 to IM-1351 - All bug fixes related to a bad version of bootstrap.

ProVision 4.1.10

Bug Fixes

IM-1290 - Resource: list view does not have default when Resource link clicked - defaults to empty list.

IM-1320 - Resource: allowed to become it's own parent.

IM-1327 - Dashboard: displaying information for resources above current sign in permission level.

IM-1331 - Import : progress bar flashes/drops to 0 at times while upload in progress.

IM-1334 - Import: new resources not adding correctly from IP import.

IM-1337 - API: Valid requests are being rejected.


IM-1338 - License check interval too long

ProVision 4.1.9

The 4.1.9 release is a bug fix release that contains a few new feature improvements.

Feature Improvements

IM-1258 - Add separate name field to DNS servers, so there is both an FQDN and name. There are now a separate fields for a server Nick Name and it's FQDN/IP. Now DNS servers can be easily recognized by their common/nick name or their FQDN/IP address, as both are displayed representing the server.



IM-1329 - Add field override for Net Name on swip.

IM-1312 - Add override field for Customer Name on swip

Both the ARIN Customer Name and Net Name can be over ridden from the automatically generated defaults at swip time using the fields provided on the RIR Integration Panel.



Bug Fixes

IM-1330 - API - IPAM get parameter block not working as expected

IM-1324 - Missing images on admin-dhcp.php

IM-1323 - API - Inconsistent results between Resource Get and Resource Add

IM-1322 - IPAM Gadget - Action menu display issue sub assignments allowed

IM-1321 - IPAM Gadget - All tags should display during edit, not just in use

IM-1319 - IPAM Admin - Bad URL "Back to IPAM Admin" in tag editor

IM-1259 - configTest - Add test items for expect, namp, and php hash extension


IM-1142 - Center command results given by assistant

ProVision 4.1.8

The 4.1.8 release is a bug fix release that contains a new feature improvement.

Feature Improvements

IM-1255 - User customizable header and support links. Under Admin->Application Settings, you can now set your own custom header image (note the image size), as well as email and phone number to contact for support.



Bug Fixes

IM-1317 - IPAM Gadget - Region dropdown is blank when editing

IM-1313 - $GENERATE on DNS not producing appropriate PTRs

IM-1310 - Admin-Users - Check User Permissions field no longer working

IM-1306 - Unable to add maintainers to new LIRs

IM-1302 - Can't Smart Assign when using the LIR parameter

IM-1237 - Admin->API page loading very slow even with no data

IM-1229 - RIR Integration missing link to LIR Manager if no LIRs exist

IM-1182 - API - fix request generator to updated resource parameters

IM-1121 - Logging message missing data for outbound contact email

ProVision 4.1.7

The 4.1.7 release is a bug fix release that contains a few feature improvements.

Feature Improvements

IM-1300 - Add all RIRs to LIR manager - All RIR's are now standardized as 1918, ARIN, RIPE, LacNIC, APNIC, and AfriNIC). All customer RIR's should be moved to LIRs and the next update will provide automatic migration.

IM-1218 - Move Resource Holder ID to fundamental attributes for type Resource Holder - The Resource Holder ID is now the Customer ID under the fundamental resource properties.

IM-1268 - Handle multiple ORGs per LIR for ARIN - Added the ability to handle multiple ORGs per LIR for the ARIN RIR.

IM-1156 - Link Resources on Dashboard to Resource records.

IM-1269 - Move DNS and IPAM admin sections to their correct locations - IPAM and DNS admin options are now under the IPAM Admin and DNS Admin sections.

Bug Fixes

IM-1166 - Sorting functions inconsistent on zone list

IM-1195 - Remove old help URLs from admin

IM-1225 - Zone import giving incorrect error when conf file omitted

IM-1249 - Available/Reverse/Holding resources should be protected

IM-1251 - DNS server add by default behavior is not correct

IM-1271 - Field mis-alignment on IPAM gadget

IM-1275 - EULA has escaped quotes

IM-1298 - Default SOA for zones being used when over ridden

IM-1299 - IP Import not working for Radius/LDAP users

ProVision 4.1.6

The 4.1.6 is bug fix release only.

Bug Fixes

IM-990 - ResourceQuery returning incorrect results from empty arrays

IM-1060 - Edit DNS zone missing mouse over text

IM-1155 - IPAM Manage Email function does nothing

IM-1199 - DNS Import Error

IM-1202 - IPAM utilization incorrect or unsplit aggregates

IM-1213 - FireFox on Windows - Admin text areas too wide

IM-1220 - IPAM edit multiple not working as expected

IM-1221 - IPAM manage loading gif not going away

IM-1226 - DNS import does not correctly handle multi-line zone declarations

IM-1228 - Warning on dashboard when no data present

IM-1232 - IP assigned totals incorrect on dashboard

IM-1233 - File swipNetBlock spelled incorrectly - problems on case sensitive systems

IM-1235 - SQL templates contain log data

IM-1238 - SQL template contains 6connect default SOA, should be generic

IM-1241 - SQL template should have more generic default IP list

IM-1242 - SQL template contains /67 in default v4 masks

IM-1243 - SQL template contains bad assortment of defualt v6 masks

IM-1244 - IPAM admin contains lists for v4/v6 exact matches - no longer used

IM-1245 - SQL template default LIR should contain more generic data

IM-1246 - Process holding tank completed text should contain resource name, not number

IM-1250 - IPAM delete throwing error, instead of returning error on bad delete action

ProVision 4.1.5

The 4.1.5 is bug fix release only.

Bug Fixes

IM-1187 - Reporting Resource count incorrect

IM-1194 - Javascript errors on dashboard (text not properly escaped)

IM-1211 - Update EULA

IM-1212 - Update text on Welcome

IM-1215 - Assigned IP count on dashboard inaccurate

IM-1216 - IPAM - can aggregate assigned block

IM-1217 - IPAM - Sub-assigning block to same resource results in being unable to reclaim block and other weirdness

IM-1222 - Move HOSTED_COMPANY define from constants to globals

ProVision 4.1.4

The 4.1.4 is bug fix release only.

Bug Fixes

IM-1270 - Fix table name in 4.1.0 upgrade script

ProVision 4.1.3

The 4.1.3 is bug fix release only.

Bug Fixes

IM-1159 - Can't generate Resource report .csv download

IM-1170 - Update copyright text

IM-1183 - Memory allocation exhaustion on large PowerDNS import

IM-1197 - IPAM view aggregate tree not restricting to top block

IM-1201 - IPAM gadget not displaying addresses

IM-1204 - Javascript error when splitting blocks

IM-1205 - IPAM Gadget browse assign does not have correct IP type set

IM-1207 - IPAM Gadget RIR integration broken

ProVision 4.1.2

The 4.1.2 release is a bug fix release only.

Bug Fixes

IM-1196 - Error on IP Imports (php 5.4 and up)

ProVision 4.1.1

The 4.1.1 is bug fix release only.

Bug Fixes

IM-1193 - Path to zones incorrect in 6connect conf file

ProVision 4.0.0

The 4.0.0 release is a major release that contains many new features and improvements. The improvements include: a complete revamp of the Resource (Asset) system, an LIR/RIR management system to manage multiple ASNs and RIR credential sets, a new permissions structure with user groups and Resource based access, global search auto-complete, and an improved GUI setup (available since 3.9.3).

New Features

RIR/LIR Manager

If you have multiple ASNs, LIRs, or RPSL Maintainer Objects to manage - this is the feature for you. You can now enter an unlimited amount of ARIN or RIPE credentials and select which set of credentials to use when updating an IP block. Additional detailed error reporting has been added to provide specific information in the event of an update failure.

The credentials for all LIR's under a particular RIR are displayed when the RIR Integration icon is clicked, allowing quick and easy switches of blocks between different organizations or maintainers.

Permissions

Control and set access to your IP data, DNS, and Resources exactly how you want it. Full CRUD permissions for each section of ProVision can now be controlled on per Resource basis through user groups. Previously, permissions were based on sections of the tool: IPAM, DNS, Peering, Resources, etc. and applied globally. Permissions for each section are now attached to individual Resources. Additionally, user groups have been added to simplify permission assignment. Full CRUD permissions for each section of ProVision can now be controlled on per Resource basis through user groups.

The new permission structure has completely replaced the Customer Portal functionality in versions pervious to 4.0.0. Customer Portal users will be migrated to standard directory of users that have permissions only on their specific customer resource.

Note: The Radius and LDAP integrations have changed signifigantly with the addition of user groups. The configurations for 3.9.3 and prior will NOT work with 4.0.
For more information, see the documentation: http://docs.6connect.com/display/DOC/Manage+Users

Global Search Auto-complete

Find what you are looking for quicker and easier. Global search will now provide a drop down of auto-complete answers, and the section that contains the relevant results.

Resource (Asset) System

ProVision has a new ultra flexible asset management system that looks good while doing it. The Resource system has a smoother look and feel with pagination, search, and quicker, more detailed methods for creating custom fields and data types. Both Catagories and types have been added to help better organize Resources.

And if you are a fan of pretty things, there is a new graphical Resource view that displays the hierarchical layout of Resources, and allows for drag /drop to reorganize Resources.

Documentation

We have moved to a new and improved documentation system at: http://docs.6connect.com/. Help documents are now fully indexed and searchable. Video tutorials are being added soon!

Improvements

No more changing text configuration files! 4.0.0 now has a GUI setup wizard to check the system configuration for errors, and load the configuration files and database from a few simple fields.

Minor Improvements

IPAM - generic code field added to API Smart Assign call. (CFR-44)
Authentication - set default login type via constant. (CFR-43)
Reporting - Add reporting functionality on Top Level IP Aggregates. (CFR-42)
DNS - List zones alphabetically, and then numerically by IP octet/nibble.

Bug Fixes

IM-812 - Confirming the Org ID of IANA on welcome page produces blank screen.
IM-922 - Successful Radius login rejected.
IM-455 - Do not allow duplicate zone creation.
IM-833 - Fix to save record on Zone View when hitting enter key.
IM-937 - Fix to close record using view icon on Zone View.
IM-941 - Fix for global search timeouts.
IM-940 - Updated import CSV header type checking to accommodate .csv files generated from a variety of different sources.

Minor Release 4.0.1

IM-1079 - IPs in Holding can be assigned via Browse Assign.

IM-1088 - Daemon user visible in accounts section.

Minor Release 4.0.2

IM-1099 - IPs in Holding can't be manually over ride reclaimed.

IM-1100 - Latest import code not checked into 4.0.0 branch.

Minor Release 4.0.3

IM-1102 - Contact info gadget information does not save on first click.

IM-1101 - IP block scan Found hosts number does not refresh on completion.

Minor Release 4.0.4

IM-1119 - Odd session behavior/results with api calls.

Minor Release 4.0.5

IM-1120 - Generate forward/reverse DNS for resources not working.

IM-1125 - Session Bug - User timeout/logout allows API request as user with no permissions

IM-1131 - Warning in search.php line 92

IM-1132 - Customer import from .csv field count issue

Minor Release 4.0.6

Maintenance release - Peering code integration

Minor Release 4.0.7

IM-1136 - ContactInfo gadget reading and saving incorrect field name for phone and fax

ProVision 3.9.0

Released March 2013

Network Discovery Scanlet (v1)

- IPv4 scanning agent for network discovery
- Discovers and imports IP, Ports and MAC Address as devices

ProVision - IPAM

- IP Sub-assignments
- IP Templates

ProVision - DNS

- DNS Views (Split Horizon Support): Includes ACL manager!
- Improved DNS Master/Slave support
- Secure64 DNS Integration (update)

ProVision - Assets

- Browse, Direct, and Smart Assign added to Assets
- Asset UI cleanup (multiple)

ProVision - Platform

- Logging fixed when entering duplicate blocks
- Propel ORM removal

ProVision 3.9.3

Overview

The 3.9.3 minor release provides a few new DNS features.

New Features

Per Server DNS View Support

Enable, disable, and manage views on a server level. This enables every server to have it's own unique combination of views implemented, or none at all.

Secure64 DNS View Support

Support for views with the Secure64 DNS system.

Bug Fixes

None.

ProVision 3.9.2

Overview

The 3.9.2 minor release provides a few new DNS features, additions to the API request generator, minor IPAM changes, and minor bug fixes.

New Features

Secure64 DNS Integration

Secure64 Master/Slave integration and DNSSEC integration.

API Request Generator - DNS Utilities

DNS Zones, DNS Records, DNS Servers, Server-Zone Linkage, and Name Server API sections have been added to the API request generator.

Changes and Updates

SWIP Information Display

When a block is swipped, it is now indicated by a green check mark next to the RIR name on the IP manage screen. Hovering over this check reveals the swip details.

Bug Fixes

Fix for IM-807 - Missing email address and exchange information on some peering request forms.
Fix for IM-808 - Scan results not displaying on IPAM manage screen.
Fix for IM-809 - Setting incorrect path for imports temp directory on local installs.

ProVision 3.9.1

Overview

The 3.9.1 minor release provides a few new IPAM features and improved data visualization. It also contains some changes and improvements DNS Master/Slave relationships, and the file structure created on BIND servers during file push.

New Features

IPAM Bulk Edit

There are now checkboxes by each IP block on the IP block management screen. When you select more than one check box, the option to edit multiple blocks appears at the top left of the IP list. Clicking "Edit selected blocks" will bring up the standard edit menu and all selected blocks will be updated to the properties chosen.

IPAM Export to .csv

The "Export Current List to .csv link is located at the upper right of the Manage list. When clicked it exports all blocks displayed on the screen to a .csv file. You can export select sub-sets of blocks simply by filtering or searching the list.

DNS Master/Slave Relationships

One the zone edit page, there is now the ability to push a zone out to a server as a master or a slave to accommodate complex and mixed master /slave environments.

Bulk Zone Server Assignments

On the DNS Admin tab, the second second provides the ability to search for zones, then perform a bulk assignment of those zones to a specific server.

IP Assignments - Hierarchical View

On the IPAM manage screen, blocks that allow sub-assignments, and have at least one sub-assigned block become a link that expands to show a hierarchical listing of space within the block and what resources the space is assigned to.

Changes and Updates

BIND Directory Structure

The directory structure for BIND has been changed so that all zone files now go into a sub folder under ./6connectGeneric that is the first character of the zone files name, either 0-9 or a-z.

RIPE IP Look-up

IP based look-up on the welcome screen for RIPE blocks is now using an improved reverse lookup on mnt-ref and displays all discovered organizations associated with an IP, allowing the user to identify the correct organization.

Bug Fixes

Fix for missing time zone, state, and country information in the admin section and customer address section. This would have only impacted new turn ups between 3/14/2013 and present.

ProVision 3.8.0

Launched in December 2012

ProVision - IPAM

- IP Import Wizard
- IP Templates/Splitting

ProVision - DNS

- Updated Zone Editor
- Zone History and Versioning (with rollback)

ProVision - Assets

- Migration to more flexible container structure

ProVision 3.7.0

Launched in September 2012

ProVision - IPAM

- Multiple UI updates, including new "Aggregate" view

ProVision - DNS

- PowerDNS support (v1)
- Zone editor refresh
- Zonelist page UI update
- Selective zone push (single zone, bulk push, etc.)
- Multiple DNS Server Support
- RFC based zone validation

ProVision - Assets

- Complete refresh, unlimited Asset Types and Custom Fields

Network Automation - Peering

- Complete UI refresh of Communication Manager and Session Manager

ProVision - Platform

- LDAP Support
- Revamped Tree View with real-time search

ProVision 3.6.0

Launched in August 2012

DNS

- Asynchronous zone push

DHCP

- ISC dhcpd support
- Support for common DHCP features
- DHCP configuration pushes and execution of custom commands
- Support for custom DHCP configurations

Portal

- Integrated UI updates from Resource Holder page

Platform

- Revamped Resource Holder page
- Updated Smart Assign function
- Multiple data visualization updates

ProVision 3.5.0

Launched in June 2012

API

- IP block history lookup
- Support for lookup by Custom field

IPAM

- tag editor refresh
- ARIN Reallocation support (via REST)
- RIPE block lookup for aggregate importing (welcome screen only)

DNS

- Zone template editor/builder
- Zone editor refresh
- Zone importer refresh
- DNS Admin UI updates including pre/post commands per server
- DynECT integration (v1) for Dyn.com DNS customers

Platform

- Customer/Delegate Portal - version 1 (includes permissions for IPAM/DNS functions)
- Real-time streaming syslog function (incl JSON support)
- Admin Tab UI updates (multiple)
- Reporting option (filter by Tag, Custom Field, Region, etc.)
- Timeserver refresh

ProVision 3.4.0

Launched in April 2012

API

- DNS functionality now accessible
- Log functionality
- php SDK v1

IPAM

- IPv6 Direct Assign Refresh
- Prep for UI refresh

DNS

- Multi-server support for zone export/push
- DNS Admin UI refresh

Platform

- Authentication revamp (login, logging, etc.)
- Sitelist UI update
- Paging UI update
- Salesforce integration (version 1)
- Prep for RIR/LIR support

ProVision 3.3.0

Launched in March 2012

API

- IPAM functionality vis RESTful web service (including SWIP)
- Add/Remove Assignee (all fields)
- Add/Remove Assignee contacts (all fields)

IPAM

- View/Edit Devices from detail screen
- SWIP data lookup (ARIN only)

DNS

- SCP support for zone exports
- Secure64 Integration (version 1)

Peering

- Support for multiple locations within an Exchange

Platform

- Dashboard refresh
- Reporting Tab refresh
- Automated IP Import wizard
- Enhanced RADIUS VSA support
- RESTful API integration (application side)
- Multiple navigation updates (tab/subtab)
- FreeBSD Virtual Appliance released

ProVision 3.2.0

Launched in February 2012

IPAM

- RPI RPSL API integration
- SWIP as "private" for ARIN region
- Parent/Child relationships for Sites (multiple levels permitted)
- Revamped Site Editing screen
- Multiple Tag support for assignments
- Filter by NetMask option

DNS

- Zone editor enhancements (multiple)
- Bulk DNS zone editor
- DNS Zone download (ZIP format)
- DNS zone file incrementer
- DNS Zone file pre-population

Peering

- Integrated Communication Manager unto UI

Asset and Device Tracking

- Rack level diagramming from Asset data
- Device tracking (IP, hostname, MAC address, VLAN, etc.)
- Generate DNS records from Device data

Platform

- Revamped global search interface
- Assistant (integrated network tools and search)
- Additional Filtering enhancements for views
- Additional Header sorting enhancements
- Double byte support
- User Management enhancements
- Integrated documentation (HTML/PDF)
- Revamped "tree view" functionality
- Granular logging with filtering and highlighting
- New "Reporting" Tab for statistics, data export and RIR reporting

ProVision 3.0.0

Launched in Fall 2011

IPAM

- ARIN API integration
- Enhanced block search functionality
- v4 network host scanning

DNS

- Zone searching and filtering enhancements
- Note storage and search per zone record entry

Asset and Device Tracking

- Create/Delete and Modify Assets (beta)

Platform

- Time Machine functionality for Zones, IP blocks and User Actions
- Local authentication engine
- Enhanced Global search functionality
- Enhanced Tree View functionality

ProVision 2.5

Launched in Summer 2011

IPAM

- Added support from /16 to /128 for IPv6
- Custom field per Block (accessed via Admin Tab)
- Custom field per Site (accessed via Admin Tab)
- Detail page retains IP settings for multiple allocations
- Added VLAN tracking per block
- Added customizable email templates to Admin Tab
- Direct Assign auto subnets for v4 and v6
- Track blocks by Region

DNS

- DNSSEC support including DS key generation
- Added paste in forward IPv6 address to resolve IPv6 PTR while editing reverse zones

Peering

- Production release (version 1)
- Support for Cisco, Juniper, Foundry, Brocade

Platform

- Data importer (beta) - including DNS zones
- Updated Admin Tab functionality and layout
- Added permissions checks for working files/directories
- php 5.3.6 compatibility
- browser compatibility updates (various)

Coming Soon

Future Release Roadmap

7.4.0 Release

- Constraints
- Resource Lists Revamp
- DNS - Server Import (from Server Settings page)
- Updated Peering Templates
- Reporting - New reports including:
    - IP Runout report
    - DHCP Server report
    - DHCP Pool report
- Routing (DNS Jump Host Support)
- Server Scanning

7.x Release 3

- Backup v2
- RIR Audit/Lookup Tools
- ISC Kea Connector for DHCP
- VMware Connectors - ESX and vCenter
- Zone/Config push options (time zone per object, etc.)
- DDNS zone management enhancements for selected DNS platforms (as supported)
    - In some cases, zone records that are not actively queried may be candidates for removal. ProVision will query DNS platform(s) and display the zone record creation and last query information so that the DNS administrator can take action as needed.
- Zone query/access statistics for selected DNS platforms to be used/displayed in the DDNS zone management enhancements

2020 Big Roadmap Items - if you want these, let us know!

VMware NSX plugin - a few customers are managing VMware environments and would like to see some tighter integration of network provisioning. Initial discussions have been centered around a similar approach to our Neutron use case. ProVision would be able to natively assign IP blocks (subnet and host) for VMware's use. Additional integration would be DNS zone record updates (forward, reverse) to the DNS server specified in ProVision (the server could be physical, virtual, service, etc.). We also received a request for DHCP support that may also be explored so that all IP data stays centralized. We are assuming automation of SWIP/RIPE functions for IP data to help reduce provisioning times. - CURRENTLY IN CLOSED BETA

VMware ESX - Currently in Beta

VMware vCenter - Currently in Beta

Circuit Manager (includes provisioning support for Supported Connectors) - building on the UI updates in addition to the robustness of the Resource Manager in ProVision, we have received multiple requests to build a dedicated Circuit Management module for ProVision. This would allow physical and virtual circuits to be provisioned across datacenter endpoints. We are scoping this as a full module, so the user will be able to "build" a circuit in the UI and define the various endpoints, then ProVision will actually configure the circuit.

SolarWinds Connector - we are scoping this out on two fronts based on some requests - one is for an IPAM connector/importer, the other is integration of their monitoring data into ProVIsion and the Resource Manager. We are still scoping this out, but see this as a great use case for our Reverse API and functionally similar to the Observium integration we built earlier this year.

OpenStack Neutron plugin - we are scoping this out on a few fronts. We are trying to be flexible on the Neutron plugin side, and accommodate various SDN technologies. We are scoping a plugin that would allow users to selectively use ProVision IPAM, DNS or DHCP services along with the Resource Manager for whatever hierarchies are being deployed.

CloudFoundry plugin - Container technology is still maturing, but there are some simple functions that would be a big time savers. One example is DNS, the initial zone setup is manual and could be automated with a simple Connector. With IP data, there is a use case for using the message bus to track and log IP data history for services in a scalable way. Their use of IP data is a bit different, but without a clear use case (especially with IPv6) we would need to some more information.

Above is a list of road mapped features for our next release. The roadmap is highly flexible, and subject to change at any time (even during the release). We receive a regular volume of feature requests, and will often change the roadmap to include customer feature requests, rather than a scheduled roadmap feature or improvement.

ProVision Plugins

Please select the ProVision plugin that you would like more information for:

VMware vRealize Orchestrator Plugin

ProVision-vRA-Plugin

Current Plugin Release Version: 3.6.21

Overview

The IPAM Service provider consists of:

- Endpoint type definition which must be registered with vRealize Automation
- One or more endpoints that connect to a backend ProVision system
- Network profiles that are associated with endpoints

During a typical VM lifecycle, vRealize Automation calls the ProVision IPAM SDK API endpoints that must provide required data as a return value.

Requirements

6connect ProVision - requires ProVision 5.3 or above

VMware Compatibility - vRealize 7.1 or above

Functionality

Get Address Space

This workflow returns a list of resource entries (Section: Resource Holder, Category: Address Space) in the ProVision. Each tenant in the vRealize Automation can have one or more address space. The parent of all address spaces is a tenant root resource.

Category *Address Space* must be added on the ProVision server.

Get IP Ranges

Returns all the IP ranges that that are assigned to the selected address space. These IP Ranges are then assigned to the network profile. Further differentiation within all the ranges is done by specifying the search tags, passed via the custom properties as follows:

Property name	Scope	Example
Custom.ProVision.SearchTags.Global	All tenants	GlobalTag:1234
Custom.ProVision.SearchTags.Tenant	Tenant	TenantTag:Tenant1
Custom.ProVision.SearchTags.BusinessGroup	Business Group	BusinessTag:BG-A
Custom.ProVision.SearchTags.BluePrint	BluePrint	NetworkType:VM-1
Custom.ProVision.SearchTags.Mode	BluePrint	OVERRIDE

Table 1 IP Range filtering tags

All of the properties above are optional and can be combined in two ways (specified by the Mode property):

- MERGE: non-null properties from all levels are merged together when performing AIP queries
- OVERRIDE: properties defined at the lower level (Global -> Tenant -> Business Group -> Blueprint) override any value above them

The values of the properties can be static dynamic. For example there could be a drop down that would list meaningful names to the customers (Floor 1, Floor 2, etc) and this can be translated to ProVision tags via vRealize Action item (which can in turn get this information externally or from vRO configuration element).

Allocate IP address

Allocates one or more IP addresses based on the input properties and returns then to vRealize automation. IP range selection can be further narrowed down by using custom properties (previous Section).

Custom property *Scc.Vm.Orch.Network<nicIndex>.EnableDHCP* determines whether the allocation is DHCP or Static. In case of *Static* allocation, the IP address is allocated from the IP ranges satisfying the conditions in custom properties. The allocation process therefore follows this process:

1. User requests virtual machine in the vRealize Automation
2. During resource allocation process, vRealize Automation determines which network profile should be used when searching for IP address
3. By using network profile, vRealize Automation, determines which IP ranges are available for allocation and passes the info (along with any custom properties) to the *Allocate* workflow.
4. *Allocate* workflow accepts the parameters from the vRealize Automation and calls the ProVision REST API.
   Allocated IP addresses are tagged with a NIC tag, indicating the index of the Network Interface Card that IP address is allocated to. For example by default, NIC index is prefixed with **NIC:** giving the tags **NIC:0,NIC:1, etc.** Tags are created automatically on the fly. The NIC prefix is defined in *ProVision Settings* configuration element field *NICTagPrefix.*

If allocation on ProVision system is successful, workflow returns the allocated IP addresses to vRealize Automation (along with the additional information, see Table 2.

1. If *Scc.Vm.Orch.Network<nicIndex>.EnableDHCP* is true, the address, static binding is also created.
2. If the requested NIC index is that of the default interface (default:0) and the *DNSZoneId* is configured in tenant settings, the DNS A record is also pushed to this zone. For the value of DNS A record, the vmName is used.
3. vRealize Automation configures returned IP addresses and makes configuration changes on the VM

Property	Description
SubnetPrefixLength	Obtained from IP range
Gateway	Obtained from IP range, /32 address tagged as gateway (Tag name configurable)
PrimaryDNS	Provided by custom properties
SecondaryDNS	

Table 2 Additional allocation information

Property name	Scope	Example
VirtualMachine.Network.Network#.DNSSuffix	BluePrint	demo.local
VirtualMachine.Network.Network#.PrimaryDNS	BluePrint	10.200.1.11
VirtualMachine.Network.Network#.SecondaryDNS	BluePrint	10.200.1.12
VirtualMachine.Network.Network#.PrimaryWINS	BluePrint	10.1.3.1
VirtualMachine.Network.Network#.SecondaryWINS	BluePrint	10.1.3.2
VirtualMachine.Network.Network#.DNSSearchSuffixes	BluePrint	demo.local, demo2.local
VirtualMachine.Network.Network#. dhcpStaticRoutes121	BluePrint	[{“key”:”10.1.0.0”,”value”: “10.1.0.1”},…]
VirtualMachine.Network.Network#. interfaceMTU26	BluePrint	1500
VirtualMachine.Network.Network#. startDate67	BluePrint	1/1/1900
VirtualMachine.Network.Network#. tftpServerName66	BluePrint	Tftp1
VirtualMachine.Network.Network#. tftpServerAddresses150	BluePrint	[“10.1.1.1”,,”10.1.1.2”]
VirtualMachine.Network.Network#.nextServer	BluePrint	1.1.2.3
VirtualMachine.Network.Network#.autconfigureDNS	BluePrint	true or false
VirtualMachine.Network.Network#.leaseTime	BluePrint	86400
Custom.ProVision.SkipHolding	BluePrint	true

Release IP address

Workflow *Release* is called when vRealize Automation deprovisions the virtual machine. Workflow accepts the IP address that needs to be released and returns it to the free IP Range. Property *Custom.ProVision.SkipHolding* specifies whether IP address should be released immediately (value 'true') or put in a holding tank (undefined/empty or 'false').

If the requested NIC index is that of the default interface (default:0) and the *DNSZoneId* is configured in tenant settings, the corresponding DNS A record is also removed from this zone.

Installation

Please contact 6connect and you will then be able to download the plugin. Once downloaded, import the plugin into vRealize Orchestrator.

1.1. Create REST Host for ProVision in vRealize Orchestrator

First, the API endpoint for the ProVision server needs to be created in vRealize Orchestrator. This is performed by executing the *Add a REST Host* workflows in the *Library/HTTP-REST/Configuration* folder.




Figure 1 Add a REST Host

In the first step fill in the name and the URL of the API endpoint. URL can be one of the following:

- Cloud instance: https://cloud.6connect.com/<tenantId>/api/v1/api.php?
- Local instance: https://provision.example.com/api/v1/api.php?

1.2. Register ProVision IPAM Endpoint type

In order to be able to create ProVision endpoints, the IPAM Endpoint type needs to be registered in vRrealize Automation. This is performed by running the *Add/Update 6Connect IPAM Endpoint* workflow located in the *6Connect/IPAM Service Provider/Configuration* folder.

This operation essentially connects the vRA actions described in paragraph Provision IPAM Service Provider with the corresponding workflows in the vRO.

In the vRA step of the workflow, the vRA server and credentials need to be entered as shown in Figure 2. Credentials entered must have sufficient permissions on the vRA server. This should normally be *administrator@vsphere.local* if default values were used at installation (SSO Default tenant password).




Figure 2 Register 6Connect IPAM Type

After this is done, new category will appear in the vRA when creating endpoints.

1.3. Create endpoint

ProVision endpoint can also be created from vRealize Automation web interface, but since custom property is used to specify REST host, it is simpler to use the workflow *Add/Update 6Connect IPAM Endpoint*.

In the *Common parameters* step, *tenantId* parameter needs to be entered. This must be the same value as tenant URL value of the corresponding tenant in vRA.




Figure 3 Tenant for IPAM endpoint

In the *vRA* step of *Add/Update 6Connect IPAM Endpoint* workflow, same information needs to be entered as in Figure 2.




Figure 4 Adding IPAM Endpoint: Provision API data

In the third step (Figure 3), ProVision API data must be provided:

- ProVision API Rest HOST: select the REST Host created in 4.1.

Endpoint name is automatically generated in the followin form: *Provision:<tenantId>*

After successfully execution, the ProVision endpoint is created in vRealize Automation and with the following custom property:

- Custom.ProVision.RestHOSTId: value contains the GUID of the ProVision REST Host that was selected. This tells the workflows on which ProVision server to execute API calls
- Custom.ProVision.TenantId: contains the tenant to which the endpoint belongs.

1.4. vRO Configuration (ProVision)

vRO configuration is stored in the cofiguration element object which can be accessed by selecting *Configurations* tab in the vRealize Orchestrator client. Configuration element is located in *Settings/ProVision Settings.*

Attribute name	Type	Default value	Description
ApiKey	String		Value ApiKey for the ProVision API
ApiSecret	String		Value of ApiSecret for the ProVision API
restHost	RESTHost		REST host for accessing the ProVision API (default)
skipHolding	Boolean	True	Global skip holding setting when releasing the IP address
Credentials	Array		Array of [RestHost, ApiKey, ApiSecret] for multi ProVision environments
AddressSpacesCategorySlug	String	customer	Resource entries category for Address Spaces in the vRealize Automation
AddressSpaceSectionSlug	String	resource-holder	Resource entries section for Address Spaces in the vRealize Automation
VirtualMachineSectionSlug	String	virtual-machine	Section in which the virtual machine resource is created
GatewayTag	String	Gateway	Tag that indicates a gateway IP address

NICTagPrefix	String	NIC:	Tag Prefix for NIC that block is assigned to (NIC Index is appended to this)
tenantSettingsPath	String	Settings /TenantSettings	Location where to store tenant settings
AggregateCategorySlug	String	aggregate	Aggregate category slug
AddressSpaceReservationTag	String	VRA:AS-Reserved	Tag to mark the address space IP blocks
AddressSpaceCategoryName	String	Address Space	The name of the address space category
AggregateCategoryName	String	Aggregate	The name of the aggregate category
TenantRootCategorySlug	String	customer	Tenant root resource category
TenantRootSectionSlug	String	resource-holder	Section of tenant root
TenantRootResourceType	String	entry	Resource type for tenant root
AggregateSectionSlug	String	resource-holder	Aggregate section
AggregateResourceType	String	entry	Aggregate resource type
nsxConfigurationElementPath	String	Settings	Path to the nsx configuration element
nsxConfigurationElementName	String	nsx-configuration-default	Name of the nsx configuration element
dhcpEnablerPropertyName	String	Scc.Vm.Orch.Network	VM property prefix for DHCP enabled property
MaxRetries	Number	3	Maximum number of retries of failed API calls
retrySleepTime	Number	3	Sleep time between API call retries

Section 1.0 ProVision Setup

The process of setting up the tenant, tenant aggregates, address spaces and ip blocks assignment is fully automated through the workflows described below.

1.1. Initial ProVision Setup

Before new tenants can be provisioned in ProVision, basic configuration workflows need to be executed once per ProVision server and vRO environment.

1.1.1.Tagging the ProVision settings element

In order to simplify searching for the ProVision settings configuration element, the following global tags are added to it:

- CONFIGURATION-SYSTEM:PROVISION
- CONFIGURATION-TYPE:GLOBAL

Execute workflow ***OrchTagConfiguration*** once per vRO server when performing upgrade existing plugin installation. The workflow will do nothing if tags are already present.

1.1.2.Creating required ProVision objects

In order for multitenancy to function properly, several object need to exist before tenants can be onboarded. This includes:

- Aggregate resource category
- Address space resource category
- Gateway tag

Execute workflow ***OrchProVisionBaseConfiguration*** once per ProVision server. If required object are already present, the workflow will do nothing.

1.2. Create New Tenant

Workflow ***OrchCreateNewTenant*** creates the following objects on ProVision:

- TenantRoot resource named <tenantId>
- TenantAggregates resource named <tenantId>-aggregates

Workflow checks if objects above already exist before creating new ones. Workflow creates a configuration element under *Settings /TenantSettings: TenantSettings-<tenantId>* and adds the following attributes to it:

- TenantId
- RestHostId: RestHostId of the ProVision server for tenant
- TenantRootResourceId: Resource id of the TenantRoot resource on ProVision server
- TenantAggregateResourceId: Resource id of the TenantAggregates resource on the ProVision server
- EndpointId: endpoint name that is created for this tenant
- DNSZoneId: DNS zone id (internal Id of ProVision DNS zone – visible in URL as zoneId query parameter)




Figure 5 Create New Tenant input form

The ***OrchCreateNewTenant*** can be repeatedly executed with new input values. If the tenant with the same id already exists, it will update the values for *RestHostId*, *DNSZoneId.* Any ProVision object that already exists will be left intact.

1.3. Add Aggregate To Tenant

Workflow *OrchAddAggregateToTenant* adds new aggregate to a tenant.




Figure 6 Add Aggregate To Tenant

Worflows performs the following:

- Creates specified aggregate block.

- Assigns it to *TenantAggregate* resource.
- If allow duplicates is set to Yes, it creates aggregate even if the same block already exists (same or other tenant)
- If allow duplicates is set to No, it will skip creation if duplicate is detected in same tenant, otherwise it will report error.

1.4. Create Address Space And Assign Block

Workflow ***OrchCreateAddressSpaceAndAssignBlock*** creates new address space resource and then assigns specified block to it. If the address space with the same name already exists, new address block is added to it. This workflow is a composite of the workflows ***OrchCreateAddressSpace*** and ***OrchAssignBlockToAddressSpace*** which are called in a sequence. They can also be called separately, depending on requirements.




Figure 7 OrchCreateAddressSpaceAndAssignBlock step 1

In step 1 of the ***OrchCreateAddressSpaceAndAssignBlock*****,** network parameters are specified:

- tenantId
- Tags to filter: a list of tags by which to filter aggregates dropdown
- Aggregates from which to assign
- IPNetwork: IP network to assign
  IP network can be empty, in which case the new network is allocated from a pool of available blocks of a given size (mask)
- Mask: size of the network
- Gateway: Default getway for a given block.
  Gateway can be specified as
  - IP address literal (e.g. 10.2.1.1) – only if IPNetwork parameter is specified
  - IP address index: Ordinal number of the ip address in a give block size (e.g. IPNetwork = 10.1.1.0/24 and gateway = 65 gives gateway address of 10.1.1.65)
  - edgeId: Edge id for DHCP reservation (NSX DLR)




Figure 8 OrchCreateAddressSpaceAndAssignBlock step 2

In step 2, DNS parameters are specified. These values are stored in the allocated IP block and are returned to vRA when *Allocate* is requested. These values can be overridden for each vNIC separately by values of the following properties:

- VirtualMachine.Network.Network#.DNSSuffix
- VirtualMachine.Network.Network#.PrimaryDNS
- VirtualMachine.Network.Network#.SecondaryDNS
- VirtualMachine.Network.Network#.PrimaryWINS
- VirtualMachine.Network.Network#.SecondaryWINS
- VirtualMachine.Network.Network#.DNSSearchSuffixes

If any of these values are not present, the value from IP block is used as a default.

In step 3, additional DHCP options can be specified in form of key-value pairs.

1.5. Delete Address Space

Workflow ***OrchDeleteAddressSpace*** removes address space and releases all of its blocks back to aggregate.




Figure 9 Delete Address Space

- tenantId
- Address Space which to remove: drop down list displays all the address spaces of the specified tenant
- Address Space Id: Address space resource id can also be specified if running in none interactive mode
- Address Space Slug: Address space alphanumeric Id. This is an Id of ***addressSpaceExternalId*** property of the address space on the vRA networkProfile.
- Ignore any leftover assignments and release addresses: If set to ***Yes***, any assigned IP addresses are unassigned before removing address space. If set to No and there are still IP addresses assigned (apart from network address, broadcast address and gateway), the workflow throws an error

When IP blocks are removed, the reaggregation is performed up to maximum blocksize possible.

1.6. Remove IP Block From Address Space

Workflow ***OrchRemoveIPBlockFromAddressSpace*** unassigns a single IP block from address space and releases it back to parent aggregate. Reaggregation is performed up to a maximum possible block size.




Figure 10 Remove IP Block From Address Space

- tenantId
- Address space from which to remove: A drop down list displays all of tenant address blocks
- IPNetwork: A drop down list displays all IP blocks that are assigned to selected address space
- AddressSpaceId: address space resource id (for non-interactive execution)
- Address BlockId: address block id (for non-interactive execution)
- Ignore any leftover assignments and release addresses: If set to ***Yes***, address block is aggregated regardless of assignments. If set to No and there are still IP addresses assigned (apart from network address, broadcast address and gateway), the workflow throws an error

1.7. Remove Aggregate From Tenant

Workflow ***OrchRemoveAggregateFromTenant*** removes an aggregate from a tenant.




Figure 11 Remove Aggregate From Tenant

- tenantId
- Aggregate to remove: a drop down list display a list of tenant aggregates
- Aggregate Id: aggregate block id (for non-interactive execution)
- Ignore any leftover assignments and release addresses: If set to ***Yes***, aggregate is deleted regardless of assignments. If set to No and there are still IP blocks assigned the workflow throws an error

1.8. Delete Tenant

Workflow ***OrchDeleteTenant*** removes tenant resources from the ProVision server.




Figure 12 Delete Tenant

- tenantId
- Ignore assigned resources: If set to ***Yes***, tenant is deleted regardless of assignments. If set to No and there are still IP blocks assigned the workflow throws an error.

Workflow tags a configuration element under *Settings/TenantSettings: TenantSettings-<tenantId>* with new tag value: CONFIGURATION-STATUS:DELETED

Section 2.0 vRealize Automation Setup

This section summarizes which custom properties and property groups need to be created in vRealize Automation. In order to simplify creation of properties, they are provided in a form of *.zip* files that can be imported with the help of cloud client application (https://code.vmware.com/tool/cloudclient/4.1.0)

Cloud client is a java CLI application that is started with the following command :

```
cloudclient.bat (or cloudclient.sh if running on Linux)
```

In order to login to the vRA server execute the following command from cloud client CLI:

```
vra login userpass --tenant <tenant>
```

To import the .zip file, execute the following:

```
vra content import --path <path to zip file> --resolution OVERWRITE --precheck ON
```

2.1. Custom properties

Properties are optional component that needs to be created if more granular selection of IP ranges is needed within one address space (base on the Tenant, BusinessGroup). In the simple scenario, where one address space contains one IP range they are normally not needed. In order for properties to take place, they need to be attached to the blueprint.

The following properties need to be created in *Administration -> Property dictionary -> Property definitions:*

- Custom.ProVision.SearchTags.Global
- Custom.ProVision.SearchTags.Tenant
- Custom.ProVision.SearchTags.BluePrint
- Custom.ProVision.SearchTags.Mode
- Custom.ProVision.SearchTags.Tenant
- Custom.ProVision.SkipHolding

2.2. Property groups

The following properties need to be created in *Administration -> Property dictionary -> Property groups:*

- CustomProVisionTenantPropertyGroup

2.3. Business group properties

The following property must be created on any business group within tenant: *Administration -> Users&Groups -> Business Groups:*

- Custom.ProVision.SearchTags.BusinessGroup

2.4. DHCP Subscriptions

DCHP subscription workflows are used to push the DHCP information on NSX during the VM provisioning phase. There are two subscription workflows for this purpose:

- OrchDHCPSubscriptionAllocate
    - Triggered in phase ‘EVENT’ and Life Cycle Event: ‘CloneWorkflow.CloneMachine.EVENT.OnCloneMachineComplete’ when MAC address becomes known
    - Pushes the IP address and DHCP options for each NIC that is DHCP enabled
    - DHCP enabled NIC must have property ‘Scc.Vm.Orch.Network#.EnableDHCP’ set to ‘true’
    - OrchDHCPSubscriptionRelease
        - Triggered in phase ‘PRE’, state ‘VMPSMasterWorkflow32.Disposing’
        - Removes the DHCP binding for all DHCP enabled NICs

DHCP Subscriptions need to be imported for each tenant separately. Run the *6Connect/Operations/OrchDHCPSubscriptionImporter* workflow and provide a *tenantId* as a parameter.

The workflow will automatically read the subscriptions stored in *6Connect-subscriptions/dhcp-subscriptions* resource element and import them into vRA.